
CONTROLLER GUIDE | STEP 1 OF 9

Prepare one controller VM



Give this picture to your server team. These are starting allocations for 20 servers.

Start with a dedicated Linux VM. The installer detects the OS and installs missing Python, Docker Engine and Compose dependencies automatically. Keep approved package and image downloads available.


Use RHEL 9 or Ubuntu 26.04. Keep SELinux enabled. Reserve UID/GID 10001 for the dedicated application account.

No dependency commands or .env editing. Your server team supplies the VM, network and verified extracted release. Run one installer command, then finish in your browser. Native OS and DC tests remain pending.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 2 OF 9

Make three connections available



These are destination TCP ports. Allow return traffic and restrict access to approved networks.


Ask the network team for a fixed IP, a stable name, correct time and trusted HTTPS. The installer needs approved image/package download access; this is not an offline installer.

The installer does not open host firewall ports. Keep backend, database and cluster ports private. An approved load balancer can provide different public URLs.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 3 OF 9

Run the controller installer



Installation illustration. Your server address and progress messages will differ.

The same command works on both supported operating systems. Existing compatible Docker is reused. Conflicting container stacks stop installation for review; they are not removed.

Ask your release/server team for prthak-controller-0.17.0.tar.gz. They must verify its signature, copy it privately and extract it into a protected root-owned folder using independently approved release trust.

Open Terminal in that extracted folder. Paste the command below. If sudo asks for your Linux password, type it and press Enter; the password does not appear on screen.

Paste this command and press Enter

```
sudo ./scripts/install-controller.sh
```

Wait for installation to finish. Keep the HTTPS setup URL that it prints. Do not create or edit an .env file.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 4 OF 9

Sign in and change the password




Illustration of the current login fields. This is not a live installation screenshot.

Open the exact HTTPS URL printed by the installer. Your server team must confirm the certificate identity before you enter credentials.


A fresh installation uses admin / admin. Replace the password with 12 to 256 characters before entering the workspace. Existing installations keep their existing users.

The built-in admin cannot be deleted, disabled, renamed or demoted. Its password can be changed or reset.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 5 OF 9

Finish the platform settings



SYNTHETIC PREVIEW · Current v0.17 synthetic preview. An installed controller enables its supported setup actions.

Click Platform settings → Setup. Use Site & cluster settings for this node, then HTTPS certificates to prepare the permanent application name and approved certificate.


Use the Storage tab for the data location. Default: /var/lib/prthak. Mount storage first; moving active data uses the reviewed GUI operation.

Leave workers on AUTO. Start with one standalone node. It runs the controller/router with SQLite; PostgreSQL HA is a separate three-voter setup stage.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 6 OF 9

Choose who may use the app



Local accounts and configured organisation sign-in use the same three roles.

Click Users & access. As Super Admin, add the named people who will use Prṛthak and select their role.


You may start with local accounts. Configure optional SAML here, or Microsoft Entra through Platform settings → Setup. SSO needs your identity team and explicitly provisioned users.

Users change their own local password through the top-right account menu. Only Super Admin manages other users and roles.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 7 OF 9

Set the update interval



SYNTHETIC PREVIEW · Current synthetic preview. Desired settings are separate from an agent receipt showing they were applied.

Click Platform settings → Agent polling. Start with 30 seconds for policy control and 900 seconds for the full inventory fallback.


Preview affected servers, save the settings, then check their applied polling status. Later you can change the whole fleet or selected groups/tags here.

Agents pull new policies automatically. Polling includes timing variation and network work; a saved setting is not a guaranteed completion time.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 8 OF 9

Confirm the dashboard is ready



SYNTHETIC PREVIEW · Current synthetic preview. A fresh installation should show your own records, not these example servers.

Check: trusted HTTPS opens, your new password works, and controller readiness is healthy. Keep the printed URL and the new password in your approved records.

Next: create your real locations in Locations, then follow the separate Agent installation guide. Servers appear after installation and their first authenticated report.


Create a backup schedule in Platform settings → Backups. Back up private trust/identity material separately as required by the recovery procedure.

An empty server list is normal before agents connect. Do not add example records to make the dashboard look populated.

© 2026 Airtel Payments Bank. All rights reserved.

CONTROLLER GUIDE | STEP 9 OF 9

If something does not work



Take the error message to your server team. Do not disable security checks to make an install continue.

No dashboard? Ask the server team to check installation completion, Docker, the address, HTTPS trust and TCP 8787 access.

Dependency error? Check approved package access, available space and any existing container stack. Keep the exact error for your server team. The installer does not remove conflicting packages.

This guide explains the current code and GUI. Your native RHEL/Ubuntu validation, actual 20-server pilot and DC/DR tests remain separate deployment work.

© 2026 Airtel Payments Bank. All rights reserved.

TRANSFER SHEET | BEFORE STEP 3

Optional: copy the approved release

Your release administrator supplies and verifies prthak-controller-0.17.0.tar.gz using independently trusted release identity. A source ZIP is not the installation archive. An approved graphical file-transfer tool can copy it to your Linux home folder.

On your laptop - replace the path, user and address

```
scp /PATH/TO/prthak-controller-0.17.0.tar.gz \
  YOUR_USER@CONTROLLER_IP:
```

Open the controller terminal

```
ssh YOUR_USER@CONTROLLER_IP
```

Extract the verified archive into a protected release folder

```
sudo install -d -o root -g root -m 0755 /opt/prthak/releases
sudo tar --no-same-owner --no-same-permissions \
  -xzf "$HOME/prthak-controller-0.17.0.tar.gz" \
  -C /opt/prthak/releases
cd /opt/prthak/releases/prthak-controller-0.17.0
```

Now run the one installer command in Step 3. It prepares missing dependencies automatically. Root/sudo, systemd and working approved repositories are required. No Git or manual .env file is needed.

© 2026 Airtel Payments Bank. All rights reserved.

REFERENCE SHEET | CPU, MEMORY AND COMPLETION

Plan capacity and confirm installation

20-server pilot: start with 4 vCPU, 8 GiB RAM, 80 GiB OS/Docker disk and a separate 100 GiB data SSD. These are VM allocations, not constant CPU or memory consumption.

5,000 servers: begin with 8 vCPU / 16 GiB per management-only controller. A combined database voter starts at 8 vCPU / 32 GiB, 80 GiB OS/Docker and 300 GiB data SSD. Managed database HA needs three eligible voters and real fencing.

Actual utilization depends on policy size, discovery, traffic learning, retention and site latency. The previous 0.16 capacity benchmark is historical evidence; these new installers do not create a fresh 5,000-server performance measurement.

Optional read-only checks - ask your server team if needed

```
sudo systemctl status prthak-appliance-manager.service --no-pager
sudo docker ps
```

GUI completion: trusted HTTPS opens, the temporary password was changed, and controller readiness is healthy. Then install the first agent and confirm its heartbeat before the rest of the pilot.

Native OS, live firewalld/rollback, DC/DR and actual pilot acceptance remain pending. See the detailed VM and capacity runbooks for connection budgeting and failover sizing.

© 2026 Airtel Payments Bank. All rights reserved.