

# VTP & NAT

Jirasak Sittigorn

Internetworking Standards & Technologies

Department of Computer Engineering, Faculty of Engineering  
King Mongkut's Institute of Technology Ladkrabang

Cisco Networking Academy®  
Mind Wide Open!

## VTP (VLAN Trunking Protocol)

- VTP is a messaging protocol that uses Layer 2 trunk frames to manage the addition, deletion, and renaming of VLAN on a single domain.
- VTP messages are encapsulated in either Cisco proprietary ISL or IEEE 802.1Q protocol frames and then passed across trunk links to other devices.
- NOTE: before creating VLANs on the switch, you must first set up a VTP management domain



## • VTP (VLAN Trunking Protocol)

- Benefits of VTP
- VTP Operation
- VTP configuration
- Adding a switch to an existing VTP domain
- VTP Pruning

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMUTT

2

## Benefits of VTP

- Before discussing VTP, it is important to understand that VTP is not necessary in order to configure VLANs or Trunking on Cisco Switches.
- VTP is a Cisco proprietary protocol that allows VLAN configuration to be consistently maintained across a common administrative domain.
- VTP minimizes the possible configuration inconsistencies that arise when changes are made.
- Additionally, VTP reduces the complexity of managing and monitoring VLAN networks, allowing changes on one switch to be propagated to other switches via VTP.
- On most Cisco switches, VTP is running and has certain defaults already configured.

# VTP Operation

- VTP advertisements are transmitted out all trunk connections, including ISL, IEEE 802.1Q, IEEE 802.10, and ATM LANE trunks.
- A critical parameter governing VTP function is the VTP configuration revision number.  
This 32-bit number indicates the particular revision of a VTP configuration.
- A configuration revision number starts at 0 and increments by 1 with each modification until it reaches **4294927295**, at which point it recycles back to 0 and starts incrementing again.  
*config# Domain name*
- Each VTP device tracks its own VTP configuration revision number VTP packets contain the sender's VTP configuration number.
- This information determines whether the received information is more recent than the current version.
- If the switch receives a VTP advertisement over a trunk link, it inherits the VTP domain name and configuration revision number.
- The switch ignores advertisements that have a different VTP domain name or an earlier configuration revision number.

# VTP Operation

- VTP switches operate in one of three modes:

- Server
- Client
- Transparent

Feature	Server	Client	Transparent
Source VTP Messages	Yes	Yes	No
Listen to VTP Messages	Yes	Yes	No
Create VLANs	Yes	No	Yes* <small>(RAM Local VLANs)</small>
Remember VLANs	Yes	No	Yes*

\*Locally Significant only

หมายความว่า

ที่เก็บอยู่ใน RAM = ต้องห้าม

- VTP servers can create, modify, delete VLAN and VLAN configuration parameters for the entire domain, and save VLAN configuration information in Catalyst NVRAM, and send VTP messages out to all trunk ports.

↓  
↓  
↓  
↓  
↓  
↓

Feature	Server	Client	Transparent
Source VTP Messages	Yes	Yes	No
Listen to VTP Messages	Yes	Yes	No
Create VLANs	Yes	No	Yes*
Remember VLANs	Yes	No	Yes*

\*Locally Significant only

- VTP clients cannot create, modify, or delete VLAN information.
- The only role of VTP clients is to process VLAN changes and send VTP messages out all trunk ports.
- The VTP client maintains a full list of all VLANs within the VTP domain, but it does not store the information in NVRAM.
- VTP clients behave the same way as VTP servers, but it is not possible to create, change, or delete VLANs on a VTP client.
- Any changes made must be received from a VTP server advertisement.

↓  
↓  
↓  
↓  
↓  
↓

Feature	Server	Client	Transparent
Source VTP Messages	Yes	Yes	No
Listen to VTP Messages	Yes	Yes	No
Create VLANs	Yes	No	Yes*
Remember VLANs	Yes	No	Yes*


\*Locally Significant only

- Switches in VTP transparent mode forward VTP advertisements but ignore information contained in the message.
- A transparent switch will not modify its database when updates are received, nor will the switch send out an update indicating a change in its own VLAN status.
- Except for forwarding VTP advertisements, VTP is disabled on a transparent switch.
- There is also an "off" VTP mode in which switches behave the same as in the VTP transparent mode, except VTP advertisements are not forwarded.

↓  
↓  
↓  
↓  
↓  
↓

# VTP configuration

- VTP can be configured by using these configuration modes.
  - VTP Configuration in global configuration mode ✓
  - VTP Configuration in VLAN configuration mode ✗
- VLAN configuration mode is accessed by entering the **vlan database** privileged EXEC command.



## VTP configuration - Version

VTP Configuration in global configuration mode:

```
Switch#config terminal  
Switch(config)#vtp version 2
```

VTP Configuration in VLAN configuration mode:

```
Switch#vlan database  
Switch(vlan)#vtp v2-mode
```

- Two different versions of VTP can run in the management domain, VTP Version 1 and VTP Version 2. Two versions are not interoperable.
- The two versions are not interoperable in the same VTP domain.
- The major difference between the two versions is version 2 introduces support for Token Ring VLANs.
- If all switches in a VTP domain can run VTP Version 2, version 2 only needs to be enabled on one VTP server switch, which propagates it to other VTP switches in the VTP domain.
- Version 2 should not be enabled unless every switch in the VTP domain supports version 2.

# VTP configuration

Step 0 : set Trunk → ~~initial set sw in trunk~~

- Step 1: Determine the version number of VTP that will be utilized.
- Step 2: Decide if this switch is to be a member of an existing management domain or if a new domain should be created. If a management domain does exist, determine the name and password of the domain.
- Step 3: Choose a VTP mode for the domain.

## ② VTP configuration - Domain and Password

VTP Configuration in global configuration mode:

```
Switch#config terminal  
Switch(config)#vtp domain cisco  
Switch(config)#vtp password mypassword
```

VTP Configuration in VLAN configuration mode:

```
Switch#vlan database  
Switch(vlan)#vtp domain cisco  
Switch(vlan)#vtp password mypassword
```

- The domain name can be between 1 and 32 characters.
- The optional password must be between 8 and 64 characters long.
- If the switch being installed is the first switch in the network, the management domain will need to be created.
- However, if the network has other switches running VTP, then the new switch will join an existing management domain.
- Caution: The domain name and password are case sensitive.

## VTP configuration - Domain and Password

VTP Configuration in global configuration mode:

```
Switch#config terminal
Switch(config)#vtp domain cisco
Switch(config)#vtp password mypassword
```

VTP Configuration in VLAN configuration mode:

```
Switch#vlan database
Switch(vlan)#vtp domain cisco
Switch(vlan)#vtp password mypassword
```

- By default, management domains are set to a nonsecure mode, meaning that the switches interact without using a password.
- Adding a password automatically sets the management domain to secure mode.
- The same password must be configured on every switch in the management domain to use secure mode.

## VTP configuration - VTP mode

VTP Configuration in global configuration mode:

```
Switch#config terminal
Switch(config)#vtp mode server /client /transparent
```

VTP Configuration in VLAN configuration mode:

```
Switch#vlan database
Switch(vlan)#vtp server
```

Feature	Server	Client	Transparent
Source VTP Messages	Yes	Yes	No
Listen to VTP Messages	Yes	Yes	No
Create VLANs	Yes	No	Yes*
Remember VLANs	Yes	No	Yes*

\*Locally Significant only

Switch#config terminal

Switch(config)#vtp mode [client|server|transparent]

Switch#vlan database

Switch(vlan)#vtp [client|server|transparent]

## VTP Configuration - Overview

- VTP Configuration in global configuration mode:

```
Switch#config terminal
Switch(config)#vtp version 2
Switch(config)#vtp mode server
Switch(config)#vtp domain cisco
Switch(config)#vtp password mypassword
```



✓

- VTP Configuration in VLAN configuration mode:

```
Switch#vlan database
Switch(vlan)#vtp v2-mode
Switch(vlan)#vtp server
Switch(vlan)#vtp domain cisco
Switch(vlan)#vtp password mypassword
```



## Verifying VTP

- This command is used to verify VTP configuration settings on a Cisco IOS command-based switch.

```
Switch#show vtp status
VTP Version :2
Configuration Revision :2
Maximum VLANs supported locally :68
Number of existing VLANs :6
VTP Operating Mode :Client
VTP Domain Name :cisco
VTP Pruning Mode :Disabled
VTP v2 Mode :Enabled
VTP Traps Generation :Disabled
MD5 digest :0x35 0x84 0x7B 0x04 0x3D
               0x55 0x3B 0xDA
Configuration last modified by 0.0.0.0 at 10-5-00 20:33:41
Switch#
```

Step 0: int switchport mode trunk

set v  
switchport {  
Step 1: VTP version e  
Step 2: VTP domain limit  
Step 3: ~~VTP~~ password cna  
Verify      Show VTP status      ~~ໃຫ້ອຳນວຍ VTP~~ ~~ອີງrunning config~~ ~~ທີ່ໄດ້~~  
Step 4: VTP mode ...

Step 5 : Config VLAN ~~ເກີດສິນລຸ່ມ (mode vtp server)~~ ກ່ອງໃຈສະໜັບສະໜູນ "ໃຫ້ " transparent"

Vlan \_\_\_\_\_

name \_\_\_\_\_

## Verifying VTP

- This command is used to display statistics about advertisements sent and received on the switch.

```
MDF_Switch#show vtp counters
```

VTP statistics:

Summary advertisements received	:4
Subset advertisements received	:1
Request advertisements received	:2
Summary advertisements transmitted	:7
Subset advertisements transmitted	:4
Request advertisements transmitted	:1
Number of config revision errors	:0
Number of config digest errors	:0
Number of V1 summary errors	:0

## Adding a switch to an existing VTP domain

- Clear the configuration
- Clear the VTP file
- Power cycle the switch
- Configure VTP mode and domain
- Password protect the domain

- Use caution when inserting a new switch into an existing domain.
- In order to prepare a switch to enter an existing VTP domain, perform the following steps.
  - Delete the VLAN database, erase the startup configuration, and power cycle the switch.
  - This will avoid potential problems resulting from residual VLAN configurations or adding a switch with a higher VTP configuration revision number that could result in the propagation of incorrect VLAN information.
  - From the privileged mode, issue the **delete vlan.dat** and **erase startup-config** commands, then power cycle the switch.

## VTP Pruning

- VTP pruning enhances network bandwidth use by reducing unnecessary flooding of traffic, such as broadcast, multicast, unknown, and flooded unicast packets, by default, VTP pruning is disabled.
- VLAN 1 (default) is always pruning ineligible.

```
Switch(vlan)#vtp pruning
To make specific VLANs pruning ineligible
Switch(config)#interface fastethernet 0/3
Switch(config-if)#switchport trunk pruning vlan
remove vlan-id
```

බඳ න්‍යුත් සේවක ත්‍රිත්වය

## NAT OPERATION

### • NAT Characteristics

- IPv4 Private Address Space
- What is NAT?
- NAT Terminology
- How NAT Works

### • Types of NAT ත්‍රිත්ව

- Static NAT
- Dynamic NAT
- Port Address Translation (PAT) තෙමැත්ත් පිළිවාන් Cisco'න PAT
- Comparing NAT and PAT


### • Benefits of NAT

- Benefits of NAT
- Disadvantages of NAT

# NAT Characteristics


- IPv4 Private Address Space

- The IPv4 address space is not big enough to uniquely address all the devices that need to be connected to the Internet
- Network private addresses are described in **RFC 1918** and are designed to be used within an organization or site only
- Private addresses are not routed by Internet routers while public addresses are
- Private addresses can alleviate IPv4 scarcity but since they aren't routed by Internet devices, they need to be translated first.
- NAT is process used to perform such translation



# NAT Characteristics

- What is NAT?




# NAT Characteristics

- **NAT Terminology**

- In NAT terminology, inside network is the set of devices using private addresses. Outside networks are all other networks


- NAT includes 4 types of addresses:

- Inside local address
- Inside global address
- Outside local address
- Outside global address




# NAT Operation

- NAT Terminology



# NAT Characteristics

- How NAT Works



# Types of NAT

- Static NAT


map [ip addr map | ip addr]

Chalkboard notes:

- Static NAT uses a one-to-one mapping of local and global addresses
- These mappings are configured by the network administrator and remain constant
- Static NAT is particularly useful when servers hosted in the inside network must be accessible from the outside network
- A network administrator can SSH to a server in the inside network by pointing his SSH client to the proper inside global address

- Static NAT

Static NAT Table	
Inside Local Address	Inside Global Address - Addresses reachable via R2
192.168.10.10	209.165.200.226
192.168.10.11	209.165.200.227
192.168.10.12	209.165.200.228



# Types of NAT

- Dynamic NAT

1 IP map 1 IP

ມີ້ນອາກອນດີ ມີ້ນໄຟລົມຕະຫຼາມ → ດີວຽກທີ່ໃຫ້ມີ້ນໄຟລົມຕະຫຼາມ

- Dynamic NAT uses a pool of public addresses and assigns them on a first-come, first-served basis
- When an inside device requests access to an outside network, dynamic NAT assigns an available public IPv4 address from the pool
- Dynamic NAT requires that enough public addresses are available to satisfy the total number of simultaneous user sessions

ມີ້ນໄຟລົມ


# Types of NAT

ມີ້ນ ມາພ ອາກອນ ທີ່ນ ນັ້ນ ດີວຽກ  
ທີ່ນ ນັ້ນ ນິຕິ ນິຕິ ນິຕິ

- Dynamic NAT

Dynamic NAT

Dynamic NAT	
Inside Local Address	Inside Global Address Pool - Addresses reachable via R2
192.168.10.12	209.165.200.226
Available	209.165.200.227
Available	209.165.200.228
Available	209.165.200.229
Available	209.165.200.230



# Types of NAT

- Port Address Translation NAT (PAT)

ມີ້ນ ປະເປີຕິ ພຣັກ

- PAT maps multiple private IPv4 addresses to a single public IPv4 address or a few addresses
- PAT uses the pair source port and source IP address to keep track of what traffic belongs to what internal client
- PAT is also known as NAT overload
- By also using the port number, PAT is able to forward the response packets to the correct internal device
- The PAT process also validates that the incoming packets were requested, thus adding a degree of security to the session

ກົງມືນງົງ

# Types of NAT

- Comparing NAT and PAT

- NAT translates IPv4 addresses on a 1:1 basis between private IPv4 addresses and public IPv4 addresses
- PAT modifies both the address and the port number
- NAT forwards incoming packets to their inside destination by referring to the incoming source IPv4 address given by the host on the public network
- With PAT, there is generally only one or a very few publicly exposed IPv4 addresses
- PAT is also able to translate protocols that don't use port numbers such as ICMP. Each one of these protocols are supported differently by PAT

# Benefits & Disadvantages of NAT

## Benefits of NAT

- Conserves the legally registered addressing scheme
- Increases the flexibility of connections to the public network 9 និមុន
- Provides consistency for internal network addressing schemes ពាន់សម្រាប់អាជីវកម្ម
- Provides network security

## Disadvantages of NAT

- Performance is degraded នៅ
- End-to-end functionality is degraded បង្កើត នូវវា
- End-to-end IP traceability is lost
- Tunneling is more complicated
- Initiating TCP connections can be disrupted

# CONFIGURING NAT

## Configuring Static NAT

- Configuring Static NAT

- Analyzing Static NAT

- Verifying Static NAT

## Configuring Dynamic NAT

- Dynamic NAT Operation

- Configuring Dynamic NAT

- Analyzing Dynamic NAT

- Verifying Dynamic NAT

## Configuring Port Address Translation (PAT)

- Configuring PAT: Address Pool

- Configuring PAT: Single Address

- Analyzing PAT

- Verifying PAT

## Port Forwarding

# Configuring Static NAT

## Configuring Static NAT


— There are two basic tasks when configuring static NAT translations:

- Create the mapping between the inside local and outside local addresses
- Define which interface belong to the inside network and which belong to the outside network

Step	Action
1 map ip	Establish static translation between an inside local address and an inside global address. <code>Router(config)# ip nat inside source static local-ip global-ip</code>
2 return with connection	Specify the inside interface. <code>Router(config)# interface type number</code>
3 return with connection	Mark the interface as connected to the inside. <code>Router(config-if)# ip nat inside</code>
4 return without connection	Exit interface configuration mode. <code>Router(config-if)# exit</code>
5 return without connection	Specify the outside interface. <code>Router(config)# interface type number</code>
6 return without connection	Mark the interface as connected to the outside. <code>Router(config-if)# ip nat outside</code>

## Configuring Static NAT

map នឹងនឹង command  
រួចរាល់




```
R2(config)# ip nat inside source static 192.168.10.254 209.165.201.5
R2(config)# interface Serial0/0/0
R2(config-if)# ip address 10.1.1.2 255.255.255.252
Identifies interface serial 0/0/0 as an inside NAT interface.
R2(config-if)# ip nat inside
R2(config-if)# exit

R2(config)# interface Serial0/1/0
R2(config-if)# ip address 209.165.200.225 255.255.255.224
Identifies interface serial 0/1/0 as the outside NAT interface.
R2(config-if)# ip nat outside
```

# Configuring Static NAT

- Analyzing Static NAT



Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMITL


37

# Configuring Static NAT

- Verifying Static NAT

The static translation is always present in the NAT table.

```
R2# show ip nat translations
Pro Inside global Inside local Outside local Outside global
--- 209.165.201.5 192.168.10.254 ---
```



The static translation during an active session.

```
R2# show ip nat translations
Pro Inside global Inside local Outside local Outside global
--- 209.165.201.5 192.168.10.254 209.165.200.254 209.165.200.254
```

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMITL

38

# Configuring Static NAT

- Verifying Static NAT

```
R2# clear ip nat statistics
R2# show ip nat statistics
Total active translations: 1 (1 static, 0 dynamic; 0 extended)
Peak translations: 0
Outside interfaces:
Serial0/0/1
Inside interfaces:
Serial0/0/0
Hits: 0 Misses: 0
<output omitted>
Client PC establishes a session with the web server
R2# show ip nat statistics
Total active translations: 1 (1 static, 0 dynamic; 0 extended)
Peak translations: 2, occurred 00:00:14 ago
Outside interfaces:
Serial0/1/0
Inside interfaces:
Serial0/0/0
Hits: 5 Misses: 0
<output omitted>
```

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMITL

39

# Configuring Dynamic NAT

- Dynamic NAT Operation


- The pool of public IPv4 addresses (inside global address pool) is available to any device on the inside network on a first-come first-served basis
- With dynamic NAT, a single inside address is translated to a single outside address
- The pool must be large enough to accommodate all inside devices
- A device won't be able to communicate to any external networks if no addresses are available in the pool

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMITL

40

# Configuring Dynamic NAT

- Configuring Dynamic NAT




Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMUTT



41

# Configuring Dynamic NAT

- Analyzing Dynamic NAT




Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMUTT

42

# Configuring Dynamic NAT

- Analyzing Dynamic NAT



Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMUTT

43

# Configuring Dynamic NAT

- Verifying Dynamic NAT

**Verifying Dynamic NAT with show ip nat translations**

```
R2# show ip nat translations
Pro Inside global    Inside local    Outside local    Outside global
--- 209.165.200.226  192.168.10.10 ---  ---
--- 209.165.200.227  192.168.11.10 ---  ---

R2#
R2# show ip nat translations verbose
Pro Inside global    Inside local    Outside local    Outside global
--- 209.165.200.226  192.168.10.10 ---  ---
      create 00:17:25, use 00:01:54 timeout:86400000, left
23:58:05, Map-Id(In): 1,
      flags:
      none, use_count: 0, entry-id: 32, lc_entries: 0
--- 209.165.200.227  192.168.11.10 ---  ---
      create 00:17:22, use 00:01:51 timeout:86400000, left
23:58:08, Map-Id(In): 1,
      flags:
      none, use_count: 0, entry-id: 34, lc_entries: 0
R2#
```

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMUTT

44

# Configuring Dynamic NAT

- Verifying Dynamic NAT

## Verifying Dynamic NAT with show ip nat statistics

```
R2# clear ip nat statistics

PC1 and PC2 establish sessions with the server

R2# show ip nat statistics
Total active translations: 2 (0 static, 2 dynamic; 0 extended)
Peak translations: 6, occurred 00:27:07 ago
Outside interfaces:
  Serial0/0/1
Inside interfaces:
  Serial0/1/0
Hits: 24 Misses: 0
CEF Translated packets: 24, CEF Punted packets: 0
Expired translations: 4
Dynamic mappings:
-- Inside Source
[Id: 1] access-list 1 pool NAT-POOL1 refcount 2
  pool NAT-POOL1: netmask 255.255.255.224
start 209.165.200.226 end 209.165.200.240
type generic, total addresses 15, allocated 2 (13%), misses 0

Total doors: 0
Appl doors: 0
Normal doors: 0
Queued Packets: 0
no4
```

Internetworking Standards and Technologies, Jirasak Sittigorn, Computer Engineering, KMITL

## Configuring PAT

- Configuring PAT: Single Address

Step 1	Define a standard access list permitting the addresses that should be translated.
	<b>access-list <i>access-list-number</i> permit <i>source[source-wildcard]</i></b>
Step 2	Establish dynamic source translation, specifying the ACL, exit interface and overload options. <i>conif Int mon</i>  <i>nat</i> <i>overload</i> <i>natoutside</i>
	<b>ip nat inside source list <i>access-list-number</i> interface <i>type number</i> <u>overload</u></b>
Step 3	Identify the inside interface.  <b>interface <i>type number</i></b> <b>ip nat inside</b>
Step 4	Identify the outside interface.
	<b>interface <i>type number</i></b> <b>ip nat outside</b>

# Configuring PAT

Config for 2 MU


## I Union Dynamics

- Configuring PAT: Address Pool

<b>Step 1</b>	Define a pool of <u>global addresses</u> to be used for overload translation.
	<b>ip nat pool <i>name</i> start-ip end-ip {netmask netmask   prefix-length prefix-length}</b>
<b>Step 2</b>	Define a standard access list permitting the <u>addresses that should be translated</u> .
	<b>access-list <i>access-list-number</i> permit source [source-wildcard]</b>
<b>Step 3</b> <i>pool</i> <i>ACI</i>	Establish overload translation, specifying the access list and pool defined in prior steps.
	<b>ip nat inside source list <i>access-list-number</i> pool <i>name</i> overload</b> <small>รับจาก ต่อจาก</small>
<b>Step 4</b>	Identify the inside interface.
	<b>interface <i>type number</i></b> <b>ip nat inside</b>
<b>Step 5</b>	Identify the outside interface.
	<b>interface <i>type number</i></b> <b>ip nat outside</b>


## Configuring PAT

- Analyzing PAT



# Configuring PAT

- Analyzing PAT



# Configuring PAT

- Verifying PAT

Verifying PAT Translations

```
R2# show ip nat translations
Pro Inside global           Inside local      Outside local      Outside global
tcp 209.165.200.226:51839  192.168.10.10:51839  209.165.201.1:80  209.165.201.1:80
tcp 209.165.200.226:42558  192.168.11.10:42558  209.165.202.129:80  209.165.202.129:80
R2#
```

R2# clear ip nat statistics

R2# show ip nat statistics

```
Total active translations: 2 (0 static, 2 dynamic; 2 extended)
Peak translations: 2, occurred 00:00:05 ago
Outside interfaces:
  Serial0/0/1
Inside interfaces:
  Serial0/1/0
Hits: 4 Misses: 0
CEF Translated packets: 4, CEF Punted packets: 0
Expired translations: 0
Dynamic mappings:
-- Inside Source
[Id: 3] access-list 1 pool NAT-POOL2 refcount 2
  pool NAT-POOL2: netmask 255.255.255.224
    start 209.165.200.226 end 209.165.200.240
    type generic, total addresses 15, allocated 1 (6%),
    lifetime 8
```

## Questions and Answers



10.4 ~~40~~ 100