



OpenNebula 5.10 Deployment guide

Release 5.10.5

OpenNebula Systems

Sep 21, 2020

This document is being provided by OpenNebula Systems under the Creative Commons Attribution-NonCommercial-Share Alike License.

THE DOCUMENT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE DOCUMENT.

CONTENTS

1	Cloud Design	1
1.1	Overview	1
1.2	Open Cloud Architecture	2
1.3	VMware Cloud Architecture	7
1.4	OpenNebula Provisioning Model	13
2	OpenNebula Installation	18
2.1	Overview	18
2.2	Front-end Installation	18
2.3	MySQL Setup	26
3	Node Installation	29
3.1	Overview	29
3.2	KVM Node Installation	30
3.3	LXD Node Installation	37
3.4	vCenter Node Installation	39
3.5	Verify your Installation	47
4	Authentication Setup	56
4.1	Overview	56
4.2	SSH Authentication	57
4.3	x509 Authentication	59
4.4	LDAP Authentication	62
5	Sunstone Setup	68
5.1	Overview	68
5.2	Sunstone Installation & Configuration	69
5.3	Sunstone Views	78
5.4	Labels	82
5.5	User Security and Authentication	92
5.6	Cloud Servers Authentication	98
5.7	Configuring Sunstone for Large Deployments	101
6	VMware Infrastructure Setup	107
6.1	Overview	107
6.2	vCenter Driver Setup	107
6.3	vCenter Datastores	129
6.4	vCenter Networking Overview	137
6.5	NSX Setup	144
7	Open Cloud Host Setup	153

7.1	Overview	153
7.2	KVM Driver	153
7.3	LXD Driver	163
7.4	Monitoring	169
7.5	PCI Passthrough	173
8	Open Cloud Storage Setup	180
8.1	Overview	180
8.2	Filesystem Datastore	182
8.3	Ceph Datastore	187
8.4	LVM Datastore	193
8.5	Raw Device Mapping (RDM) Datastore	196
8.6	iSCSI - Libvirt Datastore	198
8.7	The Kernels & Files Datastore	200
9	Open Cloud Networking Setup	202
9.1	Overview	202
9.2	Node Setup	203
9.3	Bridged Networking	205
9.4	802.1Q VLAN Networks	206
9.5	VXLAN Networks	208
9.6	Open vSwitch Networks	212
10	References	216
10.1	Overview	216
10.2	ONED Configuration	216
10.3	Logging & Debugging	233
10.4	Onedb Tool	236
10.5	Scalability Testing and Tuning	240

CLOUD DESIGN

1.1 Overview

The first step of building a reliable, useful and successful cloud is to decide a clear design. This design needs to be aligned with the expected use of the cloud, and it needs to describe which data center components are going to be part of the cloud. This comprises i) all the infrastructure components such as networking, storage, authorization and virtualization back-ends, as well as the ii) planned dimension of the cloud (characteristics of the workload, numbers of users and so on) and the iii) provisioning workflow, i.e. how end users are going to be isolated and using the cloud.

In order to get the most out of a OpenNebula Cloud, we recommend that you create a plan with the features, performance, scalability, and high availability characteristics you want in your deployment. This Chapter provides information to plan an OpenNebula cloud based on [KVM or LXD](#) or [vCenter](#). With this information, you will be able to easily architect and dimension your deployment, as well as understand the technologies involved in the management of virtualized resources and their relationship.

1.1.1 How Should I Read This Chapter

This is the first Chapter to read, as it introduces the necessary concepts to correctly define a cloud architecture.

Within this Chapter, as a first step, a design of the cloud and its dimension should be drafted. For KVM and LXD clouds proceed to [Open Cloud Architecture](#) and for vCenter clouds read [VMware Cloud Architecture](#).

Then you could read the [OpenNebula Provisioning Model](#) to identify the model wanted to provision resources to end users. In a small installation with a few hosts, you can skip this provisioning model guide and use OpenNebula without giving much thought to infrastructure partitioning and provisioning. But for medium and large deployments you will probably want to provide some level of isolation and structure.

Once the cloud architecture has been designed, the next step would be to learn how to install the [OpenNebula front-end](#).

1.1.2 Hypervisor Compatibility


Section	Compatibility
Open Cloud Architecture	This Section applies to KVM and LXD.
VMware Cloud Architecture	This Section applies to vCenter.
OpenNebula Provisioning Model	This Section applies to both KVM and vCenter.

1.2 Open Cloud Architecture

Enterprise cloud computing is the next step in the evolution of data center (DC) virtualization. OpenNebula is a simple but feature-rich and flexible solution to build and manage enterprise clouds and virtualized DCs, that combines existing virtualization technologies with advanced features for multi-tenancy, automatic provision and elasticity. OpenNebula follows a bottom-up approach driven by sysadmins, devops and users real needs.

1.2.1 Architectural Overview

OpenNebula assumes that your physical infrastructure adopts a classical cluster-like architecture with a front-end, and a set of hosts where Virtual Machines (VM) will be executed. There is at least one physical network joining all the hosts with the front-end.



A cloud architecture is defined by three components: storage, networking and virtualization. Therefore, the basic components of an OpenNebula system are:

- **Front-end** that executes the OpenNebula services.
- Hypervisor-enabled **hosts** that provide the resources needed by the VMs.
- **Datastores** that hold the base images of the VMs.
- Physical **networks** used to support basic services such as interconnection of the storage servers and OpenNebula control operations, and VLANs for the VMs.

OpenNebula presents a highly modular architecture that offers broad support for commodity and enterprise-grade hypervisors, monitoring, storage, networking and user management services. This Section briefly describes the different choices that you can make for the management of the different subsystems. If your specific services are not supported we recommend checking the drivers available in the [Add-on Catalog](#). We also provide information and support about how to develop new drivers.

1.2.2 Dimensioning the Cloud

The dimension of a cloud infrastructure can be directly inferred from the expected workload in terms of VMs that the cloud infrastructure must sustain. This workload is also tricky to estimate, but this is a crucial exercise to build an

efficient cloud.

The main aspects to take into account at the time of dimensioning the OpenNebula cloud follow.

OpenNebula front-end

The minimum recommended specs are for the OpenNebula front-end are:

Resource	Minimum Recommended configuration
Memory	8 GB
CPU	1 CPU (4 cores)
Disk Size	100 GB
Network	2 NICs

Please take into account that these recommendations are meant as a guidance and may be relaxed or increased depending on the size and workload of your cloud.

The maximum number of servers (virtualization hosts) that can be managed by a single OpenNebula instance strongly depends on the performance and scalability of the underlying platform infrastructure, mainly the storage subsystem. The general recommendation is no more than 2,500 servers and 10,000 VMs managed by a single instance. Related to this, read the section about [how to tune OpenNebula for large deployments](#).

KVM nodes

Regarding the dimensions of the Linux virtualization nodes:

- **CPU:** without overcommitment, each CPU core assigned to a VM must exists as a physical CPU core. By example, for a workload of 40 VMs with 2 CPUs, the cloud will need 80 physical CPUs. These 80 physical CPUs can be spread among different hosts: 10 servers with 8 cores each, or 5 server of 16 cores each. With overcommitment, however, CPU dimension can be planned ahead, using the CPU and VCPU attributes: CPU states physical CPUs assigned to the VM, while VCPU states virtual CPUs to be presented to the guest OS.
- **MEMORY:** Planning for memory is straightforward, as by default *there is no overcommitment of memory* in OpenNebula. It is always a good practice to count 10% of overhead for the hypervisor. (This is not an absolute upper limit, it depends on the hypervisor, however, since containers have a very low overhead, this metric is negligible for LXD nodes.) So, in order to sustain a VM workload of 45 VMs with 2GB of RAM each, 90GB of physical memory is needed. The number of hosts is important, as each one will incur a 10% overhead due to the hypervisors. For instance, 10 hypervisors with 10GB RAM each will contribute with 9GB each (10% of 10GB = 1GB), so they will be able to sustain the estimated workload. The rule of thumb is having at least 1GB per core, but this also depends on the expected workload.

LXD nodes

Since LXD avoids using virtual hardware, the amount of resources dedicated to the hypervisor are much lower when compared to KVM. There is no exact figure but you can get an idea from [this resource usage comparison vs KVM](#)

Storage

It is important to understand how OpenNebula uses storage, mainly the difference between system and image datastores.

- The **image datastore** is where OpenNebula stores all the images registered that can be used to create VMs, so the rule of thumb is to devote enough space for all the images that OpenNebula will have registered.
- The **system datastore** is where the VMs that are currently running store their disks. It is trickier to estimate correctly since volatile disks come into play with no counterpart in the image datastore; (volatile disks are created on the fly in the hypervisor).

One valid approach is to limit the storage available to users by defining quotas in the number of maximum VMs and also the Max Volatile Storage a user can demand, and ensuring enough system and image datastore space to comply

with the limit set in the quotas. In any case, OpenNebula allows cloud administrators to add more system and images datastores if needed.

Dimensioning storage is a critical aspect, as it is usually the cloud bottleneck. It very much depends on the underlying technology. As an example, in Ceph for a medium size cloud at least three servers are needed for storage with 5 disks each of 1TB, 16Gb of RAM, 2 CPUs of 4 cores each and at least 2 NICs.

Network

Networking needs to be carefully designed to ensure reliability in the cloud infrastructure. The recommendation is to have 2 NICs in the front-end (public and service), or 3 NICs depending on the storage backend, as access to the storage network may be needed, and 4 NICs present in each virtualization node (private, public, service and storage networks). Fewer NICs may be needed, depending on the storage and networking configuration.

1.2.3 Front-End

The machine that holds the OpenNebula installation is called the front-end. This machine needs network connectivity to all the hosts, and possibly access to the storage Datastores (either by direct mount or network). The base installation of OpenNebula takes less than 150MB.

OpenNebula services include:

- Management daemon (`oned`) and scheduler (`mm_sched`)
- Web interface server (`sunstone-server`)
- Advanced components: OneFlow, OneGate, econe, ...

Note: Note that these components communicate through XML-RPC and may be installed in different machines for security or performance reasons.

There are several certified platforms to act as front-end for each version of OpenNebula. Refer to the platform notes and chose the one that best fits your needs.

OpenNebula's default database uses **sqlite**. If you are planning a production or medium to large scale deployment, you should consider using [MySQL](#).

If you are interested in setting up a highly available cluster for OpenNebula, check the High Availability OpenNebula Section.

If you need to federate several datacenters, with a different OpenNebula instance managing the resources, but needing a common authentication schema, check the Federation Section.

1.2.4 Monitoring

The monitoring subsystem gathers information relative to the hosts and the virtual machines, such as the host status, basic performance indicators, as well as VM status and capacity consumption. This information is collected by executing a set of static probes provided by OpenNebula. The information is sent according to the following process: each host periodically sends monitoring data to the front-end which collects it and processes it in a dedicated module. This model is highly scalable and its limit (in terms of number of VMs monitored per second) is bounded to the performance of the server running `oned` and the database server.

Please check the [the Monitoring Section](#) for more details.

1.2.5 Virtualization Hosts

The hosts are the physical machines that will run the VMs. There are several certified platforms to act as nodes for each version of OpenNebula. Refer to the platform notes and chose the one that best fits your needs. The Virtualization Subsystem is the component in charge of talking to the hypervisor installed in the hosts and taking the actions needed for each step in the VM life-cycle.


OpenNebula natively supports two open source hypervisors, the [KVM](#) and [LXD](#).

Ideally, the configuration of the nodes will be homogeneous in terms of the software components installed, the oneadmin administration user, accessible storage and network connectivity. This may not always be the case, and homogeneous hosts can be grouped in OpenNebula clusters, e.g. LXD cluster and KVM cluster.

If you are interested in fail-over protection against hardware and operating system outages within your virtualized IT environment, check the Virtual Machines High Availability Section.

1.2.6 Storage

OpenNebula uses *Datastores* to store VMs' disk images. A datastore is any storage medium, typically backed by SAN/NAS servers. In general, each datastore has to be accessible through the front-end using any suitable technology — NAS, SAN or direct attached storage.



When a VM is deployed, its images are *transferred* from the datastore to the hosts. Depending on the actual storage technology used, it can mean a real transfer, a symbolic link or setting up an LVM volume.

OpenNebula is shipped with 3 different datastore classes:

- **System Datastores**: to hold images for running VMs. Depending on the storage technology used, these temporary images can be complete copies of the original image, qcow deltas or simple filesystem links.
- **Image Datastores**: to store the disk images repository. Disk images are moved, or cloned, to/from the System Datastore when the VMs are deployed or shutdown, or when disks are attached or snapshotted.
- *File Datastore*: a special datastore used to store plain files, not disk images. These files can be used as kernels, ramdisks or context files.

Image datastores can be of different types, depending on the underlying storage technology:

- *Filesystem*: to store disk images in a file form. There are three types: ssh, shared and qcow.
- *LVM*: to use LVM volumes instead of plain files to hold the Virtual Images. This reduces the overhead of having a file-system in place and thus increases performance.
- *Ceph*: to store disk images using Ceph block devices.

Warning: Default: The default system and images datastores are configured to use a filesystem with the ssh transfer drivers.

Please check the *Storage Chapter* for more details.

1.2.7 Networking

OpenNebula provides an easily adaptable and customizable network subsystem in order to integrate the specific network requirements of existing datacenters. **At least two different physical networks are needed:**

- **Service Network**: used by the OpenNebula front-end daemons to access the hosts in order to manage and monitor the hypervisors, and move image files. It is highly recommended to install a dedicated network for this purpose;
- **Instance Network**: offers network connectivity to the VMs across the different hosts. To make effective use of your VM deployments, you will probably need to make one or more physical networks accessible to them.

The OpenNebula administrator may associate one of the following drivers to each Host:

- *dummy* (default): doesn't perform any network operation, and firewalling rules are also ignored.
- *fw*: firewalling rules are applied, but networking isolation is ignored.
- *802.1Q*: restrict network access through VLAN tagging, which requires support by the hardware switches.
- *ebtables*: restrict network access through Ebttables rules. No special hardware configuration required.
- *ovswitch*: restrict network access with *Open vSwitch Virtual Switch*.
- *vxlan*: segment a VLAN into isolated networks using the VXLAN encapsulation protocol.

Please check the *Networking Chapter* to find out more about the networking technologies supported by OpenNebula.

1.2.8 Authentication

The following authentication methods are supported to access OpenNebula:

- Built-in User/Password
- *SSH Authentication*
- *X509 Authentication*
- *LDAP Authentication* (and Active Directory)

Warning: Default: OpenNebula comes by default with an internal built-in user/password authentication.

Please check the *Authentication Chapter* to find out more about the authentication technologies supported by OpenNebula. ===== Advanced Components

Once you have an OpenNebula cloud up and running, you can install the following advanced components:

- Multi-VM Applications and Auto-scaling: OneFlow allows users and administrators to define, execute and manage multi-tiered applications, or services composed of interconnected Virtual Machines with deployment dependencies between them. Each group of Virtual Machines is deployed and managed as a single entity, and is completely integrated with the advanced OpenNebula user and group management.
- Cloud Bursting: Cloud bursting is a model in which the local resources of a Private Cloud are combined with resources from remote Cloud providers. Such support for cloud bursting enables highly scalable hosting environments.
- Public Cloud: Cloud interfaces can be added to your Private Cloud if you want to provide partners or external users with access to your infrastructure, or to sell your overcapacity. The following interfaces provide a simple and remote management of cloud (virtual) resources at a high abstraction level: Amazon EC2 and EBS APIs.
- Application Insight: OneGate allows Virtual Machine guests to push monitoring information to OpenNebula. Users and administrators can use it to gather metrics, detect problems in their applications, and trigger OneFlow auto-scaling rules.

1.3 VMware Cloud Architecture


OpenNebula is intended for companies willing to create a self-service cloud environment on top of their VMware infrastructure without having to abandon their investment in VMware and retool the entire stack. In these environments, OpenNebula seamlessly integrates with existing vCenter infrastructures to leverage advanced features — such as vMotion, HA, DRS scheduling or NSX-T / NSX-V — provided by the VMware vSphere product family. OpenNebula exposes a multi-tenant, cloud-like provisioning layer on top of vCenter, including features like virtual data centers, data center federation or hybrid cloud computing to connect in-house vCenter infrastructures with public clouds.

OpenNebula over vCenter is intended for companies that want to keep VMware management tools, procedures and workflows. For these companies, throwing away VMware and retooling the entire stack is not the answer. However, as they consider moving beyond virtualization toward a private cloud, they can choose to either invest more in VMware, or proceed on a tactically challenging but strategically rewarding path of open infrastructure.

1.3.1 Architectural Overview

OpenNebula assumes that your physical infrastructure adopts a classical cluster-like architecture with a front-end, and a set of vCenter instances grouping ESX hosts where Virtual Machines (VM) will be executed. There is at least one physical network joining all the vCenters and ESX hosts with the front-end. Connection from the front-end to vCenter is for management purposes, whereas the connection from the front-end to the ESX hosts is to support VNC or VMRC connections.

The VMware vCenter drivers enable OpenNebula to access one or more vCenter servers that manage one or more ESX Clusters. Each ESX Cluster is presented in OpenNebula as an aggregated hypervisor. Note that OpenNebula scheduling decisions are therefore made at ESX Cluster level; vCenter then uses the DRS component to select the actual ESX host and Datastore to deploy the Virtual Machine.



A cloud architecture is defined by three components: storage, networking and virtualization. Therefore, the basic components of an OpenNebula cloud are:

- **Front-end** that executes the OpenNebula services.
- Hypervisor-enabled **hosts** that provide the resources needed by the VMs.
- **Datastores** that hold the base images of the VMs.
- Physical or software defined **networks** used to support basic services such as interconnection of the VMs.

OpenNebula presents a highly modular architecture that offers broad support for commodity and enterprise-grade hypervisors, monitoring, storage, networking and user management services. This Section briefly describes the different choices that you can make for the management of the different subsystems. If your specific services are not supported we recommend checking the drivers available in the [Add-on Catalog](#). We also provide information and support about how to develop new drivers.

1.3.2 Dimensioning the Cloud

The dimension of a cloud infrastructure can be directly inferred from the expected workload in terms of VMs that the cloud infrastructure must sustain. This workload is also tricky to estimate, but this is a crucial exercise to build an efficient cloud.

OpenNebula front-end

The minimum recommended specs are for the OpenNebula front-end are:

Resource	Minimum Recommended configuration
Memory	2 GB
CPU	1 CPU (2 cores)
Disk Size	100 GB
Network	2 NICs

When running on a front-end with the minimums described in the above table, OpenNebula is able to manage a vCenter infrastructure of the following characteristics:

- Up to 4 vCenters
- Up to 40 ESXs managed by each vCenter
- Up to 1.000 VMs in total, each vCenter managing up to 250 VMs

ESX nodes

Regarding the dimensions of the ESX virtualization nodes:

- **CPU:** without overcommitment, each CPU core assigned to a VM must exist as a physical CPU core. By example, for a workload of 40 VMs with 2 CPUs, the cloud will need 80 physical CPUs. These 80 physical CPUs can be spread among different hosts: 10 servers with 8 cores each, or 5 servers of 16 cores each. With overcommitment, however, CPU dimension can be planned ahead, using the CPU and VCPU attributes: CPU states physical CPUs assigned to the VM, while VCPU states virtual CPUs to be presented to the guest OS.
- **MEMORY:** Planning for memory is straightforward, as by default *there is no overcommitment of memory* in OpenNebula. It is always a good practice to count 10% of overhead by the hypervisor. (This is not an absolute upper limit, it depends on the hypervisor.) So, in order to sustain a VM workload of 45 VMs with 2GB of RAM each, 90GB of physical memory is needed. The number of hosts is important, as each one will incur a 10% overhead due to the hypervisors. For instance, 10 hypervisors with 10GB RAM each will contribute with 9GB each (10% of 10GB = 1GB), so they will be able to sustain the estimated workload. The rule of thumb is having at least 1GB per core, but this also depends on the expected workload.

Storage

Dimensioning storage is a critical aspect, as it is usually the cloud bottleneck. OpenNebula can manage any datastore that is mounted in the ESX and visible in vCenter. The datastore used by a VM can be fixed by the cloud admin or delegated to the cloud user. It is important to ensure that enough space is available for new VMs, otherwise its creation process will fail. One valid approach is to limit the storage available to users by defining quotas in the number of maximum VMs, and ensuring enough datastore space to comply with the limit set in the quotas. In any case, OpenNebula allows cloud administrators to add more datastores if needed.

Network

Networking needs to be carefully designed to ensure reliability in the cloud infrastructure. The recommendation is to have 2 NICs in the front-end (service and public network) and 4 NICs present in each ESX node (private, public, service and storage networks). Fewer NICs may be needed depending on the storage and networking configuration.

1.3.3 Front-End

The machine that holds the OpenNebula installation is called the front-end. This machine needs network connectivity to all the vCenter and ESX hosts. The base installation of OpenNebula takes less than 150MB.

OpenNebula services include:

- Management daemon (`oned`) and scheduler (`mm_sched`)
- Web interface server (`sunstone-server`)
- Advanced components: OneFlow, OneGate, econe, ...

Note: Note that these components communicate through XML-RPC and may be installed in different machines for security or performance reasons.

There are several certified platforms to act as front-end for each version of OpenNebula. Refer to the platform notes and chose the one that best fits your needs.

OpenNebula's default database uses **sqlite**. If you are planning a production or medium to large scale deployment, you should consider using [MySQL](#).

If you are interested in setting up a highly available cluster for OpenNebula, check the High Availability OpenNebula Section.

1.3.4 Monitoring

The monitoring subsystem gathers information relative to the hosts and the virtual machines, such as the host status, basic performance indicators, as well as VM status and capacity consumption. This information is collected by executing a set of probes in the front-end provided by OpenNebula.

Please check the [the Monitoring Section](#) for more details.

1.3.5 Virtualization Hosts

The VMware vCenter drivers enable OpenNebula to access one or more vCenter servers that manage one or more ESX Clusters. Each ESX Cluster is presented in OpenNebula as an aggregated hypervisor. The Virtualization Subsystem is the component in charge of talking with vCenter and taking the actions needed for each step in the VM life-cycle. All the management operations are issued by the front-end to vCenter, except the VNC connection that is performed directly from the front-end to the ESX where a particular VM is running.

OpenNebula natively supports the *vCenter* hypervisor. vCenter drivers need to be configured in the OpenNebula front-end.

If you are interested in fail-over protection against hardware and operating system outages within your virtualized IT environment, check the Virtual Machines High Availability Section.

1.3.6 Storage

OpenNebula interacts as a consumer of vCenter storage, and as such, supports all the storage devices supported by [ESX](#). When a VM is instantiated from a VM Template, OpenNebula's Scheduler will choose a datastore using the default policy of distributing the VMs across available datastores. However this scheduler policy can be changed, and you can force VMs to be instantiated from a template to use a specific datastore thanks to the `SCHED_DS_REQUIREMENTS` attribute. If Storage DRS is enabled, OpenNebula can request storage recommendations to the Storage DRS cluster and apply them when a VM is instantiated, so in this case OpenNebula would delegate the datastore selection to vCenter's Storage DRS.

vCenter/ESX Datastores can be represented in OpenNebula to create, clone and/or upload VMDKs. The vCenter/ESX datastore representation in OpenNebula is described in the [vCenter datastore Section](#).

1.3.7 Networking

Networking in OpenNebula is handled by creating or importing Virtual Network representations of vCenter Networks and Distributed vSwitches. In this way, new VMs with defined network interfaces will be bound by OpenNebula to these Networks and/or Distributed vSwitches. OpenNebula can create a new logical layer of these vCenter Networks and Distributed vSwitches; in particular, three types of Address Ranges can be defined per Virtual Network representing the vCenter network resources: plain Ethernet, IPv4 and IPv6. This networking information can be passed to the VMs through the contextualization process.

OpenNebula supports NSX-T and NSX-V logical switches through the NSX Manager API. Some of the key points of this integration are:

- NSX Manager is automatically detected from vCenter Server.
- Transport Zones are automatically discovered.
- Logical switches are created in the NSX Manager after a Virtual Network is created in OpenNebula.
- Link VM NICs to these logical switches through the OpenNebula GUI, both at deployment and run times.
- Import or remove existing logical switches.

Please check the [vCenter Networking Setup](#) and [NSX Setup](#) to find out more about the networking support in vCenter infrastructures by OpenNebula.

1.3.8 Authentication

The following authentication methods are supported to access OpenNebula:


- Built-in User/Password
- [SSH Authentication](#)
- [X509 Authentication](#)
- [LDAP Authentication](#) (and Active Directory)

Warning: Default: OpenNebula comes by default with an internal built-in user/password authentication.


Please check the [Authentication Chapter](#) to find out more about the authentication technologies supported by OpenNebula.

1.3.9 Multi-Datacenter Deployments

OpenNebula interacts with the vCenter instances by interfacing with its SOAP API exclusively. This characteristic enables architectures where the OpenNebula instance and the vCenter environment are located in different datacenters. A single OpenNebula instance can orchestrate several vCenter instances remotely located in different data centers. Connectivity between data centers needs to have low latency in order to have a reliable management of vCenter from OpenNebula.



When administration domains need to be isolated, or the interconnection between datacenters does not allow a single controlling entity, OpenNebula can be configured in a federation. Each OpenNebula instance of the federation is called a Zone, one of them configured as master and the others as slaves. An OpenNebula federation is a tightly coupled integration; all the instances will share the same user accounts, groups, and permissions configuration. Federation allows end users to consume resources allocated by the federation administrators regardless of their geographic location. The integration is seamless, meaning that a user logged into the Sunstone web interface of a Zone will not have to log out and enter the address of another Zone. Sunstone allows to change the active Zone at any time, and it will automatically redirect the requests to the right OpenNebula at the target Zone. For more information, check the Federation Section.



1.3.10 Advanced Components

Once you have an OpenNebula cloud up and running, you can install the following advanced components:

- Multi-VM Applications and Auto-scaling: OneFlow allows users and administrators to define, execute and manage services composed of interconnected Virtual Machines with deployment dependencies between them. Each group of Virtual Machines is deployed and managed as a single entity, and is completely integrated with the advanced OpenNebula user and group management.
- Cloud Bursting: Cloud bursting is a model in which the local resources of a Private Cloud are combined with

resources from remote Cloud providers. Such support for cloud bursting enables highly scalable hosting environments.

- **Public Cloud:** Cloud interfaces can be added to your Private Cloud if you want to provide partners or external users with access to your infrastructure, or to sell your overcapacity. The following interfaces provide a simple and remote management of cloud (virtual) resources at a high abstraction level: Amazon EC2 and EBS APIs.
- **Application Insight:** OneGate allows Virtual Machine guests to push monitoring information to OpenNebula. Users and administrators can use it to gather metrics, detect problems in their applications, and trigger OneFlow auto-scaling rules.

1.4 OpenNebula Provisioning Model


In a small installation with a few hosts, you can use OpenNebula without giving much thought to infrastructure partitioning and provisioning. But for medium and large deployments you will probably want to provide some level of isolation and structure.

This Section is meant for cloud architects, builders and administrators, to help them understand the OpenNebula model for managing and provisioning virtual resources. This model is a result of our collaboration with our user community throughout the life of the project.

1.4.1 The Infrastructure Perspective

Common large IT shops have multiple Data Centers (DCs), each one running its own OpenNebula instance and consisting of several physical Clusters of infrastructure resources (Hosts, Networks and Datastores). These Clusters could present different architectures and software/hardware execution environments to fulfill the needs of different workload profiles. Moreover, many organizations have access to external public clouds to build hybrid cloud scenarios where the private capacity of the Data Centers is supplemented with resources from external clouds, like Amazon AWS, to address peaks of demand.

For example, you could have two Data Centers in different geographic locations, Europe and USA West Coast, and an agreement for cloudbursting with a public cloud provider, such as Amazon, and/or Azure. Each Data Center runs its own zone or full OpenNebula deployment. Multiple OpenNebula Zones can be configured as a federation, and in this case they will share the same user accounts, groups, and permissions across Data Centers.



1.4.2 The Organizational Perspective


Users are organized into Groups (similar to what other environments call Projects, Domains, Tenants...). A Group is an authorization boundary that can be seen as a business unit if you are considering it as a private cloud or as a complete new company if it is a public cloud. While Clusters are used to group Physical Resources according to

common characteristics such as networking topology or physical location, Virtual Data Centers (VDCs) allow creating “logical” pools of Physical Resources (which could belong to different Clusters and Zones) and allocate them to user Groups.

A VDC is a fully-isolated virtual infrastructure environment where a Group of users (or optionally several Groups of users), under the control of a Group admin, can create and manage compute and storage capacity. The users in the Group, including the Group admin, would only see the virtual resources and not the underlying physical infrastructure. The Physical Resources allocated to the Group are managed by the cloud administrator through a VDC. These resources grouped in the VDC can be dedicated exclusively to the Group, providing isolation at the physical level too.

The privileges of the Group users and the admin regarding the operations over the virtual resources created by other users can be configured. For example, in the Advanced Cloud Provisioning Case described below, the users can instantiate virtual machine templates to create their machines, while the admins of the Group have full control over other users’ resources and can also create new users in the Group.

Users can access their resources through any of the existing OpenNebula interfaces, such as the CLI, Sunstone Cloud View, OCA, or the AWS APIs. Group admins can manage their Groups through the CLI or the Group Admin View in Sunstone. Cloud administrators can manage the Groups through the CLI or Sunstone.



The Cloud provisioning model based on VDCs enables an integrated, comprehensive framework to dynamically provision the infrastructure resources in large multi-datacenter environments to different customers, business units or groups. This brings several benefits:

- Partitioning of cloud Physical Resources between Groups of users
- Complete isolation of Users, organizations or workloads
- Allocation of Clusters with different levels of security, performance or high availability
- Containers for the execution of software-defined data centers
- Way of hiding Physical Resources from Group members
- Simple federation, scalability and cloudbursting of private cloud infrastructures beyond a single cloud instance and data center


1.4.3 Examples of Provisioning Use Cases

The following are common enterprise use cases in large cloud computing deployments:

- **On-premise Private Clouds** Serving Multiple Projects, Departments, Units or Organizations. On-premise private clouds in large organizations require powerful and flexible mechanisms to manage the access privileges to the virtual and physical infrastructure and to dynamically allocate the available resources. In these scenarios, the Cloud Administrator would define a VDC for each Department, dynamically allocating resources according to their needs, and delegating the internal administration of the Group to the Department IT Administrator.
- **Cloud Providers** Offering Virtual Private Cloud Computing. Cloud providers providing customers with a fully-configurable and isolated environment where they have full control and capacity to administer its users and resources. This combines a public cloud with the control usually seen in a personal private cloud system.

For example, you can think Web Development, Human Resources, and Big Data Analysis as business units represented by Groups in a private OpenNebula cloud, and allocate them resources from your DCs and public clouds in order to create three different VDCs.

- **VDC BLUE:** VDC that allocates (ClusterA-DC_West_Coast + Cloudbursting) to Web Development
- **VDC RED:** VDC that allocates (ClusterB-DC_West_Coast + ClusterA-DC_Europe + Cloudbursting) to Human Resources
- **VDC GREEN:** VDC that allocates (ClusterC-DC_West_Coast + ClusterB-DC_Europe) to Big Data Analysis



1.4.4 Cloud Provisioning Scenarios

OpenNebula has three predefined User roles to implement three typical enterprise cloud scenarios:

- Data center infrastructure management
- Simple cloud provisioning model
- Advanced cloud provisioning model

In these three scenarios, Cloud Administrators manage the physical infrastructure, create Users and VDCs, prepare base templates and images for Users, etc.

Cloud Administrators typically access the cloud using the CLI or the Admin View of Sunstone.

Role	Capabilities
Cloud Admin.	<ul style="list-style-type: none"> • Operates the Cloud infrastructure (i.e. computing nodes, networking fabric, storage servers) • Creates and manages OpenNebula infrastructure resources: Hosts, Virtual Networks, Datastores • Creates and manages Multi-VM Applications (Services) • Creates new Groups and VDCs • Assigns Groups and physical resources to a VDC and sets quota limits • Defines base instance types to be used by the users. These types define the capacity of the VMs (memory, CPU and additional storage) and connectivity. • Prepare VM images to be used by the users • Monitor the status and health of the cloud • Generate activity reports

Data Center Infrastructure Management

This model is used to manage data center virtualization and to integrate and federate existing IT assets that can be in different data centers. In this usage model, Users are familiar with virtualization concepts. Except for the infrastructure resources, the web interface offers the same operations available to the Cloud Admin. These are “Advanced Users” that could be considered also as “Limited Cloud Administrators”.

Users can use the templates and images pre-defined by the cloud administrator, but usually are also allowed to create their own templates and images. They are also able to manage the life-cycle of their resources, including advanced features that may harm the VM guests, like hot-plugging of new disks, resize of Virtual Machines, modify boot parameters, etc.

Groups are used by the Cloud Administrator to isolate users, which are combined with VDCs to have allocated resources, but are not offered on-demand.

These “Advanced Users” typically access the cloud by using the CLI or the User View of Sunstone. This is not the default model configured for the group Users.

Role	Capabilities
Advanced User	<ul style="list-style-type: none"> • Instantiates VMs using their own templates • Creates new templates and images • Manages their VMs, including advanced life-cycle features • Creates and manages Multi-VM Application (Services) • Check their usage and quotas • Upload SSH keys to access the VMs

Simple Cloud Provisioning

In the simple infrastructure provisioning model, the Cloud offers infrastructure as a service to individual Users. Users are considered as “Cloud Users” or “Cloud Consumers”, being much more limited in their operations. These Users access a very intuitive simplified web interface that allows them to launch Virtual Machines from predefined Templates. They can access their VMs, and perform basic operations like shutdown. The changes made to a VM disk can be saved back, but new Images cannot be created from scratch.

Groups are used by the Cloud Administrator to isolate users, which are combined with VDCs to have allocated resources, but are not offered on-demand.

These “Cloud Users” typically access the cloud by using the Cloud View of Sunstone. This is the default model configured for the group Users.

Role	Capabilities
Cloud User	<ul style="list-style-type: none"> • Instantiates VMs using the templates defined by the Cloud Admins and the images defined by the Cloud Admins or Group Admins. • Instantiates VMs using their own Images saved from a previous running VM • Manages their VMs, including <ul style="list-style-type: none"> – reboot – power off/on (short-term switching-off) – delete – save a VM into a new Template – obtain basic monitor information and status (including IP addresses) • Delete any previous VM template and disk snapshot • Check user account usage and quotas • Upload SSH keys to access the VMs

Advanced Cloud Provisioning

The advanced provisioning model is an extension of the previous one where the cloud provider offers VDCs on demand to Groups of Users (projects, companies, departments or business units). Each Group can define one or more users as Group Admins. These admins can create new users inside the Group, and also manage the resources of the rest of the users. A Group Admin may, for example, shutdown a VM from other user to free group quota usage.

These Group Admins typically access the cloud by using the Group Admin View of Sunstone.

The Group Users have the capabilities described in the previous scenario and typically access the cloud by using the Cloud View of Sunstone.

Role	Capabilities
Group Admin.	<ul style="list-style-type: none"> • Creates new users in the Group • Operates on the Group’s virtual machines and disk images • Share Saved Templates with the members of the Group • Checks Group usage and quotas

OPENNEBULA INSTALLATION

2.1 Overview

The Frontend is the central part of an OpenNebula installation. This is the machine where the server software is installed and where you connect to manage your cloud. It can be a physical node or a virtual instance.

2.1.1 How Should I Read This Chapter

Before reading this chapter make sure you have read and understood the [Cloud Design](#) chapter.

The aim of this chapter is to give you a quick-start guide to deploy OpenNebula. This is the simplest possible installation, but it is also the foundation for a more complex setup, with Advanced Components (like Host and VM High Availability, Cloud Bursting, etc...).

First you should read the [Front-end Installation](#) section. Note that by default it uses an SQLite database that is not recommended for production. So, if this is not a small proof of concept, while following the Installation section you should use the [MySQL](#).

After reading this chapter, read the [Node Installation](#) chapter next in order to add hypervisors to your cloud.

2.1.2 Hypervisor Compatibility

Section	Compatibility
Front-end Installation	This Section applies to all hypervisors
MySQL Setup	This Section applies to all hypervisors
Scheduler	This Section applies to all hypervisors

2.2 Front-end Installation

This page shows you how to install OpenNebula from the binary packages.

Using the packages provided on our site is the recommended method, to ensure the installation of the latest version, and to avoid possible package divergences with different distributions. There are two alternatives here: you can add **our package repositories** to your system, or visit the [software menu](#) to **download the latest package** for your Linux distribution.

If there are no packages for your distribution, head to the Building from Source Code guide.

Note: Installing the frontend inside a LXD container is possible, however you will have limited functionality. The LXD marketplace shouldn't be usable in this situation. The frontend requires to mount a block device and this is not doable for a LXD container.

2.2.1 Step 1. SELinux on CentOS/RHEL

SELinux can block some operations initiated by the OpenNebula Front-end, which results in failures. If the administrator isn't experienced in SELinux configuration, **it's recommended to disable this functionality to avoid unexpected failures**. You can enable SELinux anytime later when you have the installation working.

Disable SELinux (recommended)

Change the following line in `/etc/selinux/config` to **disable** SELinux:

```
SELINUX=disabled
```

After the change, you have to reboot the machine.

Enable SELinux

Change the following line in `/etc/selinux/config` to **enable** SELinux in enforcing state:

```
SELINUX=enforcing
```

When changing from the disabled state, it's necessary to trigger filesystem relabel on the next boot by creating a file `/.autorelabel`, e.g.:

```
$ touch /.autorelabel
```

After the changes, you should reboot the machine.

Note: Follow the [SELinux User's and Administrator's Guide](#) for more information on how to configure and troubleshoot SELinux.

2.2.2 Step 2. Add OpenNebula Repositories

CentOS/RHEL

To add OpenNebula repository execute the following as root:

CentOS/RHEL 7

```
# cat << "EOT" > /etc/yum.repos.d/opennebula.repo
[opennebula]
name=opennebula
baseurl=https://downloads.opennebula.org/repo/5.10/CentOS/7/$basearch
enabled=1
gpgkey=https://downloads.opennebula.org/repo/repo.key
gpgcheck=1
```

```
repo_gpgcheck=1
EOT
```

CentOS/RHEL 8

```
# cat << "EOT" > /etc/yum.repos.d/opennebula.repo
[opennebula]
name=opennebula
baseurl=https://downloads.opennebula.org/repo/5.10/CentOS/8/$basearch
enabled=1
gpgkey=https://downloads.opennebula.org/repo/repo.key
gpgcheck=1
repo_gpgcheck=1
EOT
```

Debian/Ubuntu

To add OpenNebula repository on Debian/Ubuntu execute as root:

```
# wget -q -O- https://downloads.opennebula.org/repo/repo.key | apt-key add -
```

Debian 9

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Debian/9 stable opennebula" > /etc/apt/sources.list
```

Debian 10

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Debian/10 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 16.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/16.04 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 18.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/18.04 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 19.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/19.04 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 19.10

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/19.10 stable opennebula" > /etc/apt/sources.list
```

2.2.3 Step 3. Installing the Software

Installing on CentOS/RHEL

OpenNebula depends on packages which are not in the base repositories. The following repositories have to be enabled before installation:

- only RHEL 7: **optional** and **extras** RHEL repositories
- **EPEL** (Extra Packages for Enterprise Linux)

Repository EPEL

On **CentOS**, enabling EPEL is as easy as installation of the package with additional repository configuration:

```
# yum install epel-release
```

On **RHEL 7**, you enable EPEL by running:

Note: RHEL 7 **optional** and **extras** repositories must be configured first.

```
# subscription-manager repos --enable rhel-7-server-optional-rpms
# subscription-manager repos --enable rhel-7-server-extras-rpms
# rpm -ivh https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

On **RHEL 8**, you enable EPEL by running:

```
# rpm -ivh https://dl.fedoraproject.org/pub/epel/epel-release-latest-8.noarch.rpm
```

Install OpenNebula

Install the CentOS/RHEL OpenNebula Front-end with packages from **our repository** by executing the following as root:

```
# yum install opennebula-server opennebula-sunstone opennebula-ruby opennebula-gate
→opennebula-flow
```

CentOS/RHEL Package Description

The packages for the OpenNebula frontend and the virtualization host are as follows:

- **opennebula**: Command Line Interface.
- **opennebula-server**: Main OpenNebula daemon, scheduler, etc.
- **opennebula-sunstone**: *Sunstone* (the GUI) and the EC2 API.
- **opennebula-gate**: OneGate server that enables communication between VMs and OpenNebula.
- **opennebula-flow**: OneFlow manages services and elasticity.
- **opennebula-provision**: OneProvision deploys new clusters on remote bare-metal cloud providers.
- **opennebula-node-kvm**: Meta-package that installs the oneadmin user, libvirt and kvm.
- **opennebula-common**: Common files for OpenNebula packages.
- **opennebula-rubygems**: Metapackage with dependency on all required Ruby gems.
- **opennebula-rubygem-\$NAME**: Package with Ruby gem \$NAME.
- **opennebula-debuginfo**: Package with debug information.
- **opennebula-ruby**: Ruby Bindings.
- **opennebula-java**: Java Bindings.
- **python-pyone**: Python Bindings.
- **python3-pyone**: Python3 Bindings.

Note: The configuration files are located in /etc/one and /var/lib/one/remotes/etc.

Installing on Debian/Ubuntu

To install OpenNebula on a Debian/Ubuntu Front-end using packages from **our repositories** execute as root:

```
# apt-get update
# apt-get install opennebula opennebula-sunstone opennebula-gate opennebula-flow
```

Debian/Ubuntu Package Description

These are the packages available for these distributions:

- **opennebula**: OpenNebula Daemon.
- **opennebula-common**: Provides the user and common files.
- **opennebula-tools**: Command Line interface.
- **opennebula-sunstone**: *Sunstone* (the GUI).
- **opennebula-gate**: OneGate server that enables communication between VMs and OpenNebula.
- **opennebula-flow**: OneFlow manages services and elasticity.
- **opennebula-provision**: OneProvision deploys new clusters on remote bare-metal cloud providers.
- **opennebula-node**: Prepares a node as an opennebula KVM node.
- **opennebula-node-lxd**: Prepares a node as an opennebula LXD node.
- **opennebula-lxd-snap**: Installs LXD snap (only on Ubuntu 16.04 and 18.04).
- **opennebula-rubygems**: Metapackage with dependency on all required Ruby gems.
- **opennebula-rubygem-\$NAME**: Package with Ruby gem \$NAME.
- **opennebula-dbgsym**: Package with debug information.
- **ruby-opennebula**: Ruby API.
- **libopennebula-java**: Java API.
- **libopennebula-java-doc**: Java API Documentation.
- **python-pyone**: Python API.
- **python3-pyone**: Python3 Bindings.

Note: The configuration files are located in /etc/one and /var/lib/one/remotes/etc.

2.2.4 Step 4. Ruby Runtime Installation (Optional)

Warning: Since OpenNebula 5.10, this step is **optional** and all required Ruby gems are provided as a set of **opennebula-rubygem-\$NAME** packages and **opennebula-rubygems** metapackage. Ruby gems are installed into a dedicated directory /usr/share/one/gems-dist/, but OpenNebula uses them via (symlinked) location /usr/share/one/gems/ which points to the gems-dist/ directory. When the gems/ directory (by default) exists, OpenNebula uses the gems inside **exclusively** by removing any other system Ruby gems locations from the search paths!

```
# ls -lad /usr/share/one/gems*
lrwxrwxrwx 1 root root    9 Aug 13 11:41 /usr/share/one/gems -> gems-dist
drwxr-xr-x 9 root root 4096 Aug 13 11:41 /usr/share/one/gems-dist
```

If you want to use the system-wide Ruby gems instead of the packaged ones, remove the symlink `/usr/share/one/gems/` and install all required dependencies with the `install_gems` script described below. The removed `/usr/share/one/gems/` symlink **won't be created again on the next OpenNebula upgrade**. OpenNebula-shipped Ruby gems can't be uninstalled, but their use can be disabled by removing the `/usr/share/one/gems/` symlink.

If additional Ruby gems are needed by custom drivers or hooks, they must be installed into the introduced dedicated directory. For example, set gem name in `$GEM_NAME` and run under privileged user root:

```
# export GEM_PATH=/usr/share/one/gems/
# export GEM_HOME=/usr/share/one/gems/
# gem install --no-document --conservative $GEM_NAME
```

Some OpenNebula components need Ruby libraries. OpenNebula provides a script that installs the required gems as well as some development library packages needed.

As root execute:

```
# test -L /usr/share/one/gems && unlink /usr/share/one/gems
# /usr/share/one/install_gems
```

The previous script is prepared to detect common Linux distributions and install the required libraries. If it fails to find the packages needed in your system, manually install these packages:

- sqlite3 development library
- mysql client development library
- curl development library
- libxml2 and libxslt development libraries
- ruby development library
- gcc and g++
- make

If you want to install only a set of gems for a specific component, read [Building from Source Code](#) where it is explained in more depth.

2.2.5 Step 5. Enabling MySQL/MariaDB (Optional)

You can skip this step if you just want to deploy OpenNebula as quickly as possible. However if you are deploying this for production, or in a more serious environment, make sure you read the [MySQL Setup](#) section.

Note that it **is** possible to switch from SQLite to MySQL, but since it's more cumbersome to migrate databases, we suggest that, if in doubt, use MySQL from the start.

2.2.6 Step 6. Starting OpenNebula

Warning: If you are performing an upgrade, skip this and the next steps and go back to the upgrade document.

Log in as the `oneadmin` user follow these steps:

The `/var/lib/one/.one/one_auth` file will have been created with a randomly-generated password. It should contain the following: `oneadmin:<password>`. Feel free to change the password before starting OpenNebula. For example:

```
$ echo "oneadmin:mypassword" > ~/.one/one_auth
```

Warning: This will set the `oneadmin` password on the first boot. From that point, you must use the `oneuser passwd` command to change `oneadmin`'s password. More information on how to change the `oneadmin` password is [here](#).

You are ready to start the OpenNebula daemons. You can use `systemctl` for Linux distributions which have adopted `systemd`:

```
# systemctl start opennebula
# systemctl start opennebula-sunstone
```

Or use service in older Linux systems:

```
# service opennebula start
# service opennebula-sunstone start
```

Note: If OpenNebula services fail to start, check you

- followed [Step 4. Ruby Runtime Installation \(Optional\)](#),
- are not affected by known issue on Debian and Ubuntu.

2.2.7 Step 7. Verifying the Installation

After OpenNebula is started for the first time, you should check that the commands can connect to the OpenNebula daemon. You can do this in the Linux CLI or in the graphical user interface: Sunstone.

Linux CLI

In the Front-end, run the following command as `oneadmin`:

```
$ oneuser show
USER 0 INFORMATION
ID      : 0
NAME    : oneadmin
GROUP   : oneadmin
PASSWORD : 3bc15c8aae3e4124dd409035f32ea2fd6835efc9
AUTH_DRIVER : core
ENABLED  : Yes

USER TEMPLATE
TOKEN_PASSWORD="ec21d27e2fe4f9ed08a396cbd47b08b8e0a4ca3c"

RESOURCE USAGE & QUOTAS
```

If you get an error message, then the OpenNebula daemon could not be started properly:

```
$ oneuser show
Failed to open TCP connection to localhost:2633 (Connection refused - connect(2) for
↪"localhost" port 2633)
```

The OpenNebula logs are located in `/var/log/one`. You should have at least the files `oned.log` and `sched.log`, the core and scheduler logs. Check `oned.log` for any error messages, marked with [E].

Sunstone

Now you can try to log in to Sunstone web interface. To do this, point your browser to `http://<frontend_address>:9869`. If everything is OK you will be greeted with a login page. The user is `oneadmin` and the password is the one in the file `/var/lib/one/.one/one_auth` in your Front-end.

If the page does not load, make sure you check `/var/log/one/sunstone.log` and `/var/log/one/sunstone.error`. Also, make sure TCP port 9869 is allowed through the firewall.

Directory Structure

The following table lists some notable paths that are available in your Frontend after the installation:

Path	Description
<code>/etc/one/</code>	Configuration Files
<code>/var/log/one/</code>	Log files, notably: <code>oned.log</code> , <code>sched.log</code> , <code>sunstone.log</code> and <code><vmid>.log</code>
<code>/var/lib/one/</code>	<code>oneadmin</code> home directory
<code>/var/lib/one/datastores/<dsid>/</code>	Storage for the datastores
<code>/var/lib/one/vms/<vmid>/</code>	Action files for VMs (deployment file, transfer manager scripts, etc...)
<code>/var/lib/one/.one/one_auth</code>	<code>oneadmin</code> credentials
<code>/var/lib/one/remotes/</code>	Probes and scripts that will be synced to the Hosts
<code>/var/lib/one/remotes/hooks/</code>	Hook scripts
<code>/var/lib/one/remotes/vmm/</code>	Virtual Machine Manager Driver scripts
<code>/var/lib/one/remotes/auth/</code>	Authentication Driver scripts
<code>/var/lib/one/remotes/im/</code>	Information Manager (monitoring) Driver scripts
<code>/var/lib/one/remotes/market/</code>	MarketPlace Driver scripts
<code>/var/lib/one/remotes/datastore/</code>	Datastore Driver scripts
<code>/var/lib/one/remotes/vnm/</code>	Networking Driver scripts
<code>/var/lib/one/remotes/tm/</code>	Transfer Manager Driver scripts

Firewall configuration

The list below shows the ports used by OpenNebula. These ports need to be open for OpenNebula to work properly:

Port	Description
9869	Sunstone server.
29876	VNC proxy port, used for translating and redirecting VNC connections to the hypervisors.
2633	OpenNebula daemon, main XML-RPC API endpoint.
2474	OneFlow server. This port only needs to be opened if OneFlow server is used.
5030	OneGate server. This port only needs to be opened if OneGate server is used.

OpenNebula connects to the hypervisors through ssh (port 22). Additionally oneed may connect to the OpenNebula Marketplace (<https://marketplace.opennebula.systems/>) and Linux Containers Marketplace (<https://images.linuxcontainers.org>) to get a list of available appliances. You should open outgoing connections to these ports and protocols. Note: These are the default ports; each component can be configured to bind to specific ports or use an HTTP Proxy.

2.2.8 Step 8. Next steps

Now that you have successfully started your OpenNebula service, head over to the [Node Installation](#) chapter in order to add hypervisors to your cloud.

Note: To change oneadmin password, follow the next steps:

```
#oneuser passwd 0 <PASSWORD>
#echo 'oneadmin:PASSWORD' > /var/lib/one/.one/one_auth
```

Test that everything works using *oneuser show*.

2.3 MySQL Setup

The MySQL/MariaDB back-end is an alternative to the default SQLite back-end. In this guide and in the rest of OpenNebula's documentation and configuration files we will refer to this database as MySQL. However, OpenNebula can use either MySQL or MariaDB.

The two back-ends cannot coexist (SQLite and MySQL), and you will have to decide which one is going to be used while planning your OpenNebula installation.

Note: If you are planning to install OpenNebula with MySQL back-end, please follow this guide *prior* to starting OpenNebula the first time to avoid problems with oneadmin and serveradmin credentials.

2.3.1 Installation

First of all, you need a working MySQL server. You can either deploy one for the OpenNebula installation or reuse any existing MySQL already deployed and accessible by the Frontend.

Configuring MySQL

You need to add a new user and grant it privileges on the `opennebula` database. This new database doesn't need to exist as OpenNebula will create it the first time it runs.

Assuming you are going to use the default values, log in to your MySQL server and issue the following commands:

```
$ mysql -u root -p
Enter password:
Welcome to the MySQL monitor. [...]

mysql> GRANT ALL PRIVILEGES ON opennebula.* TO 'oneadmin' IDENTIFIED BY '<thepassword>
˓→';
Query OK, 0 rows affected (0.00 sec)
```

Visit the [MySQL documentation](#) to learn how to manage accounts.

Now configure the transaction isolation level:

```
mysql> SET GLOBAL TRANSACTION ISOLATION LEVEL READ COMMITTED;
```

Configuring OpenNebula

Before you run OpenNebula for the first time, you need to set in the *oned.configuration* the connection details, and the database you have granted privileges on.

```
# Sample configuration for MySQL
DB = [ backend = "mysql",
       server = "localhost",
       port   = 0,
       user   = "oneadmin",
       passwd = "<thepassword>",
       db_name = "opennebula" ]
```

Fields:

- **server**: URL of the machine running the MySQL server.
- **port**: port for the connection to the server. If set to 0, the default port is used.
- **user**: MySQL user-name.
- **passwd**: MySQL password.
- **db_name**: Name of the MySQL database OpenNebula will use.

2.3.2 Using OpenNebula with MySQL

After this installation and configuration process you can use OpenNebula as usual.

2.3.3 MySQL database maintenance

For an optimal database performance improvement there are some tasks that should be done periodically, depending on the load of the environment. They are listed below.

Search index

In order to be able to search for VMs by different attributes, OpenNebula's database has an [FTS index](#). The size of this index can increase fast, depending on the cloud load. To free some space, perform the following maintenance task periodically:

```
alter table vm_pool drop index ftidx;
alter table vm_pool add fulltext index ftidx (search_token);
```

VMs in DONE state

When a VM is terminated, OpenNebula changes its state to DONE but it keeps the VM in the database in case the VM information is required in the future (e.g. to generate accounting reports). In order to reduce the size of the VM table, it is recommended to periodically delete the VMs in the DONE state when not needed. For this task the [onedb purge-done](#) tool is available.

NODE INSTALLATION

3.1 Overview

After the OpenNebula Front-end is correctly setup the next step is preparing the hosts where the VMs are going to run.

3.1.1 How Should I Read This Chapter

Make sure you have properly *installed the Front-end* before reading this chapter.

This chapter focuses on the minimal node installation you need to follow in order to finish deploying OpenNebula. Concepts like storage and network have been simplified. Therefore feel free to follow the other specific chapters in order to configure other subsystems.

Note that you can follow this chapter without reading any other guides and you will be ready, by the end of it, to deploy a Virtual Machine. If in the future you want to switch to other storage or networking technologies you will be able to do so.

After installing the nodes and *verifying your installation*, you can either start using your cloud or configure more components:

- *Authenticaton*. (Optional) For integrating OpenNebula with LDAP/AD, or securing it further with other authentication technologies.
- *Sunstone*. The OpenNebula GUI should be working and accessible at this stage, but by reading this guide you will learn about specific enhanced configurations for Sunstone.

3.1.2 Hypervisor Compatibility

Section	Compatibility
<i>KVM Node Installation</i>	This Section applies to KVM.
<i>LXD Node Installation</i>	This Section applies to LXD.
<i>vCenter Node Installation</i>	This Section applies to vCenter.
<i>Verify your Installation</i>	This Section applies to vCenter, KVM and LXD.

If your cloud is KVM or LXD based you should also follow:

- *Open Cloud Host Setup*.
- *Open Cloud Storage Setup*.
- *Open Cloud Networking Setup*.

Otherwise, if it's VMware based:

- Head over to the [VMware Infrastructure Setup](#) chapter.

3.2 KVM Node Installation

This page shows you how to install OpenNebula from the binary packages.

Using the packages provided on our site is the recommended method, to ensure the installation of the latest version and to avoid possible package divergences in different distributions. There are two alternatives here: you can add **our package repositories** to your system, or visit the [software menu](#) to **download the latest package** for your Linux distribution.

3.2.1 Step 1. Add OpenNebula Repositories

CentOS/RHEL

To add OpenNebula repository execute the following as root:

CentOS/RHEL 7

```
# cat << "EOT" > /etc/yum.repos.d/opennebula.repo
[opennebula]
name=opennebula
baseurl=https://downloads.opennebula.org/repo/5.10/CentOS/7/$basearch
enabled=1
gpgkey=https://downloads.opennebula.org/repo/repo.key
gpgcheck=1
repo_gpgcheck=1
EOT
```

CentOS/RHEL 8

```
# cat << "EOT" > /etc/yum.repos.d/opennebula.repo
[opennebula]
name=opennebula
baseurl=https://downloads.opennebula.org/repo/5.10/CentOS/8/$basearch
enabled=1
gpgkey=https://downloads.opennebula.org/repo/repo.key
gpgcheck=1
repo_gpgcheck=1
EOT
```

Debian/Ubuntu

To add OpenNebula repository on Debian/Ubuntu execute as root:

```
# wget -q -O- https://downloads.opennebula.org/repo/repo.key | apt-key add -
```

Debian 9

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Debian/9 stable opennebula" > /etc/apt/sources.list
```

Debian 10

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Debian/10 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 16.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/16.04 stable opennebula" > /etc/apt/sources.list
```

Ubuntu 18.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/18.04 stable opennebula" > /etc/apt/sources.list.d/opennebula.list
```

Ubuntu 19.04

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/19.04 stable opennebula" > /etc/apt/sources.list.d/opennebula.list
```

Ubuntu 19.10

```
# echo "deb https://downloads.opennebula.org/repo/5.10/Ubuntu/19.10 stable opennebula" > /etc/apt/sources.list.d/opennebula.list
```

3.2.2 Step 2. Installing the Software

Installing on CentOS/RHEL

Execute the following commands to install the node package and restart libvirt to use the OpenNebula provided configuration file:

```
$ sudo yum install opennebula-node-kvm
$ sudo systemctl restart libvirtd
```

Newer QEMU/KVM (only CentOS/RHEL 7)

You may benefit from using the more recent and feature-rich enterprise QEMU/KVM release. The differences between the base (`qemu-kvm`) and enterprise (`qemu-kvm-rhev` on RHEL or `qemu-kvm-ev` on CentOS) packages are described on the [Red Hat Customer Portal](#).

On **CentOS 7**, the enterprise packages are part of the separate repository. To replace the base packages, follow these steps:

```
$ sudo yum install centos-release-qemu-ev
$ sudo yum install qemu-kvm-ev
```

On **RHEL 7**, you need a paid subscription to the Red Hat Virtualization (RHV) or Red Hat OpenStack (RHOS) products license only for the Red Hat Enterprise Linux isn't enough! You have to check the RHV [Installation Guide](#) for your licensed version. Usually, the following commands should enable and install the enterprise packages:

```
$ sudo subscription-manager repos --enable rhel-7-server-rhv-4-mgmt-agent-rpms
$ sudo yum install qemu-kvm-rhev
```

For further configuration, check the specific guide: [KVM](#).

Installing on Debian/Ubuntu

Execute the following commands to install the node package and restart libvirt to use the OpenNebula-provided configuration file:

```
$ sudo apt-get update
$ sudo apt-get install opennebula-node
$ sudo service libvirtd restart # debian
$ sudo service libvirt-bin restart # ubuntu
```

For further configuration check the specific guide: [KVM](#).

3.2.3 Step 3. SELinux on CentOS/RHEL

Warning: If you are performing an upgrade skip this and the next steps and go back to the upgrade document.

SELinux can block some operations initiated by the OpenNebula Front-end, resulting in all the node operations failing completely (e.g., when the `oneadmin` user's SSH credentials are not trusted) or only individual failures for particular operations with virtual machines. If the administrator isn't experienced in SELinux configuration, **it's recommended to disable this functionality to avoid unexpected failures**. You can enable SELinux anytime later when you have the installation working.

Disable SELinux (recommended)

Change the following line in `/etc/selinux/config` to **disable** SELinux:

```
SELINUX=disabled
```

After the change, you have to reboot the machine.

Enable SELinux

Change the following line in `/etc/selinux/config` to enable SELinux in `enforcing` state:

```
SELINUX=enforcing
```

When changing from the `disabled` state, it's necessary to trigger filesystem relabel on the next boot by creating a file `/.autorelabel`, e.g.:

```
$ touch /.autorelabel
```

After the changes, you should reboot the machine.

Note: Depending on your OpenNebula deployment type, the following may be required on your SELinux-enabled KVM nodes:

- package `util-linux` newer than 2.23.2-51 installed
- SELinux boolean `virt_use_nfs` enabled (with datastores on NFS):

```
$ sudo setsebool -P virt_use_nfs on
```

Follow the [SELinux User's and Administrator's Guide](#) for more information on how to configure and troubleshoot SELinux.

3.2.4 Step 4. Configure Passwordless SSH

The OpenNebula Front-end connects to the hypervisor Hosts using SSH. You must distribute the public key of the `oneadmin` user from all machines to the file `/var/lib/one/.ssh/authorized_keys` in all the machines. There are many methods to achieve the distribution of the SSH keys. Ultimately the administrator should choose a method; the recommendation is to use a configuration management system. In this guide we are going to manually `scp` the SSH keys.

When the package was installed in the Front-end, an SSH key was generated and the `authorized_keys` populated. We will sync the `id_rsa`, `id_rsa.pub` and `authorized_keys` from the Front-end to the nodes. Additionally we need to create a `known_hosts` file and sync it as well to the nodes. To create the `known_hosts` file, we have to execute this command as user `oneadmin` in the Front-end with all the node names and the Front-end name as parameters:

```
$ ssh-keyscan <frontend> <node1> <node2> <node3> ... >> /var/lib/one/.ssh/known_hosts
```

Now we need to copy the directory `/var/lib/one/.ssh` to all the nodes. The easiest way is to set a temporary password for `oneadmin` in all the hosts and copy the directory from the Front-end:

```
$ scp -rp /var/lib/one/.ssh <node1>:/var/lib/one/
$ scp -rp /var/lib/one/.ssh <node2>:/var/lib/one/
$ scp -rp /var/lib/one/.ssh <node3>:/var/lib/one/
$ ...
```

You should verify that connecting from the Front-end, as user `oneadmin`, to the nodes and the Front-end itself, and from the nodes to the Front-end, does not ask for a password:

```
$ ssh <frontend>
$ exit

$ ssh <node1>
$ ssh <frontend>
$ exit
$ exit

$ ssh <node2>
$ ssh <frontend>
$ exit
$ exit


$ ssh <node3>
$ ssh <frontend>
$ exit
$ exit
```

If an extra layer of security is needed, it's possible to keep the private key just at the frontend node instead of copying it to all the hypervisors. In this fashion the `oneadmin` user in the hypervisors won't be able to access other hypervisors. This is achieved by modifying the `/var/lib/one/.ssh/config` in the front-end and adding the `ForwardAgent` option to the hypervisor hosts for forwarding the key:

```
$cat /var/lib/one/.ssh/config
Host host1
  User oneadmin
  ForwardAgent yes
Host host2
  User oneadmin
  ForwardAgent yes
```

Note: Remember that is necessary to have `ssh-agent` running with the corresponding private key imported before OpenNebula is started. You can start `ssh-agent` by running `eval "$(ssh-agent -s)"` and add the private key by running `ssh-add /var/lib/one/.ssh/id_rsa`.

3.2.5 Step 5. Networking Configuration



A network connection is needed by the OpenNebula Front-end daemons to access the hosts to manage and monitor the Hosts, and to transfer the Image files. It is highly recommended to use a dedicated network for this purpose.

There are various network models. Please check the [Networking](#) chapter to find out the networking technologies supported by OpenNebula.

You may want to use the simplest network model, that corresponds to the [bridged](#) driver. For this driver, you will need to setup a Linux bridge and include a physical device in the bridge. Later on, when defining the network in OpenNebula, you will specify the name of this bridge and OpenNebula will know that it should connect the VM to this bridge, thus giving it connectivity with the physical network device connected to the bridge. For example, a typical host with two physical networks, one for public IP addresses (attached to an `eth0` NIC for example) and the other for private virtual LANs (NIC `eth1` for example) should have two bridges:

```
$ ip link show type bridge
4: br0: ...
5: br1: ...

$ ip link show master br0
2: eth0: ...

$ ip link show master br1
3: eth1: ...
```

Note: Remember that this is only required in the Hosts, not in the Front-end. Also remember that the exact name of the resources is not important (`br0`, `br1`, etc...), however it's important that the bridges and NICs have the same name in all the Hosts.

3.2.6 Step 6. Storage Configuration

You can skip this step entirely if you just want to try out OpenNebula, as it will come configured by default in such a way that it uses the local storage of the Front-end to store Images, and the local storage of the hypervisors as storage for the running VMs.

However, if you want to set-up another storage configuration at this stage, like Ceph, NFS, LVM, etc, you should read the *Open Cloud Storage* chapter.

3.2.7 Step 7. Adding a Host to OpenNebula

In this step we will register the node we have installed in the OpenNebula Front-end, so OpenNebula can launch VMs in it. This step can be done in the CLI or in Sunstone, the graphical user interface. Follow just one method, not both, as they accomplish the same.

To learn more about the host subsystem, read this guide.

Adding a Host through Sunstone

Open Sunstone as documented [here](#). In the left side menu go to Infrastructure -> Hosts. Click on the + button.

Then fill-in the fqdn of the node in the Hostname field.

OpenNebula

Create Host

Dashboard Instances Templates Storage Network Infrastructure System Settings

Type: KVM Cluster: 0: default

Hostname: node01

Officially supported Not connected Sign in

OpenNebula 5.10.5 by OpenNebula Systems.

Finally, return to the Hosts list, and check that the Host has switched to ON status. It should take somewhere between 20s to 1m. Try clicking on the refresh button to check the status more frequently.

OpenNebula

Hosts

Dashboard Instances Templates Storage Network Infrastructure System Settings

+ Select cluster Enable Disable Offline Search

ID	Name	Cluster	RVMs	Allocated CPU	Allocated MEM	Status
0	node01	0	0	0 / 800 (0%)	0KB / 16GB (0%)	ON

Showing 1 to 1 of 1 entries Previous 1 Next

1 TOTAL 1 ON 0 OFF 0 ERROR

Officially supported Not connected Sign in

OpenNebula 5.10.5 by OpenNebula Systems.

If the host turns to err state instead of on, check `/var/log/one/oned.log`. Chances are it's a problem with SSH!

Adding a Host through the CLI

To add a node to the cloud, run this command as `oneadmin` in the Front-end:

```
$ onehost create <node01> -i kvm -v kvm

$ onehost list
  ID NAME          CLUSTER   RVM      ALLOCATED_CPU      ALLOCATED_MEM STAT
  1 localhost      default    0          -                  - init

# After some time (20s - 1m)

$ onehost list
  ID NAME          CLUSTER   RVM      ALLOCATED_CPU      ALLOCATED_MEM STAT
  0 node01         default    0        0 / 400 (0%)    OK / 7.7G (0%) on
```

If the host turns to `err` state instead of `on`, check `/var/log/one/oned.log`. Chances are it's a problem with SSH!

3.2.8 Step 8. Import Currently Running VMs (Optional)

You can skip this step, as importing VMs can be done at any moment. However, if you wish to see your previously-deployed VMs in OpenNebula you can use the import VM functionality.

3.2.9 Step 9. Next steps

You can now jump to the optional *Verify your Installation* section in order to launch a test VM.

Otherwise, you are ready to start using your cloud or you could configure more components:

- *Authentication*. (Optional) For integrating OpenNebula with LDAP/AD, or securing it further with other authentication technologies.
- *Sunstone*. The OpenNebula GUI should be working and accessible at this stage, but by reading this guide you will learn about specific enhanced configurations for Sunstone.
- *Open Cloud Host Setup*.
- *Open Cloud Storage Setup*.
- *Open Cloud Networking Setup*.

3.3 LXD Node Installation

The majority of the steps needed to install the LXD node are similar to KVM because both rely on a Linux OS. Similar steps will have a link in the name and will be indicated by “**Same as KVM**”.

3.3.1 Step 1. Add OpenNebula Repositories

Same as KVM

3.3.2 Step 2. Installing the Software

LXD nodes are only supported on Ubuntu **16.04, 18.04, 19.04, 19.10** and **Debian 10**.

Warning: Only LXD 3.0.x releases are supported, LXD 2.x and older are not compatible.

Installing on Ubuntu

It's recommended to use LXD shipped as a distribution package (via APT) on Ubuntu 16.04 and 18.04 whenever possible as snap may be broken for oneadmin when using the LXC CLI, and snap based installations are automatically refreshed whenever there is an update available on the channel. Since Ubuntu 18.10, LXD is shipped only as a snap and managed by a distribution transitional package.

Note: Since OpenNebula 5.8.2. New meta-package **opennebula-lxd-snap** is provided for Ubuntu 16.04 and 18.04 to manage the LXD snap installation. Users can choose between LXD shipped as a distribution package **lxd** or the LXD snap installed with **opennebula-lxd-snap** by manually installing the preferred one in advance. **When no package is chosen, the packaged LXD is used even though there is an existing snap installation!** On Ubuntu 18.10, the LXD snap installation is done directly by **opennebula-node-lxd**. Please note we don't overwrite any already installed LXD snap.

Warning: LXD versions packaged in Ubuntu:

- Ubuntu 16.04 — **incompatible LXD 2.0**, in xenial-backports LXD 3.0
- Ubuntu 18.04 — LXD 3.0
- Ubuntu >= 19.04 — lxd is a transitional package to install the LXD snap (3.0/stable channel)

On **Ubuntu 16.04** you have to enable **xenial-backports** with regular priority to have access to the supported package with LXD 3.0!

Check the deployment options below and handle carefully the installation in the environments where LXD is already installed and used!

Ubuntu 16.04

```
$ sudo apt-get install opennebula-node-lxd
```

or, use LXD installed as snap (**since OpenNebula 5.8.2**):

```
$ sudo apt-get install opennebula-lxd-snap opennebula-node-lxd
```

Ubuntu 18.04

```
$ sudo apt-get install opennebula-node-lxd
```

or, use LXD installed as snap (**since OpenNebula 5.8.2**):

```
$ sudo apt-get install opennebula-lxd-snap opennebula-node-lxd
```

Ubuntu >= 19.04 and Debian >= 10

```
$ sudo apt-get install opennebula-node-lxd
```

Optionals for all

To be able to use the Ceph storage drivers, you might need to install an additional package with command:

```
$ sudo apt-get install rbd-nbd
```

For further configuration check the specific guide: [LXD](#).

3.3.3 Step 4. Configure Passwordless SSH

Same as KVM

3.3.4 Step 5. Networking Configuration

Same as KVM

3.3.5 Step 6. Storage Configuration

Same as KVM

3.3.6 Step 7. Adding a Host to OpenNebula

Same as KVM

Replace kvm for lxd in the CLI and Sunstone

3.3.7 Step 8. Import Existing Containers (Optional)

You can use the import VM functionality if you want to manage pre-existing containers. It is required that containers aren't named under the pattern `one-<id>` in order to be imported. They need also to have `limits.cpu`, `allowance`, `limits.cpu` and `limits.memory` keys defined, otherwise OpenNebula cannot import them. The `opennebula-node-lxd` package should setup the default template with these values.

3.3.8 Step 9. Next steps

Same as KVM

3.4 vCenter Node Installation

This Section lays out the configuration requirements needed in the vCenter and ESX instances in order to be managed by OpenNebula.

The VMware vCenter drivers enable OpenNebula to access one or more vCenter servers that manage one or more ESX Clusters. Each ESX Cluster is presented in OpenNebula as an aggregated hypervisor, i.e. as an OpenNebula Host. This means that the representation is one OpenNebula Host per ESX Cluster.

Note that OpenNebula scheduling decisions are therefore made at ESX Cluster level. vCenter then uses the DRS component to select the actual ESX host and Datastore to deploy the Virtual Machine.

3.4.1 Requirements

The following must be met for a functional vCenter environment:

- Supported vSphere version (check Platform Notes) with at least one cluster aggregating at least one ESX.
- Define a vCenter user for OpenNebula. This vCenter user (let's call her `oneadmin`) needs to have access to the ESX clusters that OpenNebula will manage. In order to avoid problems, the hassle free approach is to **declare this `oneadmin` user as Administrator**. However, in some enterprise environments declaring the user as Administrator is not allowed. In that case, you will need to grant permissions to perform some tasks. A table with the permissions required is found at the end of this chapter.
- All ESX hosts belonging to the same ESX cluster to be exposed to OpenNebula **must** share at least one datastore among them.
- The ESX cluster **should** have DRS enabled. DRS is not required but it is recommended. As OpenNebula does not schedule to the granularity of ESX hosts, DRS is needed to select the actual ESX host within the cluster, otherwise the VM will be launched in the ESX where the VM template has been created.
- If virtual standard switches are used, check that those switches exist in every ESX host belonging to the same ESX cluster, so the network represented by a port group can be used by a VM, no matter in what ESX host it's running. If you use distributed virtual switches, check that ESX hosts have been added to switches.
- To enable VNC functionality, please check the detailed information in section [VNC on ESX hosts](#) below.

Important: OpenNebula will **NOT** modify any vCenter configuration with some exceptions, the creation of virtual switches and port groups if the vcenter network driver is used, and the creation of images for VMDK and/or ISO files.

Note: For security reasons, you may define different users to access different ESX Clusters. A different user can be defined in OpenNebula per ESX cluster, which is encapsulated in OpenNebula as an OpenNebula host.

3.4.2 Configuration

There are a few simple steps needed to configure OpenNebula so it can interact with vCenter:

Step 1: Check connectivity

The OpenNebula Front-end needs network connectivity to all the vCenters that it is supposed to manage.

Additionally, to enable VNC access to the spawned Virtual Machines, the Front-end also needs network connectivity to all the ESX hosts

Warning: OpenNebula uses port 443 to communicate with vCenter instances. Port 443 is the default port used by vCenter, so unless you're filtering that port, or you've configured a different port to listen for connections from the vSphere Web Client, OpenNebula will be able to connect with the right credentials.

Step 2: Configure the drivers in the Front-end (`oned.conf`) [Optional]

The following sections in the `/etc/one/oned.conf` file describe the information and virtualization drivers for vCenter, which are enabled by default:

```

#-----
# vCenter Information Driver Manager Configuration
#   -r number of retries when monitoring a host
#   -t number of threads, i.e. number of hosts monitored at the same time
#-----
IM_MAD = [
    NAME          = "vcenter",
    SUNSTONE_NAME = "VMWare vCenter",
    EXECUTABLE    = "one_im_sh",
    ARGUMENTS     = "-c -t 15 -r 0 vcenter" ]
#-----

#-----
# vCenter Virtualization Driver Manager Configuration
#   -r number of retries when monitoring a host
#   -t number of threads, i.e. number of hosts monitored at the same time
#   -p more than one action per host in parallel, needs support from hypervisor
#   -s <shell> to execute commands, bash by default
#   -d default snapshot strategy. It can be either 'detach' or 'suspend'. It
#       defaults to 'suspend'.
#-----
VM_MAD = [
    NAME          = "vcenter",
    SUNSTONE_NAME = "VMWare vCenter",
    EXECUTABLE    = "one_vmm_sh",
    ARGUMENTS     = "-p -t 15 -r 0 vcenter -s sh",
    default       = "vmm_exec/vmm_exec_vcenter.conf",
    TYPE          = "xml",
    IMPORTED_VMS_ACTIONS = "terminate, terminate-hard, hold, release, suspend,
                            resume, delete, reboot, reboot-hard, resched, unresched, poweroff,
                            poweroff-hard, disk-attach, disk-detach, nic-attach, nic-detach,
                            snap-create, snap-delete"
]
#-----
```

As a Virtualization driver, the vCenter driver accepts a series of parameters that control its execution. The parameters allowed are:

parameter	description
-r <num>	number of retries when executing an action
-t <num>	number of threads, i.e. number of actions done at the same time

See the Virtual Machine drivers reference for more information about these parameters, and how to customize and extend the drivers.

Additionally some behavior of the vCenter driver can be configured in the /var/lib/one/remotes/etc/vmm/vcenter/vcenterrc. The parameters that can be changed here are as follows:

parameter	description
:delete_image	Yes : You can delete the images using OpenNebula. No : VCENTER_IMPORTED attribute will be set on imported images. This attribute prevents the image being deleted.

OpenNebula needs to be restarted after any change in the /etc/one/oned.conf file. This can be done with the following command:

```
$ sudo systemctl restart opennebula
```

Step 3: Importing vCenter Clusters

OpenNebula ships with a powerful CLI tool to import vCenter clusters, VM Templates, Networks and running VMs. The tool **onecenter** is self-explanatory, just set the credentials and FQDN/IP to access the vCenter host and follow on screen instructions.

If you need to know how to import vCenter clusters, check [vCenter import tool](#).

Once the vCenter cluster is monitored successfully, ON will show as the host status. If ERROR is shown please check connectivity and have a look to the `/var/log/one/oned.log` file in order to find out the possible cause.

The following variables are added to OpenNebula hosts representing ESX clusters:

Operation	Note
VCENTER_HOST	hostname or IP of the vCenter host
VCENTER_USER	Name of the vCenter user
VCENTER_PASSWORD	Password of the vCenter user
VCENTER_VERSION	The vcenter version detected by OpenNebula e.g 5.5
VCENTER_CCR_REF	The Managed Object Reference to the vCenter cluster
VCENTER_INSTANCE_ID	The vCenter instance UUID identifier

Note: OpenNebula will create a special key at boot time and save it in `/var/lib/one/.one/one_key`. This key will be used as a private key to encrypt and decrypt all the passwords for all the vCenters that OpenNebula can access. Thus, the password shown in the OpenNebula host representing the vCenter is the original password encrypted with this special key.

Note: You have more information about what is a Managed Object Reference and what is the vCenter instance UUID in the vCenter driver section.

Step 4: Next Steps

Jump to the [Verify your Installation](#) section in order to launch a VM or learn how to setup the [VMWare infrastructure](#).

3.4.3 Permissions requirement

If the user account that is going to be used in vCenter operations is not declared as an Administrator the following table summarizes the privileges required by the tasks performed in vCenter by OpenNebula:

Privileges ID	Privilege name	Notes
Datastore.AllocateSpace	Allocate space	On all VMFS datastores represented by C
Datastore.Browse	Browse datastore	On all VMFS datastores represented by C
Datastore.FileManagement	Low level file operations	On all VMFS datastores represented by C
Datastore.Delete	Remove datastore	On all VMFS datastores represented by C
DVPortgroup.Create	Create	Required if you want OpenNebula to crea

Table 3.1 – continued from previous page

DVPortgroup.Delete	Delete	Required if you want OpenNebula to des
DVPortgroup.Modify	Modify	Required if you want OpenNebula to crea
DVSwitch.Create	Create	Required if you want OpenNebula to crea
DVSwitch.Delete	Delete	Required if you want OpenNebula to des
DVSwitch.HostOp	Host operation	Required if you want OpenNebula to crea
DVSwitch.Modify	Modify	Required if you want OpenNebula to crea
DVSwitch.PortSetting	Port setting operation	Required if you want OpenNebula to crea
Host.Config.Network	Network configuration	Required an all ESX hosts where you wa
Network.Assign	Assign network	Required on any network the Virtual Ma
Resource.ApplyRecommendation	Apply recommendation	On all Storage Pods (Storage DRS cluste
Resource.AssignVMToPool	Assign virtual machine to resource pool	Required to assign a resource pool to a vi
Resource.ColdMigrate	Migrate powered off virtual machine	Required to migrate powered off virtual
Resource.HotMigrate	Migrate powered on virtual machine	Required to migrate powered on virtual
System.Read	Read	Required to rename Uplink port group fo
VirtualMachine.Config.AddExistingDisk	Add existing disk	Required to browse for and attach an exis
VirtualMachine.Config.AddNewDisk	Add new disk	Required to create and attach a new virtua
VirtualMachine.Config.AddRemoveDevice	Add or remove device	Required to add or remove virtual devices
VirtualMachine.Config.AdvancedConfig	Advanced	Required to make advanced configuration
VirtualMachine.Config.Annotation	Set annotation	Required to set annotation on a virtual ma
VirtualMachine.Config.ChangeTracking	Disk change tracking	Required to enable or disable change tra
VirtualMachine.Config.CPUCount	Change CPU count	Required to change the number of virtual
VirtualMachine.Config.DiskExtend	Extend virtual disk	Required to extend virtual disk
VirtualMachine.Config.HostUSBDevice	Host USB device	Required to add, remove or edit a virtual
VirtualMachine.Config.Memory	Memory	Required to set the amount of virtual ma
VirtualMachine.Config.RawDevice	Raw device	Required to virtual machine raw device c
VirtualMachine.Config.RemoveDisk	Remove disk	Required to detach and optionally remova
VirtualMachine.Config.Rename	Rename	Required to rename a virtual machine
VirtualMachine.Config.Settings	Settings	Required to change virtual machine settin
VirtualMachine.Config.SwapPlacement	Swapfile placement	Required to set the placement policy for s
VirtualMachine.Interact.DeviceConnection	Device connection	Required to Connect/disconnect media an
VirtualMachine.Interact.PowerOff	Power Off	Required to power off or shutdown a virtu
VirtualMachine.Interact.PowerOn	Power On	Required to power on or resume a virtual
VirtualMachine.Interact.Reset	Reset	Reset (power cycle) a virtual machine
VirtualMachine.Interact.SetCDMedia	Configure CD media	Configure a different media for virtual CD
VirtualMachine.Interact.SetFloppyMedia	Configure floppy media	Required to Configure a different
VirtualMachine.Interact.Suspend	Suspend	Required to suspend a virtual machine
VirtualMachine.Inventory.Create	Create new	Required to create a new virtual machine
VirtualMachine.Inventory.CreateFromExisting	Create from existing	Required to create a virtual machine base
VirtualMachine.Inventory.Delete	Remove	Required to remove a virtual machine
VirtualMachine.Inventory.Move	Move	Required to move a virtual machine
VirtualMachine.Inventory.Register	Register	Required to add an existing virtual machi
VirtualMachine.Inventory.Unregister	Unregister	Required to unregister a virtual machine
VirtualMachine.Provisioning.CloneTemplate	Clone template	Required to clone a template
VirtualMachine.Provisioning.DeployTemplate	Deploy template	Required to deploy a virtual machine fro
VirtualMachine.Provisioning.ReadCustSpecs	Read customization specifications	Required to read customization specificat
VirtualMachine.State.CreateSnapshot	Create snapshot	Required to create a new snapshot of a vi
VirtualMachine.State.RemoveSnapshot	Remove snapshot	Required to remove snapshots from a virt
VirtualMachine.State.RevertToSnapshot	Revert to snapshot	Required to revert a virtual machine to a

Special Permission

The above permissions, except one, can be set at the Cluster level. However, OpenNebula needs access to the Customization spec for successful monitoring. This is a special privilege because it needs to be applied to vCenter server level. It means that if you try to apply the previous privileges into a cluster/datacenter and their inheritors, OpenNebula will fail and it will tell you that higher level permissions are necessary.

Our recommended approach is to create two roles, one for the general permissions (“opennebulapermissions”) that can be applied in the Cluster level, and another to handle this single permission. This way, you can create a role managing all OpenNebula permissions and another role (called for instance `readcustspec`) with **only** the next one:

Privileges ID	Privilege name	Notes
<code>VirtualMachine.Provisioning.ReadCustSpecs</code>	Read customization specifications	Required to read customization specifications

Once you have created the proper role, one way to manage these privileges is creating two groups.

- The first group needs to be assigned the `readcustspec` role. Place the OpenNebula user inside this group and grant permission over the vCenter instance to the group.
- The second group needs to be assigned the `opennebulapermissions` role. Place the OpenNebula user inside this group and grant permission over the desired cluster to the group.

Note: Do not forget to add the proper permissions to the datastores and any resource accessed by your OpenNebula user.

3.4.4 VNC on ESX hosts

To enable VNC functionality, you need to allow access to the VNC ports on ESX hosts. By default, access to these ports is filtered by the firewall. We provide an installation package, which adds the VNC ruleset (port range 5900-11999 excluding known reserved ports) and permits access to these ports. Also OpenNebula needs to be reconfigured to respect this specific VNC ports range. This package must be installed on each ESX host; it can be done via CLI or web UI. We'll cover the necessary steps for both ways here.

Locations of the VIB installation package or ZIP bundle:

- On your OpenNebula Front-end server, in `/usr/share/one/esx-fw-vnc/`. Installed as part of the package
 - **opennebula-server** on RHEL/CentOS
 - **opennebula** on Debian and Ubuntu.
- On the public download server. In a case of installation problems, insecure HTTP access can be used at your own risk!
 - <https://downloads.opennebula.org/packages/opennebula-5.10.0/fw-vnc-5.10.0.vib>
 - <https://downloads.opennebula.org/packages/opennebula-5.10.0/fw-vnc-5.10.0.zip>

Note: Make sure that the ESX hosts are reachable from the OpenNebula Front-end.

The VNC range whitelisted on ESX hosts must be specified in the OpenNebula configuration located in `/etc/one/oned.conf`. Please change the `VNC_PORTS` section following way:

```
VNC_PORTS = [
    START      = 5900,
    RESERVED  = "5988:5989, 6999, 8000, 8042:8045, 8080, 8100, 8182, 8200, 8300:8302, ↵
    ↪8889, 9000, 9080, 12000:65535"
]
```

and, restart OpenNebula:

```
$ sudo systemctl restart opennebula
```

Using CLI

Note: Please replace the placeholder variables \$ESX_HOST (ESX hostname), \$ESX_USER (access user name) and \$ESX_PSWD (access user's password) with the valid access parameters depending on your infrastructure configuration.

Over SSH

If you have enabled direct SSH access on the ESX hosts, copy the VIB installation packages to the ESX host via scp. Login the ESX host via SSH, allow the community packages to be installed and do the install.

Note: The absolute path to the VIB must be provided.

```
$ scp /usr/share/one/esx-fw-vnc/fw-vnc.* $ESX_HOST:/tmp/
$ ssh $ESX_HOST
$ esxcli software acceptance set --level=CommunitySupported
$ esxcli software vib install -v /tmp/fw-vnc.vib
```

This enables VNC ports for any remote host. You should limit access to the VNC only from your OpenNebula Frontend. In this example, we restrict access only from IP address 192.168.0.1.

```
$ esxcli network firewall ruleset set --ruleset-id VNC --allowed-all false
$ esxcli network firewall ruleset allowedip add --ruleset-id VNC --ip-address 192.168.0.1/32
$ esxcli network firewall ruleset allowedip list --ruleset-id VNC
```

Repeat for each ESX host.

VMware vSphere CLI

If you have a working VMware vSphere CLI, you can install the package remotely via esxcli.

First, check the CLI is working:

```
$ esxcli --server $ESX_HOST --username $ESX_USER --password $ESX_PSWD system version
↪get
```

If the connection fails on untrusted fingerprint, please specify the valid one as an extra esxcli parameter --thumbprint. Example:

```
$ esxcli --server $ESX_HOST --username $ESX_USER --password $ESX_PSWD system version
↪get
Connect to $ESX_HOST failed. Server SHA-1 thumbprint: 00:11:22:33:...:11:22:33 (not
↪trusted).
```

```
$ esxcli --server $ESX_HOST --username $ESX_USER --password $ESX_PSWD --thumbprint
↪'00:11:22:33:....11:22:33' system version get
Product: VMware ESXi
Version: 6.5.0
Build: Releasebuild-4887370
Update: 0
Patch: 9
```

Now, with all required connection parameters from a test above, use the `esxcli` to allow the community packages to be installed and proceed with the install.

Note: VIB must be accessible from the ESX host, as an absolute file path on the ESX host or downloadable URL.

```
$ esxcli <connection options> software acceptance set --level=CommunitySupported
$ esxcli <connection options> software vib install -v 'https://downloads.opennebula.org/packages/opennebula-5.10.0/fw-vnc-5.10.0.vib'
```

This enables VNC ports for any remote host. You should limit access to the VNC only from your OpenNebula Front-end. In this example, we restrict access only from IP address 192.168.0.1.


```
$ esxcli <connection options> network firewall ruleset set --ruleset-id VNC --allowed-all false
$ esxcli <connection options> network firewall ruleset allowedip add --ruleset-id VNC
↪--ip-address 192.168.0.1/32
$ esxcli <connection options> network firewall ruleset allowedip list --ruleset-id VNC
```

Repeat for each ESX host.

Using UI


The VIB package can also be installed over vSphere and ESX web UIs.

- Allow the custom VIB package to be installed (in the vSphere client)
 - Login the vSphere client
 - Go to Home -> Inventories -> Hosts and Clusters
 - Select the ESX host and its tab **Manage** or **Configure** (depends on the vSphere version)
 - Select **Security Profile** in the **System** category
 - At the very bottom, select edit on **Host Image Profile Acceptance Level**
 - Switch to **Community Supported** and confirm with **OK**




- Install the VIB package (in the ESX host UI)

- Login the ESX host UI
- Go to Help -> Update in top right corner
- Provide the VIB URL or absolute local path and click on **Update**



- Restrict VNC access to the OpenNebula Front-end only (in the vSphere client)
 - Go back again to the ESX host details in the vSphere client
 - Reload the vSphere page to see current data
 - Check again **Security Profile** in the **System category**, look on the Firewall/Incoming Connections for new **VNC** item
 - Click on **Edit** for the Firewall
 - Find the VNC and optionally restrict access only to your OpenNebula Front-end (e.g. for 192.168.0.1):



Repeat for each ESX host.

3.5 Verify your Installation

This chapter ends with this optional section, where you will be able to test your cloud by launching a virtual machine and test that everything is working correctly.

You should only follow the specific subsection for your hypervisor.

3.5.1 KVM/LXD based Cloud Verification

The goal of this subsection is to launch a small Virtual Machine, in this case a TTYLinux (which is a very small Virtual Machine just for testing purposes).

Requirements

To complete this section, you must have network connectivity to the Internet from the Front-end, in order to import an appliance from <http://marketplace.opennebula.systems>.

Step 1. Check that the Hosts are on

The Hosts that you have registered should be in ON status.

ID	Name	Cluster	RVMs	Allocated CPU	Allocated MEM	Status
0	node01	0	0	0 / 800 (0%)	0KB / 16GB (0%)	ON

Showing 1 to 1 of 1 entries

1 TOTAL 1 ON 0 OFF 0 ERROR

Step 2. Import an appliance from the MarketPlace.

We need to add an Image to our Cloud. We can do so by navigating to Storage -> Apps in the left side menu (1). You will see a list of Appliances, and you can filter by `tty kvm` (2) in order to find the one we are going to use in this guide. After that select it (3) and click to cloud button (4) in order to import it.

The screenshot shows the OpenNebula web interface with the 'Apps' tab selected in the sidebar (1). In the main area, a list of applications is displayed, with the first entry ('ttylinux - kvm') selected (3). The toolbar at the top includes a 'Download' button (2), which is highlighted with a red circle. The 'Cloud' icon in the toolbar is also highlighted with a red circle (4).


ID	Name	Owner	Group	Size	State	Registration Time	Marketplace	Zone
9	ttylinux - kvm	oneadmin	oneadmin	200MB	READY	01:00:00 01/01/1970	OpenNebula Public	0

A dialog with the information of the appliance you have selected will pop up. You will need to select the datastore under the “Select the Datastore to store the resource” (1) and then click on the “Download” button (2)

The screenshot shows the 'Download App To OpenNebula' dialog. It includes fields for 'Name' (set to 'ttylinux - kvm') and 'VM Template Name' (set to 'ttylinux - kvm'). Below this is a section titled 'Select the Datastore to store the resource'. It shows a table of datastores, with the first entry ('default') selected (1). The 'Download' button is highlighted with a red circle (2).

ID	Owner	Group	Name	Capacity	Cluster	Type	Status
1	oneadmin	oneadmin	default	158.9GB / 461.5GB (34%)	0	IMAGE	ON

Navigate now to the Storage -> Images tab and refresh until the Status of the Image switches to READY.




ID	Name	Owner	Group	Datastore	Type	Status	#VMS
0	ttylinux - kvm	onedadmin	onedadmin	default	OS	READY	0

1 TOTAL 200 MB TOTAL SIZE

Step 3. Instantiate a VM

Navigate to Templates -> VMs, then select the `ttylinux - kvm` template that has been created and click on “Instantiate”.



The screenshot shows the OpenNebula web interface for managing VM templates. On the left is a sidebar with navigation links for Dashboard, Instances, Templates (VMs selected), Services, Virtual Routers, VM Groups, Storage (Datastores, Images, Files, MarketPlaces, Apps), Network, Infrastructure, System, and Settings. A message box in the center says "Officially supported Not connected" with a "Sign in" button. The main area is titled "VM Templates" and contains a table with one entry:

	ID	Name	Owner	Group	Registration time
<input checked="" type="checkbox"/>	0	ttylinux - kvm	oneadmin	oneadmin	13/04/2020 10:22:52

Below the table, it says "Showing 1 to 1 of 1 entries" and "1 TOTAL". At the top of the table row are buttons for "+", "Update", "Instantiate" (which is circled in red), "Clone", "Lock", "Edit", and "Delete". There is also a "Search" field and a dropdown menu.

In this dialog simply click on the “Instantiate” button.

Instantiate VM Template

(Red circle)

Instantiate as persistent ?

VM Name ?

Number of instances ?

Hold ?

ttylinux - kvm

Capacity

Memory ? MB

CPU ?

VCPU ?

Disks

DISK 0: ttylinux - kvm MB

Network

Step 4. Test VNC access

Navigate to Instances -> VMs. You will see that after a while the VM switches to Status RUNNING (you might need to click on the refresh button). Once it does, you can click on the VNC icon (at the right side of the image below).

The screenshot shows the OpenNebula Sunstone web interface. On the left is a sidebar with navigation links: Dashboard, Instances (VMs, Services, Virtual Routers), Templates (VMs, Services, Virtual Routers, VM Groups), Storage (Datastores, Images, Files, MarketPlaces, Apps), Network, Infrastructure, System, and Settings. The Settings section includes a 'Officially supported' status (Not connected) and a 'Sign in' button. At the bottom of the sidebar is the text 'OpenNebula 5.10.5 by OpenNebula Systems.'.

The main area is titled 'VMs' and contains a table with one entry:

ID	Name	Owner	Group	Status	Host	IPs
0	ttylinux - kvm-0	oneadmin	oneadmin	RUNNING	node01	--

Below the table, it says 'Showing 1 to 1 of 1 entries'. At the bottom of the main area, there are statistics: 1 TOTAL, 1 ACTIVE, 0 OFF, 0 PENDING, 0 FAILED.

If the VM fails, click on the VM and then the Log tab to see why. Alternatively, you can look at the log file `/var/log/one/<vmid>.log`.

Step 5. Adding Network connectivity to your VM

As you might have noticed, this VM does not have networking yet, this is because it depends a lot in your network technology. You would need to follow these steps in order to add Networking to the template.

1. Read the [Networking](#) chapter to choose a network technology, unless you have chosen to use the dummy driver explained in the [node installation](#) section and you have configured the bridges properly.
2. Create a new Network in the Network -> Virtual Networks dialog, and fill in the details of your network: like the Bridge, or the Physical Device, the IP ranges, etc.
3. Select the `ttylinux - kvm` template and update it. In the Network section of the template, select the network that you created in the previous step.
4. Instantiate and connect to the VM.

3.5.2 vCenter based Cloud Verification

In order to verify the correct installation of your OpenNebula cloud, follow the next steps. The following assumes that Sunstone is up and running, as explained in the [front-end installation Section](#). To access Sunstone, point your browser

to `http://<frontend_address>:9869`.

Step 1. Import a Datastore

Your vCenter VM templates use virtual disks, and those virtual disks are stored in datastores. You must import into OpenNebula those vcenter datastores that contain the virtual disks.

Follow the steps to import datastores as described in the [vCenter Import Datastores Section](#)

Step 2. Import a VM Template

You will need a VM Template defined in vCenter, and then import it using the steps described in the [vCenter Import Templates Section](#).

Step 3. Instantiate the VM Template

You can easily instantiate the template to create a new VM from it using Sunstone. Proceed to the Templates tab of the left side menu, VMs Section, select the imported template and click on the Instantiate button.

Step 4. Check the VM is Running

The scheduler should place the VM in the vCenter cluster imported as part of the [vCenter Node Installation Section](#).

After a few minutes (depending on the size of the disks defined by the VM Template), the state of the VM should be RUNNING. You can check the process in Sunstone in the Instances tab of the left side menu, VMs Section.

Once the VM is running, click on the VNC blue icon, and if you can see a console to the VM, congratulations! You have a fully functional OpenNebula cloud.

The screenshot shows the OpenNebula web interface. On the left is a sidebar with navigation links: Dashboard, Instances (VMs, Services, Virtual Routers), Templates (VMs, Services, Virtual Routers, VM Groups), Storage (Datastores, Images, Files, MarketPlaces, Apps), Network (Infrastructure, System, Settings), and a sign-in section for VMware Infrastructure Setup. The main area is titled 'VMs' and displays a table with one entry: ID 1, Name TestVM, Owner oneadmin, Group oneadmin, Status RUNNING, Host cluster, and IPs --. Below the table, it says '1 TOTAL 1 ACTIVE 0 OFF 0 PENDING 0 FAILED'. At the bottom of the main area, it says 'Showing 1 to 1 of 1 entries'.

The next step would be to further configure the OpenNebula cloud to suit your needs. You can learn more in the [VMware Infrastructure Setup](#) guide.

3.5.3 Next steps

After this chapter, you are ready to start using your cloud or you could configure more components:

- [Authenticating](#). (Optional) For integrating OpenNebula with LDAP/AD, or securing it further with other authentication technologies.
- [Sunstone](#). The OpenNebula GUI should be working and accessible at this stage, but by reading this guide you will learn about specific enhanced configurations for Sunstone.

If your cloud is KVM/LXD based you should also follow:

- [Open Cloud Host Setup](#).
- [Open Cloud Storage Setup](#).
- [Open Cloud Networking Setup](#).

Otherwise, if it's VMware based:


- Head over to the [VMware Infrastructure Setup](#) chapter.

AUTHENTICATION SETUP

4.1 Overview

OpenNebula comes by default with an internal user/password authentication system; see the Users & Groups Subsystem guide for more information. You can enable an external Authentication driver.

4.1.1 Authentication



In this figure you can see three authentication configurations you can customize in OpenNebula.

a) CLI/API Authentication

You can choose from the following authentication drivers to access OpenNebula from the command line:

- Built-in User/Password and token authentication
- *SSH Authentication*
- *X509 Authentication*
- *LDAP Authentication*

b) Sunstone Authentication

By default, any authentication driver configured to work with OpenNebula can be used out-of-the-box with Sunstone. Additionally you can add TLS security to Sunstone as described in the [Sunstone documentation](#)

c) Servers Authentication

This method is designed to delegate the authentication process to high level tools interacting with OpenNebula. You'll be interested in this method if you are developing your own servers.

By default, OpenNebula ships with two servers: *Sunstone* and EC2. When a user interacts with one of them, the server authenticates the request and then forwards the requested operation to the OpenNebula daemon.

The forwarded requests are encrypted by default using a Symmetric Key mechanism. The following guide shows how to strengthen the security of these requests using x509 certificates. This is specially relevant if you are running your server in a machine other than the front-end.

- *Cloud Servers Authentication*

4.1.2 How Should I Read This Chapter

When designing the architecture of your cloud you will have to choose where to store users' credentials. Different authentication methods can be configured at the same time and selected on a per user basis. One big distinction between the different authentication methods is the ability to be used by API, CLI and/or only Sunstone (the web interface).

Can be used with API, CLI and Sunstone:

- Built-in User/Password
- LDAP

Can be used only with API and CLI:

- SSH

Can be used only with Sunstone:

- X509

The following sections are self-contained so you can directly go to the guide that describes the configuration for the chosen auth method.

4.1.3 Hypervisor Compatibility

Section	Compatibility
Built-in User/Password and token authentication	This Section applies to both KVM and vCenter.
<i>SSH Authentication</i>	This Section applies to both KVM and vCenter.
<i>X509 Authentication</i>	This Section applies to both KVM and vCenter.
<i>LDAP Authentication</i>	This Section applies to both KVM and vCenter.
<i>Sunstone documentation</i>	This Section applies to both KVM and vCenter.

4.2 SSH Authentication

This guide will show you how to enable and use the SSH authentication for the OpenNebula CLI. Using this authentication method, users log in to OpenNebula with a token encrypted with their private SSH keys.

4.2.1 Requirements

You don't need to install any additional software.

4.2.2 Considerations & Limitations

With the current release, this authentication method is only valid to interact with OpenNebula using the CLI.

4.2.3 Configuration

OpenNebula Configuration

The Auth MAD with ssh authentication is enabled by default. In case it does not work, make sure that the authentication method is in the list of enabled methods.

```
AUTH_MAD = [
    executable = "one_auth_mad",
    authn = "ssh,x509,ldap,server_cipher,server_x509"
]
```

There is an external plain user/password authentication driver, and existing accounts will keep working as usual.

4.2.4 Usage

Create New Users

This authentication method uses standard SSH RSA key pairs for authentication. Users can create these files **if they don't exist** using this command:

```
$ ssh-keygen -t rsa
```

OpenNebula commands look for the files generated in the standard location (`$HOME/.ssh/id_rsa`), so it is a good idea not to change the default path. It is also a good idea to protect the private key with a password.

The users requesting a new account have to generate a public key and send it to the administrator. The way to extract it is the following:

```
$ oneuser key
Enter PEM pass phrase:
MIIBCAKCAQEApUO+JISjsF02rFVtDr1yar/34EoUoVETx0n+RqWNavy+5wi+gHiPp3e03AfEkXzjDYi8F
vos4a4456f10UQ1QddfyPECn590eX8Zu4DH3gp1VUuDeeE8WJWyaZdK5hg6F+RdyP1pT26mnyunZB8Xd
b118seoIAQiOS6t1VFa8Fr7wLGmdEETfttS9ukyGxw5vdTp1se/fcam+r9AXBR06zjc77x+DbRFbXcgI
1XIdpVrjCFL0fdN53L0aU7kTE9VNEXRxK8sPv1Nfx+FQWpX/HtH8ICs5WReZGmXPAO/IkrSpMVg5taS
jie9JAQOMesjFIwgTWBUh6cNXuYsQ/5wIwIBIw==
```

The string written to the console must be sent to the administrator so they can create the new user in a similar way to the default user/password authentication users.

The following command will create a new user with username `newuser`, assuming that the previous public key is saved in the text file `/tmp/pub_key`:

```
$ oneuser create newuser --ssh --read-file /tmp/pub_key
```

Instead of using the `--read-file` option, the public key could be specified as the second parameter.

If the administrator has access to the user's **private ssh key**, they can create new users with the following command:

```
$ oneuser create newuser --ssh --key /home/newuser/.ssh/id_rsa
```

Update Existing Users to SSH

You can change the authentication method of an existing user to SSH with the following commands:

```
$ oneuser chauth <id|name> ssh  
$ oneuser passwd <id|name> --ssh --read-file /tmp/pub_key
```

As with the `create` command, you can specify the public key as the second parameter, or use the user's private key with the `--key` option.

User Login

Users must execute the `oneuser login` command to generate a login token. The token will be stored in the `$ONE_AUTH` environment variable. The command requires the OpenNebula username, and the authentication method (`--ssh` in this case).

```
$ oneuser login newuser --ssh
```

The default SSH key is assumed to be in `~/.ssh/id_rsa`, otherwise the path can be specified with the `--key` option.

The generated token has a default **expiration time** of 10 hours. You can change that with the `--time` option.

4.3 x509 Authentication

This guide will show you how to enable and use x509 certificates authentication with OpenNebula. The x509 certificates can be used in two different ways in OpenNebula.

The first option that is explained in this guide enables us to use certificates with the CLI. In this case the user will generate a login token with their private key. OpenNebula will validate the certificate and decrypt the token to authenticate the user.

The second option enables us to use certificates with Sunstone and the Public Cloud servers included in OpenNebula. In this case the authentication is delegated to Apache or any other TLS-capable HTTP proxy configured by the administrator. If this certificate is validated, the server will encrypt those credentials using a server certificate and will send the token to OpenNebula.

4.3.1 Requirements

If you want to use x509 certificates with Sunstone or one of the Public Clouds, you must deploy a TLS-capable HTTP proxy on top of them in order to handle the certificate validation.

4.3.2 Considerations & Limitations

The X509 driver handles the certificate DN like user passwords. It will remove any space in the certificate DN. This may cause problems in the unlikely situation that you are using a CA signing certificate subjects that only differ in spaces.

4.3.3 Configuration

The following table summarizes the available options for the x509 driver (`/etc/one/auth/x509_auth.conf`):

VARIABLE	VALUE
<code>:ca_dir</code>	Path to the trusted CA directory. It should contain the trusted CAs for the server. Each CA certificate should be named <code><CA_hash>.0</code>
<code>:check</code>	By default, if you place CRL files in the CA directory in the form <code><CA_hash>.r0</code> , OpenNebula will check them. You can enforce CRL checking by defining <code>:check_crl</code> , i.e. authentication will fail if no CRL file is found. You can always disable this feature by moving or renaming <code>.r0</code> files

Follow these steps to change oneadmin's authentication method to x509:

Warning: You should have another account in the oneadmin group, so you can revert these steps if the process fails.

- *Change the oneadmin password* to the oneadmin certificate DN.

```
$ oneuser chauth 0 x509 --x509 --cert /tmp/newcert.pem
```

- *Add trusted CA certificates* to the certificates directory:

```
$ openssl x509 -noout -hash -in cacert.pem
78d0bbd8

$ sudo cp cacert.pem /etc/one/auth/certificates/78d0bbd8.0
```

- *Create a login* for oneadmin using the `--x509` option. This token has a default expiration time set to 1 hour. You can change that value using the option `--time`.

```
$ oneuser login oneadmin --x509 --cert newcert.pem --key newkey.pem
Enter PEM pass phrase:
export ONE_AUTH=/home/oneadmin/.one/one_x509
```

- Set `ONE_AUTH` to the x509 login file

```
$ export ONE_AUTH=/home/oneadmin/.one/one_x509
```

4.3.4 Usage

Add and Remove Trusted CA Certificates

You need to copy all trusted CA certificates to the certificates directory, renaming each of them as `<CA_hash>.0`. The hash can be obtained with the `openssl` command:

```
$ openssl x509 -noout -hash -in cacert.pem
78d0bbd8

$ sudo cp cacert.pem /etc/one/auth/certificates/78d0bbd8.0
```

To stop trusting a CA, simply remove its certificate from the certificates directory.

This process can be done without restarting OpenNebula; the driver will look for the certificates each time an authentication request is made.

Create New Users

Users requesting a new account have to send their certificate, signed by a trusted CA, to the administrator. The following command will create a new user with username `newuser`, assuming that the user's certificate is saved in the file `/tmp/newcert.pem`:

```
$ oneuser create newuser --x509 --cert /tmp/newcert.pem
```

This command will create a new user whose password contains the subject DN of their certificate. Therefore, if the subject DN is known by the administrator, the user can be created as follows:

```
$ oneuser create newuser --x509 "user_subject_DN"
```

Update Existing Users to x509 & Multiple DN

You can change the authentication method of an existing user to x509 with the following command:

- Using the user certificate:

```
$ oneuser chauth <id|name> x509 --x509 --cert /tmp/newcert.pem
```

- Using the user certificate subject DN:

```
$ oneuser chauth <id|name> x509 --x509 "user_subject_DN"
```

You can also map multiple certificates to the same OpenNebula account. Just add each certificate DN separated by | to the password field:

```
$ oneuser passwd <id|name> --x509 "/DC=es/O=one/CN=user|/DC=us/O=two/CN=user"
```

User Login

Users must execute the `oneuser login` command to generate a login token. The token will be stored in the `ONE_AUTH` environment variable. The command requires the OpenNebula username, and the authentication method (`--x509` in this case).

```
newuser@frontend $ oneuser login newuser --x509 --cert newcert.pem --key newkey.pem
Enter PEM pass phrase:
```

The generated token has a default **expiration time** of 10 hours. You can change that with the `--time` option.

4.3.5 Tuning & Extending

The x509 authentication method is just one of the drivers enabled in AUTH_MAD. All drivers are located in `/var/lib/one/remotes/auth`.

OpenNebula is configured to use x509 authentication by default. You can customize the enabled drivers in the AUTH_MAD attribute of `oned.conf`. More than one authentication method can be defined:

```
AUTH_MAD = [
  executable = "one_auth_mad",
  authn = "ssh,x509,ldap,server_cipher,server_x509"
]
```

4.3.6 Enabling x509 auth in Sunstone

Update the `/etc/one/sunstone-server.conf` :auth parameter to use x509 auth:

```
:auth: x509
```

4.4 LDAP Authentication

The LDAP Authentication add-on permits users to have the same credentials as in LDAP, so effectively centralizing authentication. Enabling it will let any correctly authenticated LDAP user use OpenNebula.

4.4.1 Prerequisites

Warning: This Add-on requires the ‘`net/ldap`’ ruby library provided by the ‘`net-ldap`’ gem.

This Add-on will not install any LDAP server or configure it in any way. It will not create, delete or modify any entry in the LDAP server it connects to. The only requirement is the ability to connect to an already running LDAP server, perform a successful **ldapbind** operation, and have a user able to perform searches of users. Therefore no special attributes or values are required in the LDIF entry of the user authenticating.

4.4.2 Configuration

The configuration file for the auth module is located at `/etc/one/auth/ldap_auth.conf`. This is the default configuration:

```
server 1:
  # Ldap user able to query, if not set connects as anonymous. For
  # Active Directory append the domain name. Example:
  # Administrator@my.domain.com
  #:user: 'admin'
  #:password: 'password'

  # Ldap authentication method
:auth_method: :simple

  # Ldap server
```

```

:host: localhost
:port: 389

# Connection and authentication timeout
#:timeout: 15

# Uncomment this line for tls connections
#:encryption: :simple_tls

# base hierarchy where to search for users and groups
:base: 'dc=domain'

# alternative base hierarchy where to search for groups instead of :base:
#:group_base: 'ou=groups,dc=domain'

# group the users need to belong to. If not set any user will do
#:group: 'cn=cloud,ou=groups,dc=domain'

# field that holds the user name, if not set 'cn' will be used
:user_field: 'cn'

# for Active Directory use this user_field instead
#:user_field: 'sAMAccountName'

# field name for group membership, by default it is 'member'
#:group_field: 'member'

# user field that is in the group group_field, if not set 'dn' will be used
:#user_group_field: 'dn'

# Generate mapping file from group template info
:mapping_generate: true

# Seconds a mapping file remain untouched until the next regeneration
:mapping_timeout: 300

# Name of the mapping file in OpenNebula var directory
:mapping_filename: server1.yaml

# Key from the OpenNebula template to map to an AD group
:mapping_key: GROUP_DN

# Default group ID used for users in an AD group not mapped
:mapping_default: 1

# use RFC2307bis for groups
# if false, depending on your LDAP server configuration,
# set user_field and user_group_field 'uid' and group_field 'memberUid'
:rfc2307bis: true

# this example server wont be called as it is not in the :order list
server 2:
:auth_method: :simple
:host: localhost
:port: 389
:base: 'dc=domain'
#:group: 'cn=cloud,ou=groups,dc=domain'

```

```

:user_field: 'cn'

# List the order the servers are queried
#
# :order is defined as a list of server names and/or nested lists
# of server names (representing the availability group). The servers
# in the main list are consulted in the order they are written until
# the authentication succeeds. In the nested server lists (avail.
# groups), user is authenticated only against the first online server.
# If user is passed/refused by the server in the availability group,
# no other server is consulted from the same group, but
# the authentication process continues with the next server/group in
# the main list.
#
# Examples:
#
# 1) simple list
# :order:
#     - server1
#     - server2
#     - server3
#
# 2) list with availability group
# :order:
#     - server1
#     - ['server2', 'server3', 'server4']      # availability group
#     - server5
#
:order:
    - server 1
    #- server 2

```

The structure is a hash where any key different to `:order` will contain the configuration of one LDAP server we want to query. The special key `:order` holds an array with the order we want to query the configured servers.

Note: Items of the `:order` are the server names, or nested arrays of server names, representing the **availability group**. The items in the `:order` are processed one by one until the user is successfully authenticated, or the end of the list is reached. Inside the availability group, only the very first server which can be successfully connected to is queried. Any server not listed in `:order` won't be queried.

VARIABLE	DESCRIPTION
:user	Name of the user that can query LDAP. Do not set it if you can perform queries anonymously
:password	Password for the user defined in :user. Do not set if anonymous access is enabled
:auth_method	Only :simple is supported
:encryption	Can be set to :simple_tls if SSL connection is needed
:host	Host name of the LDAP server
:port	Port of the LDAP server
:timeout	Connection and authentication timeout
:base	Base leaf where to perform user searches
:group_base	Alternative base leaf where to perform group searches instead of in :base
:group	If set, the users need to belong to this group
:user_field	Field in LDAP that holds the user name
:mapping_gen	Automatically generate a mapping file. It can be disabled in case it needs to be done manually
:mapping_time	Number of seconds between automatic mapping file generation
:mapping_file	Name of the mapping file. Should be different for each server
:mapping_key	Key in the group template used to generate the mapping file. It should hold the DN of the mapped group
:mapping_def	Default group used when no mapped group is found. Set to false in case you don't want the user to be authorized if they do not belong to a mapped group
:rfc2307bis	Set to true when using Active Directory, false when using LDAP. Make sure you configure user_group_field and group_field

To enable ldap authentication the described parameters should be configured. OpenNebula must be also configured to enable external authentication. Add this line in /etc/one/oned.conf

```
DEFAULT_AUTH = "ldap"
```

4.4.3 User Management

Using the LDAP authentication module, the administrator doesn't need to create users with `oneuser` command, as this will be automatically done.

Users can store their credentials into the `$ONE_AUTH` file (usually `$HOME/.one/one_auth`) in this fashion:

```
<user_dn>:ldap_password
```

where

- `<user_dn>` the DN of the user in the LDAP service
- `ldap_password` is the password of the user in the LDAP service

Alternatively a user can generate an authentication token using the `oneuser login` command, so there is no need to keep the LDAP password in a plain file. Simply input the LDAP password when requested. More information on the management of login tokens and the `$ONE_AUTH` file can be found in Managing Users Guide.

DNs With Special Characters

When the user DN or password contains blank spaces, the LDAP driver will escape them so they can be used to create OpenNebula users. Therefore, users need to set up their `$ONE_AUTH` file accordingly.

Users can easily create escaped `$ONE_AUTH` tokens with the command `oneuser encode <user> [<password>]`, as an example:

```
$ oneuser encode 'cn=First Name,dc=institution,dc=country' 'pass word'
cn=First%20Name,dc=institution,dc=country:pass%20word
```

The output of this command should be put in the \$ONE_AUTH file.

4.4.4 Active Directory

LDAP Auth drivers are able to connect to Active Directory. You will need:

- An Active Directory server with support for simple user/password authentication.
- A user with read permissions in the Active Directory users tree.

You will need to change the following values in the configuration file (/etc/one/auth/ldap_auth.conf):

- :user: the Active Directory user with read permissions in the users tree plus the domain. For example for user **Administrator** at domain **win.opennebula.org** you specify it as **Administrator@win.opennebula.org**
- :password: password of this user
- :host: hostname or IP of the Domain Controller
- :base: base DN to search for users. You need to decompose the full domain name and use each part as a DN component. Example, for **win.opennebula.org** you will get the base DN: **DN=win, DN=opennebula, DN=org**
- :user_field: set it to **sAMAccountName**

4.4.5 Group Mapping

You can make new users belong to a specific group or groups. To do this a mapping is generated from the LDAP group to an existing OpenNebula group. This system uses a mapping file specified by the :mapping_file parameter and resides in the OpenNebula var directory. The mapping file can be generated automatically using data in the group template that defines which LDAP group maps to that specific group. For example we can add in the group template this line:

```
GROUP_DN="CN=technicians,CN=Groups,DC=example,DC=com"
```

and in the LDAP configuration file we set the :mapping_key to GROUP_DN. This tells the driver to look for the group DN in that template parameter. This mapping expires after the number of seconds specified by :mapping_timeout. This is done so the authentication is not continually querying OpenNebula.

You can also disable the automatic generation of this file and do the mapping manually. The mapping file is in YAML format and contains a hash where the key is the LDAP's group DN and the value is the ID of the OpenNebula group. For example:

```
CN=technicians,CN=Groups,DC=example,DC=com: '100'
CN=Domain Admins,CN=Users,DC=example,DC=com: '101'
```

When several servers are configured, you should have different :mapping_key and :mapping_file values for each one so they don't collide. For example:

```
internal:
  :mapping_file: internal.yaml
  :mapping_key: INTERNAL_GROUP_DN
```

```
external:
  :mapping_file: external.yaml
  :mapping_key: EXTERNAL_GROUP_DN
```

and in the OpenNebula group template you can define two mappings, one for each server:

```
INTERNAL_GROUP_DN="CN=technicians,CN=Groups,DC=internal,DC=com"
EXTERNAL_GROUP_DN="CN=staff,DC=other-company,DC=com"
```

Note: If the map is updated (e.g. you change the LDAP DB) the user groups will be updated next time the user is authenticated. Also note that a user may be using a login token that needs to expire for this change to take effect. The maximum lifetime of a token can be set in `oned.conf` for each driver. If you want the OpenNebula core not to update user groups (and control group assignment from OpenNebula) update `DRIVER_MANAGED_GROUPS` in the `ldap AUTH_MAD_CONF` configuration attribute.

4.4.6 Enabling LDAP auth in Sunstone

Update the `/etc/one/sunstone-server.conf` `:auth` parameter to use `opennebula`:

```
:auth: opennebula
```

Using this method, the credentials provided in the login screen will be sent to the OpenNebula core, and the authentication will be delegated to the OpenNebula auth system using the specified driver for that user. Therefore any OpenNebula auth driver can be used through this method to authenticate the user (e.g. LDAP).


To automatically encode credentials as explained in the *DN's with special characters* section, also add this parameter to the sunstone configuration:

```
:encode_user_password: true
```

SUNSTONE SETUP

5.1 Overview

OpenNebula Sunstone is a Graphical User Interface (GUI) intended for both end users and administrators that simplifies the typical management operations in private and hybrid cloud infrastructures. OpenNebula Sunstone allows easily managing all OpenNebula resources and performing typical operations on them.



5.1.1 How Should I Read this Chapter

The [Sunstone Installation & Configuration](#) section describes the configuration and customization options for Sunstone. After Sunstone is running, you can define different sunstone behaviors for each user role in the [Sunstone Views](#) section. For more information on how to customize and extend your Sunstone deployment use the following links:

- [Security & Authentication Methods](#): improve security with x509 authentication and SSL
- [Cloud Servers Authentication](#): advanced reference about the security between Sunstone and OpenNebula
- [Advanced Deployments](#): improving scalability and isolating the server

5.1.2 Hypervisor Compatibility

Sunstone is available for all the hypervisors. When using vCenter, the cloud admin should enable the `admin_vcenter`, `groupadmin_vcenter` and `cloud_vcenter` *Sunstone views*.

5.2 Sunstone Installation & Configuration

5.2.1 Requirements

You must have an OpenNebula site properly configured and running to use OpenNebula Sunstone. Be sure to check the *OpenNebula Installation and Configuration Guides* to set up your private cloud first. This section also assumes that you are familiar with the configuration and use of OpenNebula.

OpenNebula Sunstone was installed during the OpenNebula installation. If you followed the *installation guide* then you already have all ruby gem requirements. Otherwise, run the `install_gem` script as root:

```
# /usr/share/one/install_gems sunstone
```

The Sunstone Operation Center offers the possibility of starting a VNC/SPICE session to a Virtual Machine. This is done by using a VNC/SPICE websocket-based client (noVNC) on the client side and a VNC proxy translating and redirecting the connections on the server side.

Warning: The SPICE Web client is a prototype and is limited in function. More information of this component can be found in the following [link](#)

Warning: Make sure that there is free space in sunstone's log directory or it will die silently. By default the log directory is `/var/log/one`.

Requirements:

- Websockets-enabled browser (optional): Firefox and Chrome support websockets. In some versions of Firefox manual activation is required. If websockets are not enabled, Flash emulation will be used.
- Installing the python-numpy package is recommended for better VNC performance.

5.2.2 Configuration

sunstone-server.conf

The Sunstone configuration file can be found at `/etc/one/sunstone-server.conf`. It uses YAML syntax to define some options:

Available options are:

Option	Description
<code>:tmpdir</code>	Uploaded images will be temporally stored in this folder before being copied to OpenNebula
<code>:one_xmlrpc</code>	OpenNebula daemon host and port
<code>:one_xmlrpc_timeout</code>	Configure the timeout (seconds) for XMLRPC calls from sunstone. See Shell Environment variables
<code>:host</code>	IP address on which the server will listen. <code>0.0.0.0</code> by default.

Table 5

Option	Description
:port	Port on which the server will listen. 9869 by default.
:sessions	Method of keeping user sessions. It can be memory or memcache. For servers that spawn more than one instance of Sunstone, it is recommended to use memcache.
:memcache_host	Host where memcached server resides
:memcache_port	Port of memcached server
:memcache_namespace	memcache namespace where to store sessions. Useful when memcached server is used by more services.
:debug_level	Log debug level: 0 = ERROR, 1 = WARNING, 2 = INFO, 3 = DEBUG
:env	Execution environment for Sunstone. dev, Instead of pulling the minified js all the files will be pulled (applies to :http_proxy)
:max_upload_file_size	Maximum allowed size of uploaded images (in bytes). Leave commented for unlimited size
:auth	Authentication driver for incoming requests. Possible values are sunstone, opennebula, remote and local
:core_auth	Authentication driver to communicate with OpenNebula core. Possible values are x509 or cipher. Cipher is the default
:encode_user_password	For external authentication drivers, such as LDAP. Performs a URL encoding on the credentials sent to OpenNebula
:lang	Default language for the Sunstone interface. This is the default language that will be used if user has not chosen another one.
:vnc_proxy_port	Base port for the VNC proxy. The proxy will run on this port as long as Sunstone server does. 29876 by default
:vnc_proxy_support_wss	yes, no, only. If enabled, the proxy will be set up with a certificate and a key to use secure websockets.
:vnc_proxy_cert	Full path to certificate file for wss connections.
:vnc_proxy_key	Full path to key file. Not necessary if key is included in certificate.
:vnc_proxy_ipv6	Enable IPv6 for novnc. (true or false)
:vnc_client_port	Port where the VNC JS client will connect. If not set, will use the port section of :vnc_proxy_port
:vnc_request_password	Request VNC password for external windows. By default it will not be requested (true or false)
:table_order	Default table order. Resources get ordered by ID in asc or desc order.
:marketplace_username	Username credential to connect to the Marketplace.
:marketplace_password	Password to connect to the Marketplace.
:marketplace_url	Endpoint to connect to the Marketplace. If commented, a 503 service unavailable error will be returned.
:oneflow_server	Endpoint to connect to the OneFlow server.
:routes	List of files containing custom routes to be loaded. Check server plugins for more info.
:mode	Default views directory.
:keep_me_logged	True to display 'Keep me logged in' option in Sunstone login.
:get_extended_vm_info	True to display IP in table by requesting the extended vm pool to oned
:allow_vnc_federation	True to display VNC icons in federation
:http_proxy	Proxy server for HTTP Traffic.
:no_proxy	Patterns for IP addresses or domain names that shouldn't use the proxy

Note: To use Sunstone with IPv6 only systems and thin HTTP sever, use the full IPv6 address in the field :host. If you need to set the localhost address (::1) or the unspecified address (:) please use the following:

Example: :host: 0::1, :host: 0::0

Note: To use Sunstone with IPv6-only systems and thin HTTP sever, use the full IPv6 address in the field :host. If you need to set the localhost address (::1) or the unspecified address (:) please use the following:

Example: :host: 0::1, :host: 0::0

Sunstone behavior can also be configured through the user template (within a SUNSTONE=[] vector value, for instance SUNSTONE=[TABLE_ORDER="asc"]):

Option	Description
DISPLAY_NAME	Name of the user that will appear in Sunstone
TABLE_ORDER	Asc (ascending) or Desc (descending)
DEFAULT_VIEW	Name of the default view (as appearing in /etc7on/sunstone-views)
TABLE_DEFAULT_PAGE_LENGTH	Default length of Sunstone datatables' pages
LANG	Sunstone language (defaults to en_US)
DEFAULT_ZONE_ENDPOINT	Default zone at Sunstone login. Defaults to the local zone

Starting Sunstone

To start Sunstone, just issue the following command as oneadmin

```
# service opennebula-sunstone start
```

You can find the Sunstone server log file in /var/log/one/sunstone.log. Errors are logged in /var/log/one/sunstone.error.

5.2.3 Commercial Support Integration

We are aware that in production environments, access to professional, efficient support is a must, and this is why we have introduced an integrated tab in Sunstone to access [OpenNebula Systems](#) (the company behind OpenNebula, formerly C12G) professional support. In this way, support ticket management can be performed through Sunstone, avoiding disruption of work and enhancing productivity.

The Support Subscription provides expert integration and production support on supported platforms and include:

- ✓ Problem diagnosis, resolution and bug fixing
- ✓ Solving unexpected problems when using, installing or configuring the software
- ✓ Guidance about tuning for optimal and scalable performance in your environment
- ✓ Answering "how to" questions related to standard and intended product usage
- ✓ Offering hints about how to go around missing features
- ✓ Answering questions about product adaptation and integration

For more info on support subscriptions, [click here](#)

i Additional Help Resources



Documentation



Community

This tab can be disabled in the sunstone views configuration files

This tab and can be disabled in each one of the *view yaml files*.

```
enabled_tabs:
  [ ... ]
  #- support-tab
```

5.2.4 Troubleshooting

Cannot connect to OneFlow server

The Service instances and templates tabs may show the following message:

Cannot connect to OneFlow server

The screenshot shows the OpenNebula Sunstone web interface. On the left is a sidebar with navigation links: Dashboard, Instances (VMs, Services), Templates, Storage, Network, Infrastructure, System, and Settings. Under Settings, there's a box labeled 'Officially supported' with 'Not connected' and a 'Sign in' button. The main content area has a title 'Services' and a table header with columns: ID, Owner, Group, Name, and State. Below the table, a large cloud icon with an info sign indicates 'There is no data available'. At the bottom right of the table area, a red rectangular box contains the text 'Cannot connect to OneFlow server'.

You need to start the OneFlow component following this section, or disable the Service and Service Templates menu entries in the *Sunstone views yaml files*.

VNC Troubleshooting

When clicking the VNC icon, the process of starting a session begins:

- A request is made, and if a VNC session is possible, the Sunstone server will add the VM Host to the list of allowed vnc session targets and create a random token associated to it.
- The server responds with the session token, then a noVNC dialog pops up.
- The VNC console embedded in this dialog will try to connect to the proxy, either using websockets (default) or emulating them using Flash. Only connections providing the right token will be successful. The token expires and cannot be reused.

There can be multiple reasons for noVNC not correctly connecting to the machines. Here's a checklist of common problems:

- noVNC requires Python >= 2.5 for the websockets proxy to work. You may also need additional modules, such as `python2<version>-numpy`.

- You can retrieve useful information from `/var/log/one/novnc.log`
- You must have a GRAPHICS section in the VM template enabling VNC, as stated in the documentation. Make sure the attribute IP is set correctly (`0.0.0.0` to allow connections from everywhere), otherwise, no connections will be allowed from the outside.
- Your browser must support websockets, and have them enabled. This is the default in current Chrome and Firefox, but former versions of Firefox (i.e. 3.5) required manual activation. Otherwise Flash emulation will be used.
- Make sure there are no firewalls blocking the connections. The proxy will redirect the websocket data from the VNC proxy port to the VNC port stated in the template of the VM. The value of the proxy port is defined in `sunstone-server.conf`.
- Make sure that you can connect directly from the Sunstone frontend to the VM using a normal VNC client tool, such as `vncviewer`.
- When using secure websockets, make sure that your certificate and key (if not included in the certificate) are correctly set in the Sunstone configuration files. Note that your certificate must be valid and trusted for the wss connection to work. If you are working with a certificate that it is not accepted by the browser, you can manually add it to the browser trust list by visiting `https://sunstone.server.address:vnc_proxy_port`. The browser will warn that the certificate is not secure and prompt you to manually trust it.
- If your connection is very, very, very slow, there might be a token expiration issue. Please try the manual proxy launch as described below to check it.
- Doesn't work yet? Try launching Sunstone, killing the websockify proxy and relaunching the proxy manually in a console window with the command that is logged at the beginning of `/var/log/one/novnc.log`. You must generate a lock file containing the PID of the python process in `/var/lock/one/.novnc.lock`. Leave it running and click on the VNC icon on Sunstone for the same VM again. You should see some output from the proxy in the console and hopefully the reason the connection does not work.
- Please contact the support forum only when you have gone through the suggestions, above and provide full sunstone logs, errors shown, and any relevant information on your infrastructure (if there are Firewalls etc.).
- The message “SecurityError: The operation is insecure.” is usually related to a Same-Origin-Policy problem. If you have Sunstone TLS-secured and try to connect to an insecure websocket for VNC, Firefox blocks that. For Firefox, you need to have both connections secured to not get this error. And don't use a self-signed certificate for the server, this would raise the error again (you can setup your own little CA, that works, but don't use a self-signed server certificate). The other option would be to go into the Firefox config (`about:config`) and set `network.websocket.allowInsecureFromHTTPS` to `true`.

RDP Troubleshooting

To add one RDP connection link for a NIC in a VM, there are two possibilities for this purpose.

- Activate the option in the Network tab of the template:

- It can also be defined in the VM by adding:

```
NIC=[  
    ...  
    RDP = "YES"  
]
```

Once the VM is instantiated, users will be able to download the RDP file configuration.

	Permissions	Use	Manage	Admin
Owner	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	
Group	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	
Other	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	

	Ownership
Owner	oneadmin
Group	oneadmin

Important: The RDP connection is only allowed to activate on a single NIC. In any case, the file RDP will only contain the IP of the first NIC with this property enabled.

Note: If the VM template has a password and username set in the contextualization section, this will be reflected in the RDP file. You can read about them in the Virtual Machine Definition File reference section

5.2.5 Tuning & Extending

Internationalization and Languages

Sunstone supports multiple languages. If you want to contribute a new language, make corrections, or complete a translation, you can visit our:

- [Transifex project page](#)

Translating through Transifex is easy and quick. All translations should be submitted via Transifex.

Users can update or contribute translations anytime. Prior to every release, normally after the beta release, a call for translations will be made in the forum. Then the source strings will be updated in Transifex so all the translations can be updated to the latest OpenNebula version. Translation with an acceptable level of completeness will be added to the final OpenNebula release.

Customize the VM Logos

The VM Templates have an image logo to identify the guest OS. To modify the list of available logos, or to add new ones, edit `/etc/one/sunstone-logos.yaml`.

```
- { 'name': "Arch Linux",           'path': "images/logos/arch.png" }
- { 'name': "CentOS",              'path': "images/logos/centos.png" }
- { 'name': "Debian",              'path': "images/logos/debian.png" }
- { 'name': "Fedora",              'path': "images/logos/fedora.png" }
- { 'name': "Linux",               'path': "images/logos/linux.png" }
- { 'name': "Redhat",              'path': "images/logos/redhat.png" }
- { 'name': "Ubuntu",              'path': "images/logos/ubuntu.png" }
- { 'name': "Windows XP/2003",     'path': "images/logos/windowsxp.png" }
- { 'name': "Windows 8",            'path': "images/logos/windows8.png" }
```

Branding the Sunstone Portal

You can easily add your logos to the login and main screens by updating the `logo:` attribute as follows:

- The login screen is defined in the `/etc/one/sunstone-views.yaml`.
- The logo of the main UI screen is defined for each view in [the view yaml file](#).

`sunstone-views.yaml`

OpenNebula Sunstone can be adapted to different user roles. For example, it will only show the resources the users have access to. Its behavior can be customized and extended via [views](#).

The preferred method to select which views are available to each group is to update the group configuration from Sunstone; as described in [Sunstone Views section](#). There is also the `/etc/one/sunstone-views.yaml` file that defines an alternative method to set the view for each user or group.

Sunstone will calculate the views available to each user using:

- From all the groups the user belongs to, the views defined inside each group are combined and presented to the user
- If no views are available from the user's group, the defaults would be fetched from `/etc/one/sunstone-views.yaml`. Here, views can be defined for:
 - Each user (`users:` section): list each user and the set of views available for her.
 - Each group (`groups:` section): list the set of views for the group.
 - The default view: if a user is not listed in the `users:` section, nor its group in the `groups:` section, the default views will be used.
 - The default views for group admins: if a group admin user is not listed in the `users:` section, nor its group in the `groups:` section, the `default_groupadmin` views will be used.

By default, users in the `oneadmin` group have access to all views, and users in the `users` group can use the `cloud` view.

The following `/etc/one/sunstone-views.yaml` example enables the user (`user.yaml`) and the cloud (`cloud.yaml`) views for helen and the cloud (`cloud.yaml`) view for group `cloud-users`. If more than one view is available for a given user the first one is the default.

```
---
logo: images/opennebula-sunstone-v4.0.png
users:
  helen:
    - cloud
    - user
groups:
  cloud-users:
    - cloud
default:
  - user
default_groupadmin:
  - groupadmin
  - cloud
```

A Different Endpoint for Each View

OpenNebula *Sunstone views* can be adapted to deploy a different endpoint for each kind of user. For example if you want an endpoint for the admins and a different one for the cloud users. You just have to deploy a *new sunstone server* and set a default view for each sunstone instance:

```
# Admin sunstone
cat /etc/one/sunstone-server.conf
...
:host: admin.sunstone.com
...

cat /etc/one/sunstone-views.yaml
...
users:
groups:
default:
  - admin
```

```
# Users sunstone
cat /etc/one/sunstone-server.conf
...
:host: user.sunstone.com
...

cat /etc/one/sunstone-views.yaml
...
users:
groups:
default:
  - user
```

5.3 Sunstone Views

The OpenNebula Sunstone Views can be grouped into two different layouts. On one hand, the classic Sunstone layout exposes a complete view of the cloud, allowing administrators and advanced users to have full control of any physical or virtual resource of the cloud. On the other hand, the cloud layout exposes a simplified version of the cloud, where end-users will be able to manage any virtual resource of the cloud without taking care of physical resource management.

Using the OpenNebula Sunstone Views you will be able to provide a simplified UI aimed at end-users of an OpenNebula cloud. The OpenNebula Sunstone Views are fully customizable, so you can easily enable or disable specific information tabs or action buttons. *You can define multiple views for different user groups.* You can define multiple views for different user groups. Each view defines a set of UI components, so each user just accesses and views the relevant parts of the cloud for her role. Default views:

- *Admin View.*
- *Group Admin View.*
- *Cloud View.*
- *User View.*

These views are in 3 directories **kvm**, **vcenter** and **mixed** that Opennebula proposes by default:

- /etc/one/sunstone-views/kvm for KVM hypervisor.
- /etc/one/sunstone-views/vcenter for vCenter hypervisor.
- /etc/one/sunstone-views/mixed to manage both hypervisors in the same view.

To choose the views, you just have to change the configuration parameter **mode** in `sunstone-server.conf`.


```
# Default views directory
:mode: 'mixed'
```

The **mixed** directory includes the views explained above with all the functionality of KVM and vCenter together.

5.3.1 Default Views

Admin View

This view provides full control of the cloud. Details can be configured in the `/etc/one/sunstone-views/* /admin.yaml` file.




Group Admin View

Based on the Admin View. It provides control of all the resources belonging to a group, but with no access to resources outside that group, that is, restricted to the physical and virtual resources of the group. This view features the ability to create new users within the group as well as set and keep track of user quotas. For more information on how to configure this scenario see this section

Cloud View

This is a simplified view, mainly intended for end-users that just require a portal where they can provision new virtual machines easily from pre-defined Templates. For more information about this view, please check the `/etc/one/sunstone-views/*/cloud.yaml` file.

In this scenario the cloud administrator must prepare a set of templates and images and make them available to the cloud users. These Templates must be ready to be instantiated. Before using them, users can optionally customize the VM capacity, add new network interfaces, and provide values required by the template. Thereby, the user doesn't have to know any details of the infrastructure, such as networking or storage. For more information on how to configure this scenario see this section



Virtual Machines

Owner	RUNNING	DEPLOYING	OFF	ERROR
11	103	17	46	0


Group
4

Virtual Machines

Add **Grid**

User View

Based on the Admin View; it is an advanced user view. It is intended for users that need access to more actions than the limited set available in the cloud view. Users will not be able to manage nor retrieve the hosts and clusters of the cloud. They will be able to see Datastores and Virtual Networks in order to use them when creating a new Image or Virtual Machine, but they will not be able to create new ones. Details can be configured in the `/etc/one/sunstone-views/*/user.yaml` file.



Dashboard

Virtual Networks		Images	
15	VNETS	1	USED
6	USED IPs	1 GB	USED

Virtual Machines			
10	ACTIVE	0	FAILED
2	PENDING		

5.3.2 Configuring Access to the Views

By default, the `admin` view is only available to the `oneadmin` group. New users will be included in the `users` group and will use the default `cloud` view. The views assigned to a given group can be defined in the group creation form or by updating an existing group to implement different OpenNebula models. For more information on the different OpenNebula models please check the [Understanding OpenNebula documentation](#).

5.3.3 Usage

Sunstone users can change their current view from the top-right drop-down menu:

They can also configure several options from the settings tab:

- Views: change between the different available views.
- Language: select the language that they want to use for the UI.
- Use secure websockets for VNC: Try to connect using secure websockets when starting VNC sessions.

- Display Name: If the user wishes to customize the username that is shown in Sunstone, it is possible to do so by adding a special parameter named SUNSTONE/DISPLAY_NAME with the desired value. It is worth noting that Cloud Administrators may want to automate this with a hook on user create in order to fetch the user name from outside OpenNebula.

These options are saved in the user template, as well as other hidden settings, like for instance the attribute that lets Sunstone remember the number of items displayed in the datatables per user. If not defined, defaults from /etc/one/sunstone-server.conf are taken.

The screenshot shows the 'Settings' tab in the OpenNebula Sunstone interface. On the left, there's a sidebar with navigation links: Dashboard, Instances, Templates, Storage, Network, Infrastructure, System, and Settings. A message box indicates 'Officially supported' and 'Not connected'. Below the sidebar is a 'Sign in' button and the text 'OpenNebula 5.10.5 by OpenNebula Systems'. The main content area has tabs for Info, Quotas, Group Quotas, Accounting, Showback, and Auth. The 'Info' tab is selected, displaying user details: ID (0), Name (oneadmin), Table Order (-), Language (-), View (admin), and Default Zone Endpoint (-). There are edit icons next to each field. Below this is an 'Attributes' section with a TOKEN_PASSWORD entry (6b375a0586526021465b607f9d44996e9da575ea9c1a1ca9ac1825d519f5315) with edit and delete icons. A large text input field at the bottom contains the placeholder 'label/fedora'.

5.4 Labels

The screenshot shows the 'Edit Labels' interface. At the top are two buttons: a grey one with a tag icon and a red one with a trash bin icon. The main area has a title 'Edit Labels' and a tree view under a dropdown menu. The tree shows a 'label' node with a checked checkbox, and under it are 'linux' and 'label_persist' nodes, both also with checked checkboxes. Below the tree is a search bar containing the text 'label/fedora'.

Labels can be defined for most of the OpenNebula resources from the admin view. Each resource will store the label information in its own template, thus it can be easily edited from the CLI or Sunstone. This feature enables the

possibility to group the different resources under a given label and filter them in the admin and cloud views. The user will be able to easily find the template she wants to instantiate, or select a set of resources to apply a given action.

The screenshot shows the OpenNebula Sunstone interface. On the left, there is a navigation sidebar with the following structure:

- Open Nebula** logo
- Dashboard**
- Instances**
 - VMs** (selected)
 - default**
 - label**
 - label_persist**
- Services**
- Virtual Routers**
- Templates**
- Storage**
- Network**
- Infrastructure**
- System**
- Settings**

The main area is titled "VMs" and displays a table of virtual machines. The table has columns: ID, Name, Owner, Group, and Status. There are two entries:

ID	Name	Owner	Group	Status
1	Ttylinux - KVM-1	oneadmin	oneadmin	RUNNING
0	Ttylinux - KVM-0	oneadmin	oneadmin	RUNNING

Below the table, it says "Showing 1 to 2 of 2 entries". At the bottom, there are statistics: 2 TOTAL, 2 ACTIVE, 0 OFF, 0 PENDING, 0 FA.

To the right of the table, there are two sections:

- Edit Labels**: A panel with checkboxes for "label" and "label_persist".
- System Labels**: A list of system labels: "default" (checked) and "oneadmin". Below this is a text input field labeled "Add Label".

The list of labels defined for each pool will be shown in the left navigation menu. After clicking on one of these labels only the resources with this label will be shown in the table. This filter is also available in the cloud view inside the virtual machine creation form to easily select a specific template.

To create a label hierarchy, use the '/' character. For example, you could have the labels 'Linux/Ubuntu' and 'Linux/CentOS'. Please note that a resource with the label 'Linux/Ubuntu' is not automatically added to the parent 'Linux' label, but you can do it explicitly.

5.4.1 Persistent Labels

You can also create persistent labels. These types of labels will not be deleted even when they have no associated resources. To define persistent tags we have 2 options, defining them as system tags, and including them in the file /etc/one/sunstone-views.yaml or adding them to the user's template. This second form can be done through the CLI or through the sunstone interface, doing Click on the padlock of already-created tags.

Edit Labels

- label
- label_persist

System Labels

- default
- oneadmin

Add Label

User Labels

These labels will be saved in the user's template when the user clicks on the padlock. These labels are easily editable from the CLI or Sunstone interface. Add the following template when you save a label in the user's template

```
TEMPLATE = [
    LABELS = "labels_persist,label_persist_2"
]
```

System Labels

These labels are defined in `/etc/one/sunstone-views.yaml`. You can separate them per groups of users or introduce them into the default section.

```
logo: images/opennebula-5.0.png
groups:
  oneadmin:
    - admin
    - admin_vcenter
    - groupadmin
    - groupadmin_vcenter
    - user
    - cloud
    - cloud_vcenter
```

```

default:
  - cloud
default_groupadmin:
  - groupadmin
  - cloud
labels_groups:
  oneadmin:
    - oneadmin
  default:
    - default

```

5.4.2 Defining a New OpenNebula Sunstone View or Customizing an Existing one

View definitions are placed in the `/etc/one/sunstone-views/*` directory. Each view is defined by a configuration file, in the form:

```
<view_name>.yaml
```

The name of the view will be the filename without the yaml extension.

```

/etc/one/
...
|-- sunstone-views/
|   |-- mixed/
|   |   |-- admin.yaml      <--- the admin view
|   |   `-- cloud.yaml     <--- the cloud view
|   |-- kvm/
|   |   |-- admin.yaml      <--- the admin view
|   |   `-- cloud.yaml     <--- the cloud view
|   |-- vcenter/
|   |   |-- admin.yaml      <--- the admin view
|   |   `-- cloud.yaml     <--- the cloud view
`-- sunstone-views.yaml
...

```

Note: The easiest way to create a custom view is to copy the `admin.yaml` or `cloud.yaml` file and modify it as needed.

Admin View Customization

The contents of a view file specifies the logos, links, confirm actions, group filter, enabled features, visible tabs, and enabled actions.

- *small_logo*: Image path to customize the Sunstone logo in admin views. By default, the OpenNebula logo.
- *provision_logo*: Image path to customize the Sunstone logo in user views. By default, the OpenNebula logo.
- *link_logo*: External URL below the logo.
- *text_link_logo*: Text link for link_logo.
- *confirm_vms*: If true, the user will need to confirm the actions on a VM.
- *filter_view*: If false, hides the group name by which it's filtering.

For the dashboard, the following widgets can be configured:

```
# The following widgets can be used inside any of the '_per_row' settings
# below. As the name suggests, the widgets will be scaled to fit one,
# two, or three per row. The footer uses the widgets at full size, i.e.
# one per row.
#
# - storage
# - users
# - network
# - hosts
# - vms
# - groupquotas
# - quotas
panel_tabs:
actions:
    Dashboard.refresh: false
    Sunstone.toggle_top: false
widgets_one_per_row:
    - hosts
widgets_three_per_row:
widgets_two_per_row:
    - vms
    - users
    - storage
    - network
widgets_one_footer:
```

Inside features there are twelve settings:

- **showback**: When this is false, all Showback features are hidden. The monthly report tables, and the cost for new VMs in the create VM wizard.
- **secgroups**: If true, the create VM wizard will allow adding security groups to each network interface.
- **instantiate_hide_cpu**: If true, hide the CPU setting in the VM creation dialog.
- **instantiate_cpu_factor**: False to not scale the CPU from VCPU. Number [0, 1] to scale.
- **instantiate_persistent**: True to show the option to make an instance persistent.
- **vcenter_vm_folder**: True to show an input to specify the VMs and Template path/folder where a vCenter VM will be deployed.
- **show_ds_instantiate**: True to show the datastore datatable to instantiate the VM.
- **show_vmgpoinstantiate**: True to show the vmgroup datatable to instantiathe VM.
- **show_vnet_instantiate**: True to show the vnet datatable to instantiate the VM.
- **show_host_instantiate**: True to show the host datatable to instantiate the VM.
- **show_monitoring_info**: True to show monitoring info (VM & VRouter).
- **show_attributes_info**: True to show attributes info (VM & VRouter).
- **resize_enforce**: If set to True, the host capacity will be checked. This will only affect oneadmin requests; limits on regular users' resize requests will always be enforced.
- **deploy_enforce**: If set to True, the host capacity will be checked. This will only affect oneadmin requests; limits on regular users' resize requests will always be enforced.
- **migrate_enforce**: If set to True, the host capacity will be checked. This will only affect oneadmin requests; limits on regular users' resize requests will always be enforced.

```

features:
  # True to show showback monthly reports, and VM cost
  showback: true

  # Allows to change the security groups for each network interface
  # on the VM creation dialog
  secgroups: true

```

This file also defines the tabs available in the view. (Note: the tabs is one of the main sections of the UI, those in the left-side menu.) Each tab can be enabled or disabled by updating the `enabled_tabs`: attribute. For example to disable the Clusters tab, comment out the `clusters-tab` entry:

```

enabled_tabs:
  - dashboard-tab
  - instances-top-tab
  - vms-tab
  - oneflow-services-tab
  - templates-top-tab
  - templates-tab
  - oneflow-templates-tab
  - storage-top-tab
  - datastores-tab
  - images-tab
  - files-tab
  - marketplaces-tab
  - marketplaceapps-tab
  - network-top-tab
  - vnets-tab
  - vrouters-tab
  - vnets-topology-tab
  - secgroups-tab
  - infrastructure-top-tab
  #- clusters-tab
  - hosts-tab
  - zones-tab
  - system-top-tab
  - users-tab
  - groups-tab
  - vdcs-tab
  - acls-tab
  - settings-tab
  - support-tab

```

Each tab can be tuned by selecting:

- The individual resource tabs available (`panel_tabs`: attribute) in the tab; these are the tabs activated when an object is selected (e.g. the information, or capacity tabs in the Virtual Machines tab).
- The columns shown in the main information table (`table_columns`: attribute).
- The action buttons available to the view (`actions`: attribute).

The attributes in each of the above sections should be self-explanatory. As an example, the following section defines a simplified datastore tab, without the info panel tab and no action buttons:

```

datastores-tab:
  panel_tabs:
    datastore_info_tab: false
    datastore_image_tab: true

```

```

datastore_clusters_tab: false
table_columns:
  - 0          # Checkbox
  - 1          # ID
  - 2          # Owner
  - 3          # Group
  - 4          # Name
  - 5          # Capacity
  - 6          # Cluster
  #- 7          # Basepath
  #- 8          # TM
  #- 9          # DS
  - 10         # Type
  - 11         # Status
  #- 12         # Labels
actions:
  Datastore.refresh: true
  Datastore.create_dialog: false
  Datastore.import_dialog: false
  Datastore.addtocluster: false
  Datastore.rename: false
  Datastore.chown: false
  Datastore.chgrp: false
  Datastore.chmod: false
  Datastore.delete: false
  Datastore.enable: false
  Datastore.disable: false

```

Cloud View Customization

The cloud layout can also be customized by changing the corresponding `/etc/one/sunstone-views/` yaml files. In this file you can customize the options available when instantiating a new template, the dashboard setup, or the resources available for cloud users.

Features

- `showback`: When this is false, all Showback features are hidden: the monthly report tables, and the cost for new VMs in the create VM wizard.
- `secgroups`: If true, the create VM wizard will allow adding security groups to each network interface.
- `instantiate_hide_cpu`: If true, hide the CPU setting in the VM creation dialog.
- `instantiate_cpu_factor`: False to not scale the CPU from VCPU. Number [0, 1] to scale.
- `instantiate_persistent`: True to show the option to make an instance persistent.
- `cloud_vm_create`: True to allow creating machines by cloud users.
- `show_monitoring_info`: True to show the monitoring info (VM & VRouters).
- `show_attributes_info`: True to show the attributes info (VM & VRouters).
- `show_attach_disk_advanced`: True to show advanced options in the attach disk dialog.
- `show_attach_nic_advanced`: True to show advanced options in the attach NIC dialog.

```

features:
  # True to show showback monthly reports, and VM cost
  showback: true

  # Allows changing the security groups for each network interface
  # on the VM creation dialog
  secgroups: true

```

Resources

The list of VMs is always visible. The list of VM Templates and OneFlow Services can be hidden with the provision_tabs setting.

```

tabs:
  provision-tab:
    provision_tabs:
      flows: true
      templates: true

```

Dashboard

The dashboard can be configured to show users' quotas, group quotas, overview of user VMs, and an overview of group VMs.

```

tabs:
  dashboard:
    # Connected user's quotas
    quotas: true
    # Overview of connected user's VMs
    vms: true
    # Group's quotas
    vdcquotas: false
    # Overview of group's VMs
    vdcvms: false

```

Create VM Wizard

The create VM wizard can be configured with the following options:

```

tabs:
  create_vm:
    # True to allow capacity (CPU, MEMORY, VCPU) customization
    capacity_select: true
    # True to allow NIC customization
    network_select: true
    # True to allow DISK size customization
    disk_resize: true

```

Actions

The actions available for a given VM can be customized and extended by modifying the yaml file. You can even insert VM panels from the admin view into this view, for example to use the disk snapshots or scheduled actions.

- Hiding the delete button

```
tabs:
  provision-tab:
    ...
    actions: &provisionactions
    ...
    VM.shutdown_hard: false
    VM.delete: false
```

- Using undeploy instead of power off

```
tabs:
  provision-tab:
    ...
    actions: &provisionactions
    ...
    VM.poweroff: false
    VM.poweroff_hard: false
    VM.undeploy: true
    VM.undeploy_hard: true
```

- Adding panels from the admin view, for example the disk snapshots tab

```
tabs:
  provision-tab:
    panel_tabs:
      ...
      vm_snapshot_tab: true
      ...
    ...
  actions: &provisionactions
  ...
  VM.disk_snapshot_create: true
  VM.disk_snapshot_revert: true
  VM.disk_snapshot_delete: true
```

Open Nebula Dashboard VMs Templates Services oneadmin OpenNebula Officially supported

Ttylinux - KVM-1

RUNNING

- x0.1 - 128MB - Ttylinux - KVM
- 192.168.122.12, 192.168.122.13
- oneadmin 1h ago - ID: 1

Actions:

Metrics:

- CPU: Shows usage over time from 16:33 to 17:23.
- Memory: Shows usage over time from 16:33 to 17:23.
- Net RX: Shows receive rate over time from 16:33 to 17:23.
- Net TX: Shows transmit rate over time from 16:33 to 17:23.
- Net Download Speed: Shows download speed over time from 16:33 to 17:23.
- Net Upload Speed: Shows upload speed over time from 16:33 to 17:23.

Storage:

ID	Target	Image / Size-Format	Size	Persistent	Actions
0	vda	Ttylinux - KVM	27MB/200MB	NO	
1	hda	Context	1MB/-	NO	

Showing 1 to 2 of 2 entries

Cost / MByte: 0

Disk Metrics:

- Disk read bytes: Shows read bytes over time from 16:33 to 17:23.
- Disk write bytes: Shows write bytes over time from 16:33 to 17:23.
- Disk read IOPS: Shows read IOPS over time from 16:33 to 17:23.
- Disk write IOPS: Shows write IOPS over time from 16:33 to 17:23.

Autorefresh

VM autorefresh time (ms) of the individual VM view. By default, 10 seconds. You must add the following line in `vms-tab` in the different views:

```
actions:
  VM.refresh: true
  ...
  VM.menu_labels: true
autorefresh_info: 5000 # ms
```

5.5 User Security and Authentication

By default Sunstone works with the core authentication method (user and password) although you can configure any authentication mechanism supported by OpenNebula. In this section you will learn how to enable other authentication methods and how to secure the Sunstone connections through SSL.

5.5.1 Authentication Methods

Authentication is two-fold:

- **Web client and Sunstone server.** Authentication is based on the credentials stored in the OpenNebula database for the user. Depending on the type of these credentials the authentication method can be: sunstone, x509 and opennebula (supporting LDAP or other custom methods).
- **Sunstone server and OpenNebula core.** The requests of a user are forwarded to the core daemon, including the original user name. Each request is signed with the credentials of a special `server` user. This authentication mechanism is based either on symmetric key cryptography (default) or x509 certificates. Details on how to configure these methods can be found in the [Cloud Authentication section](#).

The following sections detail the client-to-Sunstone server authentication methods.

Basic Auth

In the basic mode, username and password are matched to those in OpenNebula's database in order to authorize the user at the time of login. Rack cookie-based sessions are then used to authenticate and authorize the requests.

To enable this login method, set the `:auth:` option of `/etc/one/sunstone-server.conf` to `sunstone`:

```
:auth: sunstone
```

OpenNebula Auth

Using this method the credentials included in the header will be sent to the OpenNebula core, and the authentication will be delegated to the OpenNebula auth system using the specified driver for that user. Therefore any OpenNebula auth driver can be used through this method to authenticate the user (e.g. LDAP). The sunstone configuration is:

```
:auth: opennebula
```

x509 Auth

This method performs the login to OpenNebula based on a x509 certificate DN (Distinguished Name). The DN is extracted from the certificate and matched to the password value in the user database.

The user password has to be changed by running one of the following commands:

```
$ oneuser chauth new_user x509 "/C=ES/O=ONE/OU=DEV/CN=clouduser"
```

or the same command using a certificate file:

```
$ oneuser chauth new_user --x509 --cert /tmp/my_cert.pem
```

New users with this authentication method should be created as follows:

```
$ oneuser create new_user "/C=ES/O=ONE/OU=DEV/CN=clouduser" --driver x509
```

or using a certificate file:

```
$ oneuser create new_user --x509 --cert /tmp/my_cert.pem
```

To enable this login method, set the :auth: option of /etc/one/sunstone-server.conf to x509:

```
:auth: x509
```

The login screen will not display the username and password fields anymore, as all information is fetched from the user certificate:



Note that OpenNebula will not verify that the user is holding a valid certificate at the time of login: this is expected to be done by the external container of the Sunstone server (normally Apache), whose job is to tell the user's browser that the site requires a user certificate, and to check that the certificate is consistently signed by the chosen Certificate Authority (CA).

Warning: The Sunstone x509 auth method only handles the authentication of the user at the time of login. Authentication of the user certificate is a complementary setup, which can rely on Apache.

Remote Auth

This method is similar to x509 auth. It performs the login to OpenNebula based on a Kerberos REMOTE_USER. The USER@DOMAIN is extracted from the REMOTE_USER variable and matched to the password value in the user

database. To use Kerberos authentication, users need to be configured with the public driver. Note that this will prevent users authenticating through the XML-RPC interface; only Sunstone access will be granted to these users. To update existing users to use Kerberos authentication, change the driver to public and update the password as follows:

```
$ oneuser chauth new_user public "new_user@DOMAIN"
```

New users with this authentication method should be created as follows:

```
$ oneuser create new_user "new_user@DOMAIN" --driver public
```

To enable this login method, set the :auth: option of /etc/one/sunstone-server.conf to remote:

```
:auth: remote
```

The login screen will not display the username and password fields anymore, as all information is fetched from the Kerberos server or a remote authentication service.

Note that OpenNebula will not verify that the user is holding a valid Kerberos ticket at the time of login: this is expected to be done by the external container of the Sunstone server (normally Apache), whose job is to tell the user's browser that the site requires a valid ticket to login.


Warning: The Sunstone remote auth method only handles the authentication of the user at the time of login. Authentication of the remote ticket is a complementary setup, which can rely on Apache.

Two Factor Authentication

With this method, not only does it request a username and password, it also requires a token generated by any of these applications: [Google Authentication](#), [Authy](#) or [Microsoft Authentication](#).

To enable this, you must follow these steps:

- Log in sunstone, and select menu **Setting**. Inside find and select the tab **Auth**



The screenshot shows the OpenNebula Sunstone interface. On the left is a sidebar with links: Dashboard, Instances, Templates, Storage, Network, Infrastructure, System, and Settings. The Settings link is underlined. The main area has a header 'Settings' and a sub-header 'Auth'. Below these are tabs: Info (which is active), Quotas, Group Quotas, Accounting, Showback, and Auth. Under the 'Auth' tab, there is a section titled 'Information' with the following table:

ID	0
Name	oneadmin
Table Order	-
Language	-
View	-

Each row has a checkbox icon to its right.

- Inside find and select the button **Manage two factor authentication**

The screenshot shows the OpenNebula Settings interface. On the left is a sidebar with links like Dashboard, Instances, Templates, Storage, Network, Infrastructure, System, and Users. The main area has tabs for Info, Quotas, Group Quotas, Accounting, Showback, and Auth (which is underlined). Under Auth, there's a section for Authentication with sub-options for core, Two factor authentication, Password, and Login token. Below these are buttons for Manage two factor authentication, View, and Manage login tokens.

- A window will appear with a QR code. It must be scanned with the app [Google Authentication](#), [Authy](#) or [Microsoft Authentication](#). That will generate a 6-character code which you must place in the code input field.

Two Factor Authentication

Two factor authentication can be enabled for logging into Sunestone UI.



- Get authenticator app: [Authy](#), [Google Authenticator](#), [Microsoft Authenticator](#).
- Scan this Barcode.
- Enter Verification Code.

[Enable](#)

Internally sunstone adds the field **TWO_FACTOR_AUTH_SECRET**.

```
SUNSTONE=[  
    TWO_FACTOR_AUTH_SECRET="2LJUUXIEEYAK6NQR" ]  
TOKEN_PASSWORD="5dcff75786fdb552f31e3c6af105a7de0b5cd0dfcca42a77349c7c9ff9038cc3"
```

- To disable 2FA, go to the setting, Auth and select the button **Disable**.

This screenshot shows the same OpenNebula Settings interface as the previous one, but the 'Two factor authentication' section has been modified. The 'core' label and the 'View' and 'Manage login tokens' buttons are still present, but a new 'Disable' button has been added to the right of the 'Two factor authentication' label.

5.5.2 Configuring an SSL Proxy

OpenNebula Sunstone runs natively just on normal HTTP connections. If the extra security provided by SSL is needed, a proxy can be set up to handle the SSL connection that forwards the request to the Sunstone server and returns the answer to the client.

This set up needs:

- A server certificate for the SSL connections
- An HTTP proxy that understands SSL
- OpenNebula Sunstone configuration to accept requests from the proxy

If you want to try out the SSL setup easily, the following lines provide an example to set a self-signed certificate to be used by a web server configured to act as an HTTP proxy to a correctly configured OpenNebula Sunstone.

Let's assume the server where the proxy is going to be started is called `cloudserver.org`. Therefore, the steps are:

Step 1: Server Certificate (Snakeoil)

We are going to generate a snakeoil certificate. If using an Ubuntu system follow the next steps (otherwise your mileage may vary, but not a lot):

- Install the `ssl-cert` package

```
# apt-get install ssl-cert
```

- Generate the certificate

```
# /usr/sbin/make-ssl-cert generate-default-snakeoil
```

- As we are using lighttpd, we need to append the private key to the certificate to obtain a server certificate valid to lighttpd

```
# cat /etc/ssl/private/ssl-cert-snakeoil.key /etc/ssl/certs/ssl-cert-snakeoil.pem > /etc/lighttpd/server.pem
```

Step 2: SSL HTTP Proxy

lighttpd

You will need to edit the `/etc/lighttpd/lighttpd.conf` configuration file and

- Add the following modules (if not present already)
 - mod_access
 - mod_alias
 - mod_proxy
 - mod_accesslog
 - mod_compress
- Change the server port to 443 if you are going to run lighttpd as root, or any number above 1024 otherwise:

```
server.port = 8443
```

- Add the proxy module section:

```
#### proxy module
## read proxy.txt for more info
proxy.server = ( "" =>
                  ( " " =>
                      (
                          "host" => "127.0.0.1",
                          "port" => 9869
                      )
                  )
              )

#### SSL engine
ssl.engine = "enable"
ssl.pemfile = "/etc/lighttpd/server.pem"
```

The host must be the server hostname of the computer running the Sunstone server, and the port the one that the Sunstone Server is running on.

nginx

You will need to configure a new virtual host in nginx. Depending on the operating system and the method of installation, nginx loads virtual host configurations from either `/etc/nginx/conf.d` or `/etc/nginx/sites-enabled`.

- A sample `cloudserver.org` virtual host is presented next:

```
#### OpenNebula Sunstone upstream
upstream sunstone {
    server 127.0.0.1:9869;
}

#### cloudserver.org HTTP virtual host
server {
    listen 80;
    server_name cloudserver.org;

    ### Permanent redirect to HTTPS (optional)
    return 301 https://$server_name:8443;
}

#### cloudserver.org HTTPS virtual host
server {
    listen 8443;
    server_name cloudserver.org;

    ### SSL Parameters
    ssl on;
    ssl_certificate /etc/ssl/certs/ssl-cert-snakeoil.pem;
    ssl_certificate_key /etc/ssl/private/ssl-cert-snakeoil.key;

    ### Proxy requests to upstream
    location / {
```

```

        proxy_pass          http://sunstone;
        proxy_set_header    X-Real-IP $remote_addr;
        proxy_set_header    X-Forwarded-For $proxy_add_x_forwarded_for;
        proxy_set_header    X-Forwarded-Proto $scheme;
    }
}

```

The IP address and port number used in `upstream` must be the ones the server Sunstone is running on. On typical installations the nginx master process is run as user root so you don't need to modify the HTTPS port.

Step 3: Sunstone Configuration

Edit `/etc/one/sunstone-server.conf` to listen at localhost:9869.

```

:host: 127.0.0.1
:port: 9869

```

Once the proxy server is started, OpenNebula Sunstone requests using HTTPS URIs can be directed to `https://cloudserver.org:8443`, that will then be unencrypted, passed to localhost, port 9869, satisfied (hopefully), encrypted again and then passed back to the client.

Note: To change the `serveradmin` password, follow the next steps:

```

#oneuser passwd 1 --sha256 <PASSWORD>
#echo 'serveradmin:PASSWORD' > /var/lib/one/.one/oneflow_auth
#echo 'serveradmin:PASSWORD' > /var/lib/one/.one/ec2_auth
#echo 'serveradmin:PASSWORD' > /var/lib/one/.one/onegate_auth
#echo 'serveradmin:PASSWORD' > /var/lib/one/.one/occi_auth
#echo 'serveradmin:PASSWORD' > /var/lib/one/.one/sunstone_auth

```

Restart Sunstone after changing the password.

5.6 Cloud Servers Authentication

OpenNebula ships with two servers: *Sunstone* and EC2. When a user interacts with one of them, the server authenticates the request and then forwards the requested operation to the OpenNebula daemon.

The forwarded requests between the servers and the core daemon include the original user name, and are signed with the credentials of a special `server` user.

In this guide this request forwarding mechanism is explained, and how it is secured with a symmetric-key algorithm or x509 certificates.

5.6.1 Server Users

The *Sunstone* and EC2 services communicate with the core using a `server` user. OpenNebula creates the **serveradmin** account at bootstrap, with the authentication driver **server_cipher** (symmetric key).

This `server` user uses a special authentication mechanism that allows the servers to perform an operation on behalf of another user.

You can strengthen the security of the requests from the servers to the core daemon by changing the serveruser's driver to **server_x509**. This is specially relevant if you are running your server in a machine other than the frontend.

Please note that you can have as many users with a **server_*** driver as you need. For example, you may want to have Sunstone configured with a user with **server_x509** driver, and EC2 with **server_cipher**.

5.6.2 Symmetric Key

Enable

This mechanism is enabled by default, you will have a user named **serveradmin** with driver **server_cipher**.

To use it, you need a user with the driver **server_cipher**. Enable it in the relevant configuration file in `/etc/one`:

- *Sunstone*: `/etc/one/sunstone-server.conf`
- EC2: `/etc/one/ec2.conf`

```
:core_auth: cipher
```

Configure

You must update the configuration files in `/var/lib/one/.one` if you change the serveradmin's password, or create a different user with the **server_cipher** driver.

```
$ ls -l /var/lib/one/.one
ec2_auth
sunstone_auth

$ cat /var/lib/one/.one/sunstone_auth
serveradmin:1612b78a4843647a4b541346f678f9e1b43bbcf9
```

Warning: The serveradmin password is hashed in the database. You can use the `--sha256` flag when issuing `oneuser passwd` command for this user.

Warning: When Sunstone is running in a different machine than oned you should use an SSL connection. This can be achieved with an SSL proxy like stunnel or apache/nginx acting as proxy. After securing the OpenNebula XML-RPC connection, configure Sunstone to use https with the proxy port:

```
:one_xmlrpc: https://frontend:2634/RPC2
```

5.6.3 x509 Encryption

Enable

To enable it, change the authentication driver of the **serveradmin** user, or create a new user with the driver **server_x509**:

```
$ oneuser chauth serveradmin server_x509
$ oneuser passwd serveradmin --x509 --cert usercert.pem
```

The serveradmin account should look like:

```
$ oneuser list

  ID GROUP      NAME          AUTH
  ↵PASSWORD
  ↵ 0 oneadmin   oneadmin     core
  ↵c24783ba96a35464632a624d9f829136edc0175e
  ↵ 1 oneadmin   serveradmin  server_x           /C=ES/O=ONE/OU=DEV/
  ↵CN=server
```

You need to edit `/etc/one/auth/server_x509_auth.conf` and uncomment all the fields. The defaults should work:

```
# User to be used for x509 server authentication
:srv_user: serveradmin

# Path to the certificate used by the OpenNebula Services
# Certificates must be in PEM format
:one_cert: "/etc/one/auth/cert.pem"
:one_key: "/etc/one/auth/pk.pem"
```

Copy the certificate and the private key to the paths set in `:one_cert:` and `:one_key:`, or simply update the paths.

Then edit the relevant configuration file in `/etc/one`:

- `Sunstone`: `/etc/one/sunstone-server.conf`
- `EC2`: `/etc/one/econe.conf`

```
:core_auth: x509
```

Configure

To trust the serveradmin certificate (`/etc/one/auth/cert.pem` if you used the default path) the CA's certificate must be added to the `ca_dir` defined in `/etc/one/auth/x509_auth.conf`. See the [x509 Authentication guide for more information](#).

```
$ openssl x509 -noout -hash -in cacert.pem
78d0bbd8

$ sudo cp cacert.pem /etc/one/auth/certificates/78d0bbd8.0
```

5.6.4 Tuning & Extending

Files

You can find the drivers in these paths:

- `/var/lib/one/remotes/auth/server_cipher/authenticate`
- `/var/lib/one/remotes/auth/server_server/authenticate`

Authentication Session String

OpenNebula users with the driver **server_cipher** or **server_x509** use a special authentication session string (the first parameter of the XML-RPC calls). A regular authentication token is in the form:

```
username:secret
```

whereas a user with a **server_*** driver must use this token format:

```
username:target_username:secret
```

The core daemon understands a request with this authentication session token as “perform this operation on behalf of target_user”. The `secret` part of the token is signed with one of the two mechanisms explained before.

Two Factor Authentication

To use 2FA see the following [Link](#)

5.7 Configuring Sunstone for Large Deployments

Low to medium size enterprise clouds will typically deploy Sunstone in a single machine along with the OpenNebula daemons. However this simple deployment can be improved by:

- Isolating access from Web clients to the Sunstone server. This can be achieved by deploying the Sunstone server in a separate machine.
- Improve the scalability of the server for large user pools. Usually deploying sunstone in a separate application container in one or more hosts.

Check also the [api scalability guide](#), as those tips also have an impact on Sunstone performance.

5.7.1 Deploying Sunstone in a Different Machine

By default the Sunstone server is configured to run in the frontend, but you are able to install the Sunstone server in a machine different from the frontend.

- You will need to install only the sunstone server packages in the machine that will be running the server. If you are installing from source, use the `-s` option for the `install.sh` script.
- Make sure the `:one_xmlprc:` variable in `sunstone-server.conf` points to the place where OpenNebula frontend is running. You can also leave it undefined and export the `ONE_XMLRPC` environment variable.
- Provide the serveradmin credentials in the file `/var/lib/one/.one/sunstone_auth`. If you changed the serveradmin password please check the [Cloud Servers Authentication guide](#).
- If you want to upload files to OpenNebula, you will have to share the upload directory (`/var/tmp` by default) between sunstone and oned. Some servers do not take into account the `TMPDIR` environment variable, in which case this directory must be defined in the configuration file, for example in Passenger (`client_body_temp_path`).

```
$ cat /var/lib/one/.one/sunstone_auth
serveradmin:1612b78a4843647a4b541346f678f9e1b43bbcf9
```

Using this setup the virtual machine logs will not be available. If you need to retrieve this information you must deploy the server in the frontend.

5.7.2 Running Sunstone Inside Another Webserver

Self contained deployment of Sunstone (using `sunstone-server` script) is OK for small to medium installations. This is no longer true when the service has lots of concurrent users and the number of objects in the system is high (for example, more than 2000 simultaneous virtual machines).

The Sunstone server was modified to be able to run as a `rack` server. This makes it suitable to run in any web server that supports this protocol. In the Ruby world this is the standard supported by most web servers. We now can select web servers that support spawning multiple processes, like `unicorn`, or embedding the service inside `apache` or `nginx` web servers using the Passenger module. Another benefit will be the ability to run Sunstone in several servers and balance the load between them.

Warning: Deploying Sunstone behind a proxy in a federated environment requires some specific configuration to properly handle the Sunstone headers required by the Federation.

- `nginx`: enable `underscores_in_headers on;` and `proxy_pass_request_headers on;`

Configuring memcached

When using `one` on these web servers, use of a memcached server is necessary. Sunstone needs to store user sessions so it does not ask for user/password for every action. By default Sunstone is configured to use memory sessions, that is, the sessions are stored in the process memory. Thin and webrick web servers do not spawn new processes but new threads, and all of them have access to that session pool. When using more than one process for the Sunstone server, there must be a service that stores this information and can be accessed by all the processes. In this case we will need to install memcached. It comes with most distributions and its default configuration should be OK. We will also need to install ruby libraries to be able to access it. The rubygem library needed is `memcache-client`. If there is no package for your distribution with this ruby library you can install it using rubygems:

```
$ sudo gem install memcache-client
```

Then in the sunstone configuration (`/etc/one/sunstone-server.conf`) you will have to change the value of `:sessions` to `memcache`.

If you want to use noVNC you need to have it running. You can start this service with the command:

```
$ novnc-server start
```

Another thing you have to take into account is the user under which the server will run. The installation sets the permissions for the `oneadmin` user and group, and files like the Sunstone configuration and credentials can not be read by other users. Apache usually runs as the `www-data` user and group, so to let the server run as this user the group of these files must be changed, for example:

```
$ chgrp www-data /etc/one/sunstone-server.conf
$ chgrp www-data /etc/one/sunstone-plugins.yaml
$ chgrp www-data /var/lib/one/.one/sunstone_auth
$ chmod a+x /var/lib/one
$ chmod a+x /var/lib/one/.one
$ chmod a+x /var/lib/one/sunstone
$ chgrp www-data /var/log/one/sunstone*
$ chmod g+w /var/log/one/sunstone*
```

We advise using Passenger in your installation but we will show you how to run Sunstone inside a Unicorn web server as an example.

For more information on web servers that support rack and more information about it you can check the [rack documentation](#) page. You can alternatively check a [list of ruby web servers](#).

Running Sunstone with Unicorn

To get more information about this web server you can go to its [web page](#). It is a multi-process web server that spawns new processes to deal with requests.

The installation is done using rubygems (or with your package manager if it is available):

```
$ sudo gem install unicorn
```

In the directory where Sunstone files reside (`/usr/lib/one/sunstone` or `/usr/share/opennebula/sunstone`) there is a file called `config.ru`. This file is specific for rack applications and tells how to run the application. To start a new server using unicorn you can run this command from that directory:

```
$ unicorn -p 9869
```

The default unicorn configuration should be OK for most installations, but a configuration file can be created to tune it. For example, to tell unicorn to spawn 4 processes and write `stderr` to `/tmp/unicorn.log` we can create a file called `unicorn.conf` that contains:

```
worker_processes 4
logger debug
stderr_path '/tmp/unicorn.log'
```

and start the server and daemonize it using:

```
$ unicorn -d -p 9869 -c unicorn.conf
```

You can find more information about the configuration options in the [unicorn documentation](#).

Running Sunstone with Passenger in Apache

Warning: Since OpenNebula 5.10, all required Ruby gems are packaged and installed into a dedicated directory `/usr/share/one/gems-dist/` symlinked to `/usr/share/one/gems/`. Check the details in [Front-end Installation](#).

If the symlinked location is preserved, the shipped Ruby gems are used exclusively. It might be necessary to force the Ruby running inside the web server to use the dedicated locations by configuring the `GEMS_HOME` and `GEMS_PATH` environment variables, for example by putting following settings into your Apache configuration:

```
SetEnv GEM_PATH /usr/share/one/gems/
SetEnv GEM_HOME /usr/share/one/gems/
```

Phusion Passenger is a module for the [Apache](#) and [Nginx](#) web servers that runs ruby rack applications. This can be used to run the Sunstone server and will manage all its life cycle. If you are already using one of these servers or, just feel comfortable with one of them, we encourage you to use this method. This kind of deployment adds better concurrency and lets us add an https endpoint.

We will provide the instructions for Apache web server but the steps will be similar for nginx following [Passenger documentation](#).

The first thing you have to do is install Phusion Passenger. For this you can use pre-made packages for your distribution or follow the [installation instructions](#) from their web page. The installation is self explanatory and will guide you in all the process. Follow the guidance and you will be ready to run Sunstone.

The next thing we have to do is to configure the virtual host that will run our Sunstone server. We have to point to the `public` directory from the Sunstone installation. Here is an example:

```
<VirtualHost *:80>
    ServerName sunstone-server
    PassengerUser oneadmin
    # For OpenNebula >= 5.10, variables configuring dedicated directory
    # with shipped Ruby gems must be set if these gems weren't explicitly
    # disabled (by removing specified directory symlink).
    SetEnv GEM_PATH /usr/share/one/gems/
    SetEnv GEM_HOME /usr/share/one/gems/
    # !!! Be sure to point DocumentRoot to 'public'!
    DocumentRoot /usr/lib/one/sunstone/public
    <Directory /usr/lib/one/sunstone/public>
        # This relaxes Apache security settings.
        AllowOverride all
        # MultiViews must be turned off.
        Options -MultiViews
        # Uncomment this if you're on Apache >= 2.4:
        #Require all granted
        # Comment this if you're on OpenNebula < 5.6.0:
        Options FollowSymLinks
    </Directory>
</VirtualHost>
```

Note: It's compulsory to add the `FollowSymLinks` option in the virtual host.

Note: When you're experiencing login problems you might want to set `PassengerMaxInstancesPerApp 1` in your passenger configuration or try memcached, since Sunstone does not support sessions across multiple server instances.

Now the configuration should be ready. Restart — or reload — the Apache configuration to start the application, and point to the virtual host to check if everything is running.

Running Sunstone behind an nginx SSL Proxy

How to set things up with nginx ssl proxy for sunstone and encrypted VNC:

```
# No squealing.
server_tokens off;

# OpenNebula Sunstone upstream
upstream sunstone {
    server 127.0.0.1:9869;
}

# HTTP virtual host, redirect to HTTPS
server {
    listen 80 default_server;
    return 301 https://$server_name:443;
```

```

}

# HTTPS virtual host, proxy to Sunstone
server {
    listen 443 ssl default_server;
    ssl_certificate /etc/ssl/certs/opennebula-certchain.pem;
    ssl_certificate_key /etc/ssl/private/opennebula-key.pem;
    ssl_stapling on;
}

```

And these are the changes that have to be made to `sunstone-server.conf`:

```

UI Settings

:vnc_proxy_port: 29876
:vnc_proxy_support_wss: only
:vnc_proxy_cert: /etc/one/ssl/opennebula-certchain.pem
:vnc_proxy_key: /etc/one/ssl/opennebula-key.pem
:vnc_proxy_ipv6: false

```

If using a self-signed certificate, the connection to VNC windows in Sunstone will fail. Either get a real certificate, or manually accept the self-signed one in your browser before trying it with Sunstone. Now, VNC sessions should show “encrypted” in the title. You will need to have your browser trust that certificate for both the 443 and 29876 ports on the OpenNebula IP or FQDN.

Running Sunstone with Passenger using FreeIPA/Kerberos auth in Apache

It is also possible to use Sunstone remote authentication with Apache and Passenger. Configuration in this case is quite similar to Passenger configuration, but we must include the Apache auth module line. How to configure a FreeIPA server and Kerberos is outside of the scope of this document, you can get more info from the [FreeIPA Apache setup example](#).

for example, to include Kerberos authentication we can use two different modules: `mod_auth_gssapi` or `mod_authn_z_pam` and generate the keytab for the http service. Here is an example with Passenger:

```

LoadModule auth_gssapi_module modules/mod_auth_gssapi.so

<VirtualHost *:80>
    ServerName sunstone-server
    PassengerUser oneadmin
    # For OpenNebula >= 5.10, variables configuring dedicated directory
    # with shipped Ruby gems must be set if these gems weren't explicitly
    # disabled (by removing specified directory symlink).
    SetEnv GEM_PATH /usr/share/one/gems/
    SetEnv GEM_HOME /usr/share/one/gems/
    # !!! Be sure to point DocumentRoot to 'public'!
    DocumentRoot /usr/lib/one/sunstone/public
    <Directory /usr/lib/one/sunstone/public>
        # Only is possible to access to this dir using a valid ticket
        AuthType GSSAPI
        AuthName "EXAMPLE.COM login"
        GssapiCredStore keytab:/etc/http.keytab
        Require valid-user
        ErrorDocument 401 '<html><meta http-equiv="refresh" content="0; URL=https://
        ↪yourdomain"><body>Kerberos authentication did not pass.</body></html>'
        AllowOverride all
        # MultiViews must be turned off.
    
```

```
Options -MultiViews
</Directory>
</VirtualHost>
```

Note: Users must generate a valid ticket by running `kinit` to get access to the Sunstone service. You can also set a custom 401 document to warn users about any authentication failure.

Now our configuration is ready to use Passenger and Kerberos. Restart or reload the Apache configuration, and point to the virtual host using a valid ticket to check if everything is running.

Running Sunstone in Multiple Servers

You can run Sunstone in several servers and use a load balancer that connects to them. Make sure you are using memcache for sessions and both Sunstone servers connect to the same memcached server. To do this change the parameter `:memcache_host` in the configuration file. Also make sure that both Sunstone instances connect to the same OpenNebula server.

MarketPlace

If you plan on using the MarketPlaceApp download functionality, the Sunstone server(s) will need access to the MarketPlace backends.

If you are using Phusion Passenger, take the following recommendations into account:

- Set `PassengerResponseBufferHighWatermark` to `0`.
- Increase `PassengerMaxPoolSize`. Each MarketPlaceApp download will take one of these application processes.
- If `Passenger Enterprise` is available, set `PassengerConcurrencyModel` to `thread`.

If you are using another backend than Passenger, please port these recommendations to your backend.

VMWARE INFRASTRUCTURE SETUP

6.1 Overview

After configuring the OpenNebula front-end and the vCenter nodes, the next step is to learn what capabilities can be leveraged from the vCenter infrastructure and fine tune the OpenNebula cloud to make use of them.

The Virtualization Subsystem is the component in charge of talking with the hypervisor and taking the actions needed for each step in the VM life-cycle. This Chapter gives a detailed view of the vCenter drivers, the resources it manages and how to setup OpenNebula to leverage different vCenter features.

6.1.1 How Should I Read This Chapter

You should be reading this chapter after performing the *vCenter node install*.

This Chapter is organized in the *vCenter Driver Section*, which introduces the vCenter integration approach under the point of view of OpenNebula, with description of how to import, create and use VM Templates, resource pools, limitations and so on; the *Networking Setup Section* section that glosses over how OpenNebula can consume or create networks and how those networks can be used, the *Datastore Setup Section* which introduces the concepts of OpenNebula datastores as related to vCenter datastores, and the VMDK image management made by OpenNebula, and the *NSX Setup Section* that introduces the integration of OpenNebula with the NSX component.

After reading this Chapter, you can delve on advanced topics like OpenNebula upgrade, logging, scalability in the *Reference Chapter*. The next step should be proceeding to the Operations guide to learn how the Cloud users can consume the cloud resources that have been set up.

6.1.2 Hypervisor Compatibility

All this Chapter applies exclusively to vCenter hypervisor.

6.2 vCenter Driver Setup

The vCenter Driver is the responsible for all the integration of OpenNebula with VMware based infrastructures. All the interaction between OpenNebula and vSphere is channeled through the vCenter API, except for the VNC console connection where Sunstone server (more specifically, the noVNC server) contacts with the ESX hypervisors directly.

This section lays out the actions needed to incorporate VMware resources to an OpenNebula cloud.

6.2.1 vCenter Import Tool


vCenter clusters, VM templates, networks, datastores and VMDK files located in vCenter datastores can be easily imported into OpenNebula:

- Using the **onevcenter** tool from the command-line interface

```
$ onevcenter <command> -o <object type> -h <opennebula host_id> [<options>] [<args>]
```

- Using the Import button in Sunstone.

The Import button will be available once the `admin_vcenter` view is enabled in Sunstone. To do so, click on your user's name (Sunstone's top-right). A drop-down menu will be shown, click on Views and finally click on `admin_vcenter`.



Warning: The image import operation may take a long time. If you use the Sunstone client and receive a “Cannot contact server: is it running and reachable?” the 30 seconds Sunstone timeout may have been reached. In this case either configure Sunstone to live behind Apache/NGINX or use the CLI tool instead.

Following vCenter resources can be easily imported into OpenNebula:

- vCenter clusters (modelled as OpenNebula Hosts)
- Datastores
- Networks
- VM Templates
- Wild VMs (VMs launched outside of OpenNebula)
- Images

6.2.2 Importing vCenter Clusters

vCenter cluster is the first thing that you will want to add into your vCenter installation because all other vCenter resources depend on it. OpenNebula will import these clusters as OpenNebula hosts so you can monitor them easily using Sunstone (Infrastructure/Hosts) or through CLI (`onehost`). Also this is the only step where the authentication is to be required so it's important to assure that the process finishes successfully.

Import a cluster with **onevcenter**

When you select a vCenter Cluster to be imported, OpenNebula will create an OpenNebula Host that will represent the vCenter Cluster. Also, you'll have to tell OpenNebula in what OpenNebula Cluster you want to group the OpenNebula

Host, if you don't select a previously existing cluster, the default action is that OpenNebula will create an OpenNebula cluster for you. A vCenter Cluster may have the same name in different folders and subfolders of a datacenter, OpenNebula will inform you about the location of the vCenter Cluster so you can identify it.

A sample section follows:

```
$ onevcenter hosts --vcenter <vcenter-host> --vuser <vcenter-username> --vpass
→<vcenter-password>

Connecting to vCenter: vcenter.host...done!

Exploring vCenter resources...done!

Do you want to process datacenter Datacenter (y/[n])? y

* vCenter cluster found:
  - Name      : Cluster2
  - Location   :
Import cluster (y/[n])? y

In which OpenNebula cluster do you want the vCenter cluster to be included?

  - ID: 100 - NAME: Cluster
  - ID: 101 - NAME: Cluster3

Specify the ID of the cluster or press Enter if you want OpenNebula to create
→a new cluster for you:

OpenNebula host Cluster2 with ID 2 successfully created.
```

Note: If vCenter is using a port other than the default port, you can use the `--port` command.

Import a cluster with Sunstone

You can also import a cluster from Sunstone. Click on Hosts under the Infrastructure menu entry and then click on the Plus sign, a new window will be opened.



In the new window, select VMWare vCenter from the Type drop-down menu.

Introduce the vCenter hostname (the `<SERVER>:<PORT>` notation can be used for non default ports) or IP address and the credentials used to manage the vCenter instance and click on **Get Clusters**

The screenshot shows the 'Create Host' page. At the top, there are 'Create Host' and 'Reset' buttons. Below them is a dropdown menu labeled 'Type' with 'VMWare vCenter' selected. To the right is a dropdown for 'Cluster' with '0:default' chosen. The main area is titled 'vCenter' and contains three input fields: 'Hostname' (with a red box around it), 'User' (with a red box around it), and 'Password' (with a red box around it). At the bottom are two buttons: 'Get Clusters' (blue) and 'Import' (green).

Once you enter the vCenter credentials you'll get a list of the vCenter clusters that haven't been imported yet. You'll have the name of the vCenter cluster and the location of that cluster inside the Hosts and Clusters view in vSphere.

Note: A vCenter cluster is considered that it hasn't been imported if the cluster's moref and vCenter instance uuid is not found in OpenNebula's image pool.

If OpenNebula finds new clusters they will be grouped by the datacenter they belong.

The screenshot shows the 'Datacenter DataCenter' page. It lists three vCenter clusters: 'Cluster', 'Cluster2', and 'Cluster with spaces'. The 'Cluster' column for 'Cluster2' and 'Cluster with spaces' is empty, while for 'Cluster' it shows 'domain:c7'. The 'vCenter ref' column shows 'domain:c14042' for 'Cluster2', 'domain:c1752' for 'Cluster with spaces', and 'domain:c7' for 'Cluster'. The 'Location' column shows '/' for all three. At the bottom, there are pagination controls for 'Showing 1 to 3 of 3 entries' and 'Previous'/'Next' buttons.

Before you check one or more vCenter clusters to be imported, you can select an OpenNebula cluster from the drop-down Cluster menu, if you select the default datastore (ID:0), OpenNebula will create a new OpenNebula cluster for you.

The screenshot shows a dropdown menu for 'Cluster' with '0: default' selected. There is also a 'Select all 3 Clusters' link above the dropdown.

Select the vCenter clusters you want to import and finally click on the Import button. Once the import tool finishes you'll get the ID of the OpenNebula hosts created as representations of the vCenter clusters.

The screenshot shows the 'Datacenter DataCenter' page after importing vCenter clusters. It lists the same three clusters: 'Cluster', 'Cluster2', and 'Cluster with spaces'. The 'Cluster' column for both 'Cluster2' and 'Cluster with spaces' now contains 'domain:c14042' and 'domain:c1752' respectively. The 'vCenter ref' column shows 'domain:c14042' for 'Cluster2' and 'domain:c1752' for 'Cluster with spaces'. The 'Location' column shows '/' for all three. To the right of the table, there are two green checkmarks with the message 'Host created successfully. ID: 4' and 'Host created successfully. ID: 3'. At the bottom, there are pagination controls for 'Showing 1 to 3 of 3 entries' and 'Previous'/'Next' buttons.

You can check that the hosts representing the vCenter clusters have a name containing the cluster name, and if there is name collision with a previously imported vCenter cluster, a string is added to avoid the collision. Also you can see that if you select the default datastore, OpenNebula will assign a new OpenNebula cluster with the same name of the imported vCenter cluster.

The screenshot shows the 'Hosts' table in the 'Datacenter DataCenter' interface. It lists two hosts: 'Cluster2' (ID 4) and 'Cluster' (ID 3). The table has columns for ID, Name, Cluster, RVMs, Allocated CPU, Allocated MEM, and Status. Both hosts show 0 RVMs, 0/1000 (0%) Allocated CPU, and 0KB/31.8GB (0%) Allocated MEM. Their status is ON. The 'Name' column shows 'Cluster2' and 'Cluster' respectively.

Note that if you delete an OpenNebula host representing a vCenter cluster and if you try to import it again you may have an error like the following.



[ClusterAllocate] NAME is already taken by CLUSTER 128.

In that case should specify the right cluster from the Cluster drop-down menu or remove the OpenNebula Cluster so OpenNebula can create the cluster again automatically when the vCenter Cluster is imported.

Note: It's important to understand that OpenNebula will see vCenter Clusters as OpenNebula hosts, and an OpenNebula Cluster is created too when a new vCenter Cluster is imported as an OpenNebula host. All resources from that vCenter cluster (networks and storage) will be automatically imported to that same OpenNebula Cluster.

Note: You can define VM_PREFIX attribute within host template. This attribute means that when you instanciate a VM in this host, all vm will be named begin with VM_PREFIX.

6.2.3 Importing vCenter resources

Once you have imported your vCenter cluster you can import the rest of the vCenter resources delegating the authentication to the imported OpenNebula host. It's important then to check that the imported host is working otherwise you won't be able to import any resource with the host's credentials.

Importation tool operates with similar way in both Sunstone and Command Line Interface it's completely mandatory to have at least one vCenter cluster already working in order to import the rest of the resources, also in some case like images you need to have imported the proper datastore. Resources like Networks or Datastores could belong to more than one cluster so the tool will warn you about that situation.

We could differenciate the creation of vCenter resources with OpenNebula in two steps:

- Get concrete information about the vCenter server and the desired kind of resource, **list**:
 - [CLI] Using `onevcenter list -o <resource type> -h <host_id> [additional_info]`.
 - [Sunstone] Navigate to the proper section on sunstone and click on import button and select the proper host.

This will show you the list of objects that you can import giving you some information.

- **Import** selecteds resources based on the previous information collected by the first step:
 - [CLI] Using `onevcenter import <desired objects> -o <resource type> -h <host_id> [additional_info]`.

There are several ways to perform this operation, in this list an ID column arranging the unimported resources will appear in addition to the REF column, you can use both columns to select certain resoures:

Command (Example)	Note
<code>onevcenter import ref</code>	This will import the resource with ref
<code>onevcenter import 0</code>	This will import the first resource showd on the list, the resource with IM_ID 0
<code>onevcenter import "ref0, ref1"</code>	This will import both items with refs ref0 and ref1
<code>onevcenter import 0..5</code>	This will import items with IM_ID 0, 1, 2, 3, 4, 5

- [Sunstone] Simply select the desired resources (checking any option) from the previous list

Importing all resources with default configuration

In some scenarios you will want to import every resource of any vCenter server, the importation of some resources like could be the networks have an ‘interactive’ interface due to they require some options. This makes the automated importation a hard way for the administrator. Despite all of this in both Sunstone and onevcenter you can import all the resources from a vCenter host with the default configuration, this makes the labour of importing all resources an easy task.

- [CLI] using onevcenter import_defaults command:

```
onevcenter import_defaults -o datastores -h 0
```

This will import all datastores related to the imported OpenNebula host with ID: 0.


- [Sunstone] Click on the first checkbox at the corner of the table.

6.2.4 Importing vCenter Datastores

Virtual hard disks, which are attached to vCenter virtual machines and templates, have to be represented in OpenNebula as images. Images must be placed in OpenNebula’s image datastores which can be easily created thanks to the import tools. vCenter datastores can be imported using the **onevcenter** tool or the Sunstone user interface.

Once you run the import tool, OpenNebula gives you information about the datastores it finds on each datacenter: the name of the datastore, the capacity of the datastores, and the IDs of OpenNebula Clusters which the vCenter datastores can be assigned to. If there are no OpenNebula Cluster’s IDs it means that you haven’t imported any vCenter cluster that uses this datastore. Although it’s not mandatory that you import vCenter clusters before importing a vCenter datastore you may have later to assign a datastore to an OpenNebula cluster so OpenNebula VMs and Templates can use that datastore.

A vCenter datastore is unique inside a datacenter, so it is possible that two datastores can be found with the same name in different datacenters and/or vCenter instances. When you import a datastore, OpenNebula generates a name that avoids collisions, that name contains the datastore name, the datastore type between parentheses and, if there was another datastore with that name, a suffix. That name can be changed once the datastore has been imported to a more human-friendly name. This is sample name:



There’s an important thing to know related to imported datastores. When you import a vCenter datastore, OpenNebula will store the vCenter hostname or IP address, the vCenter user and vCenter password (encrypted) inside the datastore template definition, as OpenNebula needs that credentials to perform API actions on vCenter. So if you ever change the user or password for the vCenter connections from OpenNebula you should edit the datastore template and change that user and/or password (password can be typed on clear and OpenNebula will stored it encrypted).

VCENTER_HOST	vcenter.vcenter3		
VCENTER_PASSWORD	5TRPlpwZQAA==		
VCENTER_USER	administrator@vsphere.local		

Warning: You need to have already imported the vCenter cluster in order to import the datastore. Otherwise OpenNebula will complain that you need to import the associated vcenter cluster (see the previous point).

Import a datastore with onevcenter

Here's an example showing how a datastore is imported using the command-line interface:

First of all we already have one vCenter cluster imported with ID 0.

```
onevcenter list -o datastores -h 0

# vCenter: vCenter.server

IMID REF           NAME          CLUSTERS
0   datastore-15   datastore2   [102]
1   datastore-11   datastore1   []
2   datastore-15341 datastore1 (1) [100]
3   datastore-16   nfs          [102, 100]
```

The import tool (list) will discover datastores in each datacenter and will show the name of the datastore, the capacity and OpenNebula cluster IDs which this datastore will be added to.

Once you know what datastore you want to import:

```
onevcenter import datastore-16 -o datastores -h 0
ID: 100
ID: 101
```

When you select a datastore, two representations of the same datastore are created in OpenNebula: an IMAGE datastore and a SYSTEM datastore that's why you can see that two datastores have been created (unless the datastore is a StorageDRS, in that case only a SYSTEM datastore is created).

Import a datastore with Sunstone

In Sunstone, click on Datastores under the Storage menu entry and then click on the Import button, a new window will be opened.



In the new window, choose a cluster to authenticate you into this vCenter instance and click on **Get Datastores**.

ID	Name	Cluster	RVMs	Allocated CPU	Allocated MEM	Status
4	Cluster2	103	0	0 / 1000 (0%)	0KB / 31.8GB (0%)	ON
3	Cluster	102	0	0 / 1000 (0%)	0KB / 31.8GB (0%)	ON

When you click on the Get Datastores button you'll get a list of datastores. You'll get the name of the datastores, its capacity and the IDs of existing OpenNebula clusters where a datastore will be assigned to. Remember, if OpenNebula Clusters IDs column is empty that means that the import tool could not find an OpenNebula cluster where the datastore can be grouped and you may have to assign it by hand later or you may cancel the datastore import tool action and try to import the vCenter clusters before.

OpenNebula will search for datastores that haven't been imported yet.

vCenter Datastores: vcenter:vcenter65-1						
Select all 3 Datastores						
	Name	vCenter ref	Datacenter	Total MB	Free MB	OpenNebula Cluster IDs
	datastore2	datastore-15	Datacenter	946176	930353	103
	datastore1 (1)	datastore-15341	Datacenter	946176	583734	102
	nfs	datastore-16	Datacenter	4691989	1675846	103,102

Previous 1 Next

From the list, select the datastore you want to import and finally click on the Import button. Once you select a datastore and click on the Import button, the IDs of the datastores that have been created will be displayed:

Datacenter DataCenter						
2 Datastores selected. Select all 4 Datastores						
	Name	Total MB	Free MB	OpenNebula Cluster IDs		
	datastore2	132352	129304	128		
<input checked="" type="checkbox"/>	datastore1	230656	32433	128	 Datastores created successfully, IDs: 337,340	
	DRSDatastoreCluster	132352	129304	128		
<input checked="" type="checkbox"/>	nfs	4691989	1562332	128	 Datastores created successfully, IDs: 338,339	

Previous 1 Next

In the datastore list you can check the datastore name. Also between parentheses you can find SYS for a SYSTEM datastore, IMG for an IMAGE datastore or StorDRS for a StorageDRS cluster representation. Remember that datastore name can be changed once the datastore has been imported. Finally the datastores have been added to an OpenNebula cluster too if IDs were listed in the OpenNebula Cluster IDs column.

107	nfs(SYS)	oneadmin	oneadmin	-/-	102,103	SYSTEM	ON
106	nfs(IMG)	oneadmin	oneadmin	OKB/-	102,103	IMAGE	ON
105	datastore1 (1)(SYS)	oneadmin	oneadmin	-/-	102	SYSTEM	ON
104	datastore1 (1)(IMG)	oneadmin	oneadmin	OKB/-	102	IMAGE	ON

6.2.5 Importing vCenter VM Templates

The **onevcenter** tool and the Sunstone interface can be used to import existing VM templates from vCenter.

Important: This step should be performed **after** we have imported the datastores where the template's hard disk files are located as it was explained before.

Important: Before importing a template check that the datastores that hosts the virtual hard disks have been monitored and that they report its size and usage information. You can't create images in a datastore until it's monitored.

The import tools (either the onevcenter tool or Sunstone) gives you information about the templates, when a template is selected to be imported, you have to note that OpenNebula inspects the template in search for virtual disks and virtual network interface cards.

It's mandatory that you import vCenter datastores used by your vCenter template before importing it, because OpenNebula requires an IMAGE datastore to put the images that represents detected virtual disks. If OpenNebula doesn't find the datastore the import action will fail.

ERROR: datastore nfs: has to be imported first as an image datastore! ×

OpenNebula will create OpenNebula images that represents found disks, and OpenNebula Virtual Networks that represents the port groups used by the virtual NICs. For example, we have a template that has three disks and a nic

connected to the VM Network port group.

▶ Hard disk 1	70,00 MB
▶ Hard disk 2	10,00 MB
▶ Hard disk 3	5,00 MB
▶ Network adapter 1	VM Network (disconnected)

Indeed after the import operation finishes there will be three images representing each of the virtual disks found within the template. The name of the images have been generated by OpenNebula and contains the file name, the datastore where it's found and OpenNebula's template ID so it's easier for you to know what image is associated with what template. Note that these images are non-persistent. The name of the images can be changed after the images have been imported.

278	corelinux7_x86_64-5-000001-nfs	oneadmin	oneadmin	rfs [vcentervccenter3 - Datacenter] (IMG)	OS	READY	0
277	corelinux7_x86_64-3-000001-nfs	oneadmin	oneadmin	rfs [vcentervccenter3 - Datacenter] (IMG)	OS	READY	0
276	corelinux7_x86_64-4-000001-nfs	oneadmin	oneadmin	rfs [vcentervccenter3 - Datacenter] (IMG)	OS	READY	0

Also a virtual network will be created. The name will be the same as vCenter . Note that the virtual network is added automatically to an OpenNebula cluster which contains the vCenter cluster. E.g This network belongs to two OpenNebula clusters (100, 101) in the following screenshot.



A vCenter template name is only unique inside a folder, so you may have two templates with the same name in different folders inside a datacenter. If OpenNebula detects a collision it will add a string (based on a SHA1 hash operation on the VM Template characteristics) to the name to prevent name duplication in OpenNebula. The VM Template name in OpenNebula can be changed once it has been imported. The following screenshot shows an example:



Import a VM Template with onevcenter

This would be the process using the **onevcenter** tool.

```
$ onevcenter list -o templates -h 0

# vCenter: vceneter.Server

IMID REF      NAME
 0 vm-8720   corelinux7 x86_64 with spaces
 1 vm-9199   one-corelinux7_x86_64
 2 vm-8663   dist_nic_test
```

In this example our vceneter.server has 3 templates and they are listed from IM_ID = 0 to 2.

Whenever you are ready to import:

```
onevcenter import vm-1754 -o templates -h 0

- Template: corelinux7_x86_64
```

In this section you'll be asked several questions and different actions will be taken depending on your answers.

First you'll be prompted if you want to use linked clones.

Would you like to use Linked Clones with VMs based on this template (y/[n])?

If you want to use linked clones with the template, as explained before, you can create a copy of the template so the original template remains intact.

Do you want OpenNebula to create a copy of the template, so the original template ↵remains untouched ([y]/n)?

If you want to create a copy of the template, you can give it a name or use the same name with the one- prefix.

The new template will be named adding a one- prefix to the name of the original ↵template.

If you prefer a different name please specify or press Enter to use defaults: ↵corelinux7_linked_x86_64

If a copy of the template is used, this action may take some time as a full clone of the template and its disks has to be performed.

WARNING!!! The cloning operation can take some time depending on the size of disks. ↵Please wait...

If linked clone usage was selected, delta disks will be created and that action will also require some time.

Delta disks are being created, please be patient...

Now, either you use linked clones or not, you can select the folder where you want VMs based on this template to be shown in vSphere's VMs and Templates inventory.

Do you want to specify a folder where the deployed VMs based on this template will appear in vSphere's VM and Templates section?
If no path is set, VMs will be placed in the same location where the template lives.
Please specify a path using slashes to separate folders e.g /Management/VMs or press ↵Enter to use defaults:

OpenNebula will inspect the vCenter template and will create images and networks for the virtual disks and virtual networks associated to the template. Those actions will require some time to finish.

The existing disks and networks in the template are being imported, please be patient.
...

The template is almost ready but you have the chance to specify a Resource Pool or provide a list to users so they can select which Resource Pool will be used.

By default OpenNebula will use the first Resource Pool that is available in the datacenter unless a specific Resource Pool has been set for the host representing the vCenter cluster. If you haven't already have a look to the "Resource Pools in OpenNebula" section in this chapter so you can fully understand the following.

This template is currently set to launch VMs in the default resource pool.
Press y to keep this behaviour, n to select a new resource pool or d to delegate the choice to the user ([y]/n/d)?

If you want to select a new resource pool, a list of available Resource Pools will display so you can select one of them:

The list of available resource pools is:

- TestResourcePool/NestedResourcePool
- TestResourcePool

Please input the new default resource pool name:

If you want to create a list of Resource Pools that will allow the user to select one of them, you have the chance of accepting the list generated by the import tool or enter the references of the Resource Pools using a comma to separate the values:

```
The list of available resource pools to be presented to the user are
→ "TestResourcePool/NestedResourcePool,TestResourcePool"
Press y to agree, or input a comma separated list of resource pools to edit ([y]/
→comma separated list)
```

If you selected a list, you will be asked to select the reference of the default Resource Pool in that list:


```
The default resource pool presented to the end user is set to "TestResourcePool/
→NestedResourcePool".
Press y to agree, or input a new resource pool ([y]/resource pool name)
```

Import a VM Template with Sunstone


In Sunstone, click on VMs under the Template menu entry and then click on the Import button, a new window will be opened.




In the new window, choose a cluster to authenticate you into this vCenter instance and click on **Get Templates**.



OpenNebula will search for templates that haven't been imported yet.



Before importing a template, you can click on the down arrow next to the template's name and specify the Resource Pools as it was explained in the Resource Pools in OpenNebula section in this chapter



Note: If the vCenter cluster doesn't have DRS enabled you won't be able to use Resource Pools and hence the down arrow won't display any content at all.

Select the template you want to import and finally click on the Import button. **This process may take some time** as OpenNebula will import the disks and network interfaces that exists in the template and will create images and networks to represent them.



Once the template has been imported you get the template's ID.



Note: A vCenter template is considered that it hasn't been imported if the template's moref and vCenter instance uuid is not found in OpenNebula's template pool.

Warning: If OpenNebula does not find new templates, check that you have previously imported the vCenter clusters that contain those templates.

Warning: If you want to use linked clones with a template, please import it using the **onevcenter** tool as explained in the previous section.

Note: When an image is created to represent a virtual disk found in the vCenter template, the VCENTER_IMPORTED attribute is set to YES automatically. This attribute prevents OpenNebula to delete the file from the vCenter datastore when the image is deleted from OpenNebula.

After a vCenter VM Template is imported as a OpenNebula VM Template, it can be modified to change the capacity in terms of CPU and MEMORY, the name, permissions, etc. It can also be enriched to add:

- New disks
- New network interfaces
- Context information

Important: If you modify a VM template and you edit a disk or nic that was found by OpenNebula when the template was imported, please read the following notes:

- Disks and nics that were discovered in a vCenter template have a special attribute called OPENNEBULA_MANAGED set to NO.
- The OPENNEBULA_MANAGED=NO should only be present in DISK and NIC elements that exist in your vCenter template as OpenNebula doesn't apply the same actions that those applied to disks and nics that are not part of your vCenter template.

- If you edit a DISK or NIC element in your VM template which has OPENNEBULA_MANAGED set to NO and you change the image or virtual network associated to a new resource that is not part of the vCenter template please don't forget to remove the OPENNEBULA_MANAGED attribute in the DISK or NIC section of the VM template either using the Advanced view in Sunstone or from the CLI with the onetemplate update command.

Before using your OpenNebula cloud you may want to read about the vCenter specifics.

6.2.6 Importing running Virtual Machines

Once a vCenter cluster is monitored, OpenNebula will display any existing VM as Wild. These VMs can be imported and managed through OpenNebula once the host has been successfully acquired.

In the command line we can list wild VMs with the one host show command:

```
$ onehost show 0
HOST 0 INFORMATION
ID : 0
NAME : MyvCenterHost
CLUSTER : -
[....]

WILD VIRTUAL MACHINES

NAME IMPORT_ID CPU
MEMORY test-rp-removeme - Cluster vm-2184 1
256 [....]
```

In Sunstone we have the Wild tab in the host's information:

VM name	Remote ID
[REDACTED]	vn-2351
[REDACTED]	vm-2187
[REDACTED]	vm-1931
[REDACTED]	vm-12
[REDACTED]	vm-34
test-rp-removeme - Cluster	vm-2184

VMs in running state can be imported, and also VMs defined in vCenter that are not in Power On state (this will import the VMs in OpenNebula as in the poweroff state).

Important: Before you import a Wild VM you must have imported the datastores where the VM's hard disk files are located as it was explained before. OpenNebula requires the datastores to exist before the image that represents an existing virtual hard disk is created.

Warning: While the VM is being imported, OpenNebula will inspect the virtual disks and virtual nics and it will create images and virtual networks referencing the disks and port-groups used by the VM so the process may take some time, please be patient.

To import existing VMs you can use the ‘onehost importvm’ command.

```
$ onehost importvm 0 "test-rp-removeme - Cluster"
```

```
$ onevm list
```

ID	USER	GROUP	NAME	STAT	UCPU	UMEM	HOST	TIME
3	oneadmin	oneadmin	test-rp-removem	runn	0.00	20M	[vcenter.v]	0d 01h02

Also the Sunstone user interface can be used from the host's Wilds tab. Select a VM from the list and click on the Import button.

VM name	Remote ID
[redacted]	vm-2351
[redacted]	vm-2187
[redacted]	vm-1931
[redacted]	vm-12
[redacted]	vm-34
[redacted]	vm-2184

After a Virtual Machine is imported, their life-cycle (including creation of snapshots) can be controlled through OpenNebula. The following operations *cannot* be performed on an imported VM:

- Recover –recreate
- Undeploy (and Undeploy –hard)
- Migrate (and Migrate –live)
- Stop

Once a Wild VM is imported, OpenNebula will reconfigure the vCenter VM so VNC connections can be established once the VM is monitored.

Also, network management operations are present like the ability to attach/detach network interfaces, as well as capacity (CPU and MEMORY) resizing operations and VNC connections if the ports are opened before hand.

After a VM has been imported, it can be removed from OpenNebula and imported again. OpenNebula sets information in the vCenter VM metadata that needs to be removed, which can be done with the onevcenter cleartags command:

- opennebula.vm.running
- opennebula.vm.id
- opennebula.disk.*

The following procedure is useful if the VM has been changed in vCenter and OpenNebula needs to “rescan” its disks and NICs:

- Use onevcenter cleartags on the VM that will be removed:

```
$ onevcenter cleartags <vmid>
```

vmid is the id of the VM whose attributes will be cleared.

- Un-register VM

```
$ onevm recover --delete-db <vmid>
```

- Re-import VM: on the next host's monitoring cycle you will find this VM under **Wilds** tab, and it can be safely imported.

6.2.7 Importing vCenter Networks

OpenNebula can create Virtual Network representations of existing vCenter networks (standard port groups and distributed port groups). OpenNebula can handle on top of these representations three types of Address Ranges: Ethernet, IPv4 and IPv6. This networking information can be passed to the VMs through the contextualization process.

When you import a vCenter port group or distributed port group, OpenNebula will create an OpenNebula Virtual Network that represents that vCenter network.

The import tool (either the `onevcenter` tool or Sunstone) gives you information about the found networks on each datacenter:

- The name of the network
- The type of network (Standard Port Group or Distributed Port Group)
- The name of the vCenter cluster where the port group is used and the ID of the OpenNebula host referenced to the proper vCenter cluster.

If there are no OpenNebula Cluster's ID it means that you haven't imported any vCenter cluster that uses this port group so to import properly the network you should have imported the vcenter cluster first.

Note: Multicluseter networks are supported by OpenNebula, Port Groups and Distributed Port Groups spanning across than 1 vCenter cluster can be properly imported. OpenNebula will show up the related vCenter clusters and at least 1 should be imported before proceeding with the network import process. Even if it is possible to import a multicluseter network having only 1 vCenter cluster imported, it is best to import all vCenter clusters related to the network into OpenNebula first (arranging them into OpenNebula clusters).

A vCenter network name is unique inside a datacenter, so it is possible that two networks can be found with the same name in different datacenters and/or vCenter instances. When a network is imported, OpenNebula checks its existing network pool and generates a name that avoids collisions if needed. This name can be changed once the virtual network has been imported. The following screenshot shows an example:



VM Network

Warning: You need to have already imported the vCenter cluster in order to import any vnet. Otherwise OpenNebula will complain that you need to import the associated vcenter cluster (see the previous point).

Import networks with `onevcenter`

The import tool will discover port groups in each datacenter and will show the name of the port group, the port group type (Port Group or Distributed Port Group), the cluster that uses that port group and the OpenNebula cluster ID which this virtual network will be added to.

You will notice that the cluster name have color, this can mean two things:

In case that the network had more than 1 vCenter cluster associated, the list command will show a list of the OpenNebula clusters.

Here's an example showing how a standard port group or distributed port group is imported using the command-line interface:

Like always we need first to get the list of the importable objects:

```
$ onevcenter list -o networks -h 0

# vCenter: vcenter.Server

  IMID  REF          NAME          CLUSTERS
  0    network-12     VM Network   [100, 102]
  1    network-12245  testing00    [100, 102]
  2    network-12247  testing03    [102]
  3    network-12248  testing02    [102]
  4    network-12246  testing01    [100, 102]
```

Note: It is possible to get networks with CLUSTERS column set to -1, this means that there are vCenter clusters related to the network that you don't have already imported depending on how many -1 you are seeing, look at the previous note above.

With this information, we now want to import 'Testing0*' networks (it's common to import more than one network). Easily with the list command we realize that testing networks are included in IMIDs 1 to 4.

```
$ onevcenter import 1..4 -o networks -h 0
```

or

```
$ onevcenter import "network-12245, network-12247, network-12246, network-12248" -o_
networks -h 0
```

Even if the second option (above) is too long it's still very useful when you want to import a couple of not sequential nets. After this you'll be asked several questions and different actions will be taken depending on your answers.

If you want to import the network and the vnet has vlan id it will show to you in first place. Next step is to assign an Address Range. You can know more about address ranges in the Managing Address Ranges section.

First you have to specify the size of the address pool:

```
How many VMs are you planning to fit into this network [255] ?
```

Next you have to specify the type of address pool:

```
What type of Virtual Network do you want to create (IPv[4], IPv[6], [E]thernet) ?
```

If you choose an Ethernet pool, you can choose the first mac address in the pool although it's optional:

```
Please input the first MAC in the range [Enter for default]:
```

If you choose an IPv4 address pool, you'll have to specify the initial IP address and the first mac address in the pool (optional):

```
Please input the first IP in the range: 10.0.0.0
Please input the first MAC in the range [Enter for default]:
```

If you choose an IPv6 address pool, you'll have to specify the first mac address in the pool (optional) and if you want to use SLAAC:

Please input the first MAC in the range [Enter **for** default]:
 Do you want to use SLAAC Stateless Address Autoconfiguration? ([y]/n)

For SLAAC autoconfiguration you'll have to specify the GLOBAL PREFIX and the ULA_PREFIX or use the defaults.

Please input the GLOBAL PREFIX [Enter **for** default]:
 Please input the ULA PREFIX [Enter **for** default]:

If you don't want to use SLAAC autoconfiguration you'll have to specify an IPv6 address and the prefix length.

Please input the IPv6 address (cannot be empty):
 Please input the Prefix length (cannot be empty):

Finally if the network was created successfully you'll get a message with the name of the network (generated automatically by OpenNebula as described earlier) and the numeric ID.

OpenNebula virtual network TestPG - Cluster [vcenter.vcenter3 - Datacenter] b26ffced07734 with ID 148 created with size 255!

Import networks with Sunstone

In Sunstone the process is similar, click on Virtual Networks under the Network menu entry and then click on the Import button, a new window will be opened.

In the new window, choose a cluster to authenticate you into this vCenter instance and click on **Get Networks**.

ID	Name	Cluster	RVMs	Allocated CPU	Allocated MEM	Status
4	Cluster2	303	0	0/1000 (0%)	OKB/31.8GB (0%)	ON
3	Cluster	102	0	0/1000 (0%)	OKB/31.8GB (0%)	ON

When you click on the Get Networks, you'll get a list of port groups. You'll get the name of the port group, its type, the cluster, the location of the cluster and the IDs of an existing OpenNebula cluster which this virtual network will be assigned to. If OpenNebula Clusters ID is -1 that means that the import tool could not find an OpenNebula cluster where the datastore can be grouped and you may have to assign it by hand later or you may cancel the datastore import tool action and try to import the vCenter clusters before.

vCenter Networks: vcenter\vccenter65-1

Select all 10 Networks | Toggle advanced sections

Network

- testing_multicloud - Distributed Port Group
- DPortGroup - Distributed Port Group
- testing_singlecloud - Distributed Port Group
- test_pg_1531175000 - Port Group
- test_pg_1531168349 - Port Group
- VM Network - Port Group
- testing00 - Port Group
- testing01 - Port Group
- testing03 - Port Group
- testing02 - Port Group

Showing 1 to 10 of 10 entries

Before importing a network, you can click on the down arrow next to the network's name and specify the type of address pool you want to configure:

- eth for an Ethernet address range pool.
- ipv4 for an IPv4 address range pool.
- ipv6 for an IPv6 address range pool with SLAAC.
- ipv6_static for an IPv6 address range pool without SLAAC (it requires an IPv6 address and a prefix length).

VM Network - Port Group

Size	Type	MAC
255	eth	Optional

Cluster(s) to import

Cluster

Unimported Cluster(s)

When you import a network, the default address range is a 255 MAC addresses pool.

Finally click on the Import button, the ID of the virtual network that has been created will be displayed:

TestPG-10 - Port Group - Cluster: Cluster - Location: / - OpenNebula Cluster ID: 128

Virtual Network created successfully. ID: 141

Warning: If OpenNebula does not find new networks, check that you have previously imported the vCenter clusters that are using those port groups.

6.2.8 Importing vCenter Images

OpenNebula can create Image representations of vCenter VMDK and ISO files that are present in vCenter datastores.

A VMDK or ISO file may have the same name in different locations inside the datastore. The import tools will provide you the following information for each found file:

- The path inside the datastore.
- The size of the VMDK file. This will be the capacity size of the VMDk file as it was seen from a Virtual Machine perspective. For example, a VMDK file may be only a few KBs in size as it may have been thin provisioned, however the size that would report a Virtual Machine, if that file was attached to the VM, would be different and hence the capacity is displayed if it's available otherwise it will display the file's size.
- The type of the file: VmDiskFileInfo or IsoImageFileInfo.

When you import an image, OpenNebula generates a name that avoids collisions, that name contains the image name and, if there was another image with that name, a suffix. That name can be changed once the image has been imported to a more human-friendly name. This is sample name:

one-11-corelinux7_x86_64-11_2

The import tools will look for files that haven't been previously imported, checking if there's a file with the same PATH and DATASTORE_ID attributes.

Import images with onevcenter

The **onevcenter** tool and the Sunstone interface can be used to import this kind of files.

The onevcenter tool needs that an OpenNebula's IMAGE datastore name is specified as an argument. OpenNebula will browse the datastores and look for VMDK and ISO files. This means that it's mandatory to have the proper vCenter image datastore imported into OpenNebula, we can pass on this information through onevcenter tool with -d option so be sure to check this before the import image operation:

This is an easy way for check available vcenter datastores:

```
onedatastore list | grep -E 'img.*vcenter'

100 datastore2(IM) 924G 100% 102 1 img vcenter vcenter on
102 datastore1(IM) 924G 88% - 0 img vcenter vcenter on
106 nfs(IMG) 4.5T 39% 100,102 24 img vcenter vcenter on
```

Here's an example showing how a VMDK file can be imported using the command-line interface. In this case we are going to use datastore1 (102) and host 0:


```
onevcenter list -o images -h 0 -d 106
# vCenter: vcenter.vcenter65-1

IMID REF PATH
0 one-21 one_223304/21/one-21.vmdk
1 Core-current.iso.iso one_223304/22/Core-current.iso.iso
```

Once the image has been imported, it will report the OpenNebula image ID.

Import images with Sunstone

Images can also be imported from Sunstone. Click on Images under the Storage menu entry and click on the Import button.



In the new window, choose a cluster to authenticate you into this vCenter instance and click on **Get Images**.

OpenNebula will search for VMDK and ISO files that haven't been imported yet.

Select the images you want to import and click on the Import button. The ID of the imported images will be reported.

Note: When an image is created using the import tool, the VCENTER_IMPORTED attribute is set to YES automatically. This attribute prevents OpenNebula to delete the file from the vCenter datastore when the image is deleted from OpenNebula, so it can be used to prevent a virtual hard disk to be removed accidentally from a vCenter template. This default behavior can be changed in `/var/lib/one/etc/remotes/vmm/vcenter/vcenterc` by setting `DELETE_IMAGES` to Yes.

6.2.9 Migrate vCenter Virtual Machines with OpenNebula

vCenter Driver allows migration of VMs between different vCenter clusters (ie, OpenNebula hosts) and/or different datastores. Depending on the type of migration (cold, the VM is powered off, or saved; or live, the VM is migrated while running), or the target (cluster and/or datastore), several requirements needs to be met in order to migrate the machine.

Migrating a VM Between vCenter Clusters (OpenNebula Hosts)

Requirements (both live and cold migrations)

- Every Network attached to the selected VMs need to exists in both vCenter clusters and OpenNebula clusters
- Every Datastore that is used by the VM need to exist in both vCenter clusters and OpenNebula clusters
- Target OpenNebula host can specify a `ESX_MIGRATION_LIST` attribute:
 - If not specified, target ESX host is not explicitly declared and migration may fail
 - If set to an empty string (""), OpenNebula will randomly chose a target ESX from all the ESXs that belong to the vCenter target cluster

- If set to a space-separated list of ESX hostnames (that need to belong to the vCenter target cluster), OpenNebula will randomly choose a target ESX from the list

Note: A good place to check if the VM meets the OpenNebula requirements is to peek into the ‘AUTOMATIC_REQUIREMENTS’ attribute of the Virtual Machine (this can be reviewed in the Template info tab) and check if it includes the target OpenNebula clusters (remember, a cluster in OpenNebula is a collection of hosts, virtual networks and datastores, a cluster in vCenter is represented as a host in OpenNebula).

Requirements (only live migrations)

- vMotion interface enabled in both vCenter clusters (otherwise the driver will warn about compatibility issues)
- OpenNebula live migration only works for running VMs so be sure to check the state before

Usage (CLI)

Cold Migration

```
$ onevm migrate "<VM name>" <destination host id>
```

Live Migration

```
$ onevm migrate --live "<VM name>" <destination host id>
```

Migrating a VM Between Datastores

On a VM migration, target datastore can be changed. Disks belonging to the VM will be migrated to the target datastore. This is useful for rebalancing resources usage among datastores.

Requirements (both cold and live migrations)

- Every Datastore that is used by the VM needs to exist in both vCenter clusters and OpenNebula clusters

Usage (CLI)

Cold Migration

```
$ onevm migrate "<VM name>" <destination host id> <destination datastore id>
```

Live Migration

```
$ onevm migrate --live "<VM name>" <destination host id> <destination datastore id>
```

6.2.10 vCenter Hooks

OpenNebula has two hooks to manage networks in vCenter and [NSX](#).

Hook Name	Hook Description
vcenter_net_create	Allows you to create / import vCenter and NSX networks
vcenter_net_delete	Allows you to delete vCenter and NSX networks

These hooks should be created automatically when you add a vCenter cluster. If accidentally deleted, they can be created again manually.

Go to [Create vCenter Hooks](#) and follow the steps to create a new hook.

Note: Detailed information about how hooks work is available here.

List vCenter Hooks

Type the next command to list registered hooks:

```
$ onehook list
```

The output of the command should be something like this:

ID	NAME	TYPE
1	vcenter_net_delete	api
0	vcenter_net_create	api

Create vCenter Hooks

The following command can be used to create a new hook:

```
$ onehook create <template_file>
```

where template file is the name of the file that contains the hook template information.

The hook template for network creation is:

```
NAME = vcenter_net_create
TYPE = api
COMMAND = vcenter/create_vcenter_net.rb
CALL = "one.vn.allocate"
ARGUMENTS = "$API"
ARGUMENTS_STDIN = yes
```

The latest version <https://raw.githubusercontent.com/OpenNebula/one/master/share/hooks/vcenter/templates/create_vcenter_net.tpl>__

The hook template for network deletion is:

```
NAME = vcenter_net_delete
TYPE = api
COMMAND = vcenter/delete_vcenter_net.rb
CALL = "one.vn.delete"
ARGUMENTS = "$API"
ARGUMENTS_STDIN = yes
```

The latest version of the hook delete template can be found [here](#)

Delete vCenter Hooks

A hook can be deleted if its ID is known. The ID can be retrieved using onehook list, and then deleted using the following command.

```
$ onehook delete <hook_id>
```

6.2.11 Driver tuning

Drivers can be easily customized please refer to vCenter Driver Section in the Integration Guide.

Some aspects of the driver behavior can be configured on `/var/lib/one/remotes/etc/vmm/vcenter/vcenterrc`:

- **delete_images**: Allows OpenNebula to delete imported vCenter images. Default: **no**.
- **vm_poweron_wait_default**: Timeout for deploy action. Default: **300**.
- **debug_information**: Provides more verbose logs. Default: **false**.
- **retries**: Some driver actions support a retry if a failure occurs. This parameter will set the amount of retries. Default: **3**.
- **retry_interval**: Amount of time to wait between retry attempts (seconds). Default: **1**.

6.3 vCenter Datastores

vCenter datastores hosts VMDK files and other file types so VMs and templates can use them, and these datastores can be represented in OpenNebula as both an Images datastore and a System datastore:

- Images Datastore. Stores the images repository. VMDK files are represented as OpenNebula images stored in this datastore.
- System Datastore. Holds disk for running virtual machines, copied or cloned from the Images Datastore.

For example, if we have a vcenter datastore called nfs, when we import the vCenter datastore into OpenNebula, two OpenNebula datastores will be created as an Images datastore and as a System datastore pointing to the same vCenter datastores:

```
* Datastore found:
  - Name      : nfs
  - Datacenter: Datacenter
  - Total MB  : 4691989
  - Free MB   : 1564950
  - Import name: nfs [vcenter.vcenter5-devel - Datacenter]
Import this datastore [y/n]? y

NOTE: For each vCenter datastore a SYSTEM and IMAGE datastore
will be created in OpenNebula except for a StorageDRS which is
represented as a SYSTEM datastore only.

OpenNebula datastore 315 created!
OpenNebula datastore 316 created!


```

ID	NAME	SIZE	AVAIL	CLUSTERS	IMAGES	TYPE	DS	TM	STAT
313	LocalDatastor	225.3G	17%	0,120	0	img	vcenter	vcenter	on
314	LocalDatastor	225.3G	17%	0,120	0	svs	-	vcenter	on
315	nfs [vcenter.	4.5T	33%	0,120	0	img	vcenter	vcenter	on
316	nfs [vcenter.	4.5T	33%	0,120	0	sys	-	vcenter	on

Important: If the vCenter instance features a read only datastore, please be aware that you should disable the SYSTEM representation of the datastore after importing it to avoid OpenNebula trying to deploy VMs in it.

6.3.1 Images and disks

When the vCenter hypervisor is used we have three OpenNebula image types:

- OS: A bootable disk Image. Every VM template must define one DISK referring to an Image of this type.
- CDROM: These Images are read-only data.
- DATABLOCK: A datablock Image is a storage for data. These Images can be created from previous existing data (e.g uploading a VMDK file), or as an empty drive.

OpenNebula images can be also classified in **persistent** and **non-persistent** images:

- Non-persistent images. These images are used by at least one VM. It can still be used by other VMs. When a new VM using a non-persistent image is deployed a copy of the VMDK file is created.
- Persistent images. A persistent image can be used only by a VM. It cannot be used by new VMs. The original file is used, no copies are created.

Disks attached to a VM will be backed by a non-persistent or persistent image although volatile disks are also supported. Volatile disks are created on-the-fly on the target hosts and they are disposed when the VM is shutdown.

6.3.2 Limitations

- When a vCenter template or wild VM is imported into OpenNebula, the virtual disks are imported, and images are created in OpenNebula representing those virtual disks. Although these images represent files that already exist in the datastores, OpenNebula accounts the size of those imported images as if they were new created files and therefore the datastore capacity is decreased even though no real space in the vCenter datastore is being used by the OpenNebula images. You should understand this limitation if for example an image cannot be imported as OpenNebula reports that no more space is left or if you're using disk quotas.
- No support for disk snapshots in the vCenter datastore.
- Image names and paths cannot contain spaces or non ASCII characters.

6.3.3 The vCenter Transfer Manager

OpenNebula's vCenter Transfer Manager driver deals with disk images in the following way:

- New disk images created by OpenNebula are placed in an Images datastore. They can be created as persistent or non-persistent images.
- Persistent images are used by vCenter VMs from the datastore where the persistent images were created.
- Non-persistent images are copied from the Images datastore where they were created to a System datastore chosen by OpenNebula's scheduler.
- Volatile images are created in a System datastore chosen by the scheduler and deleted from that datastore once it's no longer needed (e.g disk detach or VM's terminate action).
- Creation of empty datablocks and VMDK image cloning are supported, as well as image deletion.

The scheduler chooses the datastore according to the configuration in the /etc/one/sched.conf as explained in the Operation's guide:

- By default it tries to optimize storage usage by selecting the datastore with less free space.
- It can optimize I/O by distributing the VMs across available datastores.

The vCenter datastore in OpenNebula is tied to a vCenter instance in the sense that all operations to be performed in the datastore are going to be performed through the vCenter instance, using the credentials defined on that instance.

vCenter datastores can be represented in OpenNebula to achieve the following VM operations:

- *Upload VMDK files*
- *Upload ISO files*
- *Create empty datablocks*
- Clone VMDKs images
- Delete VMDK images

OpenNebula Clusters

A Cluster is a group of Hosts and clusters can have associated Datastores and Virtual Networks. When a vCenter cluster is imported, the import tool assigns automatically a cluster to the OpenNebula host representing the vCenter cluster.

Important: When a vCenter datastore is imported into OpenNebula, OpenNebula tries to add the datastores to an existing OpenNebula cluster. If you haven't previously imported a vCenter cluster that uses that datastore, the automatic assignment won't have found a suitable OpenNebula cluster and hence the scheduler won't know which are the right datastores that can be used when a VM is deployed. In this case you should add the datastores to the cluster where the OpenNebula host (representing the vCenter Cluster) is found as explained in the Add Resources to Clusters section.

File location used by the Transfer Manager

VMDK files or ISO files are placed and named into a vcenter datastore, according to these rules:

- Persistent images. These images are placed following this pattern: IMAGE_DIR/IMAGE_ID/one-IMAGE_ID.vmdk, e.g: one/258/one-258.vmdk. IMAGE_DIR is by default the directory **one** but a different directory can be used thanks to the VCENTER_DS_IMAGE_DIR attribute.
- Non-persistent images. These images are placed following this pattern: IMAGE_DIR/IMAGE_ID/one-IMAGE_ID.vmdk, e.g: one/259/one-259.vmdk. IMAGE_DIR is by default the directory **one** but a different directory can be used thanks to the VCENTER_DS_IMAGE_DIR attribute.
- Non-persistent images used by a Virtual Machine. The copy of a non-persistent image follows this pattern: IMAGE_DIR/IMAGE_ID/one-VMID-IMAGE_ID-DISK_NUMBER.vmdk where VMID is replaced with the VM numeric identifier, IMAGE_ID would be the identifier of the original image and DISK_NUMBER is replaced with the position of the disk inside the VM.
- Volatile disks attached to a VM. These images are placed following this pattern: VOLATILE_DIR/one-VMID-DISK_NUMBER.vmdk, e.g one-volatile/285/one-285-2.vmdk. VOLATILE_DIR is by default the one-volatile directory but a different directory can be used thanks to the VCENTER_DS_VOLATILE_DIR attribute.

In the following example we can see that the file associated to the Image with OpenNebula's ID 8 contains the VMDK file using the placement logic explained above.



Important: OpenNebula is committed to not leaving unneeded folders and files on your datastores, however note that in vCenter 6.5 we have detected a bug in its API that currently prevents OpenNebula to delete empty directories created by OpenNebula. Hence you may find empty folders in your datastores inside locations mentioned earlier that you may have to remove by hand if those folders bothers you somehow.

6.3.4 Requirements

In order to use the vCenter datastore, the following requirements need to be met:

- All the ESX servers controlled by vCenter need to mount the same VMFS datastore with the same name.
- The ESX servers need to be part of the Cluster controlled by OpenNebula
- Before you can create images in an IMAGE datastore check that the datastore has been monitored and that it reports its size and usage information. You can't create images in a datastore until it's monitored.

6.3.5 Upload VMDK files

You can upload VMDK files that can be attached to Virtual Machines as Virtual Hard Disks.

The file containing the VMDK can be uploaded in two ways:

- Adding the file from your web browser or
- Specify the path using an URL.

The file to be uploaded can be:

- A standalone VMDK file. This file can also be compressed with gzip or bzip2.
- Flat files and a VMDK descriptor in an archived tar file. Both files must live in the first level of the archived tar file as folders and subfolders are not supported by OpenNebula inside the tar. The tar file can also be compressed with gzip or bzip2.

Using the CLI

You can use the `oneimage` CLI command. Here's an example where we want to upload a standalone vmdk file to the IMAGE datastore with ID 154.

We specify the vcenter driver, type, a name and a description. The type parameter can be OS (if you want to tell OpenNebula that the image contains an Operating System), DATABLOCK and CDROM. If you want to specify other options run `oneimage` without parameters and you'll have a list of the parameters and some examples.

```
$ oneimage create -d 153 --type OS --name test_standalone --path /tmp/tinycore-2.1-
 ↲x86.vmdk --driver vcenter --description "Upload test"
ID: 134
```

The command will return the image ID. While the image is being uploaded the Image status will be LOCKED. You can check later if the status has changed to READY or ERROR.

Using Sunstone

You have to select the IMAGE datastore where you want that file to be uploaded and specify if you want the image to be persistent or non-persistent when used by a Virtual Machine.

When you upload a VMDK file you can assign the image a type either Operating System Image or Generic Storage Datablock.

In the following example we're uploading a tar.gz file containing a flat file and vmdk descriptor, using our browser. OpenNebula will upload the file to a temporary location, untar and uncompress that file and upload its contents to the vCenter datastore you've chosen.

The screenshot shows the 'Create Image' interface in Sunstone. The 'Name' field contains 'test_upload_vmdk'. The 'Type' dropdown is set to 'Generic storage datablock'. The 'Datastore' dropdown shows '153:nfs[vcenter:vcenter65-2-Datacenter][IMG]'. A note in the 'Description' field says 'Trying to upload a VMDK tared and gzipped containing a flat file and a vmdk file.' Below the form, there's a file selection area with 'Test.tar.gz' selected. At the bottom, there are radio buttons for 'Path in OpenNebula server', 'Upload' (which is selected), and 'Empty disk image'.

Warning: If your Sunstone server is not located behind an Apache or NGINX server with Passenger, you may receive an error with the message **Cannot contact server. Is it running or reachable?** if the upload operation takes more than 30 seconds to finish. In that case you may refresh the Images window and you'll see that the new image is in the LOCKED state but the upload operation is still on course, so check it again later to see if the Image is in the READY state or ERROR.

Click on the Create button to start the file uploading process.

While the image is uploaded the status will be LOCKED, you can refresh the Images tab later to check if the status is READY to use or ERROR.

132	test_upload_vmdk	onadmin	onadmin	nfs[vcenter:vcenter65-2-Datacenter][IMG]	DATABLOCK	READY	0
-----	------------------	---------	---------	--	-----------	-------	---

6.3.6 Upload ISO files

You can upload ISO files that can be used as CDROM images that can be attached to Virtual Machines.

Note: CDROM images files can only be attached to a Virtual Machine when it's in the POWEROFF state as the ISO files is attached to the Virtual Machine as an IDE CD-ROM drive which is not a hot-pluggable devices.

The ISO file can be uploaded in two ways:

- Adding the file from your web browser or
- Specify the path using an URL.

Using the CLI

You can use the oneimage CLI command. Here's an example where we want to upload a standalone vmdk file to the IMAGE datastore with ID 154.

We specify the vcenter driver, type will be CDROM, a name and a description.

```
$ oneimage create -d 153 --name test_iso_file --type CDROM --path http://
˓→tinycorelinux.net/8.x/x86/release/Core-current.iso --driver vcenter --description
˓→"Upload ISO test"
ID: 135
```

The command will return the image ID. While the ISO image is being uploaded the Image status will be LOCKED. You can check later if the status has changed to READY or ERROR.

Using Sunstone

In the following example we're using an URL in Internet. OpenNebula will download the ISO file to a temporary file and then upload it to the vCenter datastore you've chosen.

Warning: If your Sunstone server is not located behind an Apache or NGINX server with Passenger, you may receive an error with the message **Cannot contact server. Is it running or reachable?** if the upload operation takes more than 30 seconds to finish. In that case you may refresh the Images window and you'll see that the new image is in the LOCKED state but the upload operation is still on course, so check it again later to see if the Image is in the READY state or ERROR.

Click on the Create button to start the file uploading process.

While the image is uploaded the status will be LOCKED, you can refresh the Images tab later to check if the status is READY to use or ERROR.

131	test_upload_cdrom	oneadmin	oneadmin	nfs [vcenter:vcenter65-2 · Datacenter] (IMG)	CDROM	READY	0
-----	-------------------	----------	----------	--	-------	-------	---

6.3.7 Create empty datablocks

You can easily create empty VMDK datablocks from OpenNebula.

In Sunstone you can follow these steps:

- Give the datablock a name. A description is optional.
- Select Generic storage datablock in the drop-down Type menu.
- Choose the IMAGE datastore where you want OpenNebula to create the empty datablock.
- Select Empty disk image.
- Specify the size in MB of the datablock.

- Select the disk type (Optional). You have a full list of disk types in the VCENTER_DISK_TYPE attribute description explained in the Configuration section.
- Select the bus adapter (Optional). You have a full list of controller types in the VCENTER_ADAPTER_TYPE attribute description explained in the Configuration section.

Finally click on Create.

While the VMDK file is created in the datastore the Image status will be LOCKED, you can refresh the Images tab later to check if the status is READY to use or ERROR.

Note: If you don't specify a disk type and/or bus adapter controller type the default values contained in the /etc/one/vcenter_driver.default file are applied. You have more information here.

6.3.8 Configuration

In order to create a OpenNebula vCenter datastore that represents a vCenter VMFS datastore, a new OpenNebula datastore needs to be created with the following attributes. The onevcenter import tool creates a datastore representation with the required attributes.

Attribute	Description
DS_MAD	Must be set to vcenter if TYPE is SYSTEM_DS
TM_MAD	Must be set vcenter
TYPE	Must be set to SYSTEM_DS or IMAGE_DS
VCENTER	Default adapter type used by virtual disks to plug inherited to VMs for the images in the datastore. It is inherited by images and can be overwritten if specified explicitly in the image. Possible values (careful with the case): lsiLogic, ide, busLogic. More information in the VMware documentation . Known as “Bus adapter controller” in Sunstone.
VCENTER	Type of DISK to be created when a DATABLOCK is requested. This value is inherited from the datastore to the image but can be explicitly overwritten. The type of disk has implications on performance and occupied space. Values (careful with the case): delta,eagerZeroedThick,flatMonolithic,preallocated,raw,rdm,rdmp,seSparse,sparse2Gb,sparseMonolithic,thick,thick2Gb,thi
VCENTER	More information in the VMware documentation . Known as “Disk Provisioning Type” in Sunstone.
VCENTER	Managed Object Reference of the vCenter datastore. Please visit the Managed Object Reference section to know more about these references.
VCENTER	Name of the vCenter datastore
VCENTER	Managed Object Reference of the vCenter datacenter. Please visit the Managed Object Reference section to know more about these references.
VCENTER	Name of the vCenter datacenter.
VCENTER	The vCenter instance ID. Please visit the Managed Object Reference section to know more about these references.
VCENTER	Hostname or IP of the vCenter host
VCENTER	(Optional) Specifies what folder under the root directory of the datastore will host persistent and non-persistent images e.g one
VCENTER	(Optional) Specifies what folder under the root directory of the datastore will host the volatile disks

All OpenNebula datastores are actively monitoring, and the scheduler will refuse to deploy a VM onto a vCenter datastore with insufficient free space.

6.3.9 Datastore clusters with Storage DRS


Thanks to OpenNebula’s scheduler, you can manage your datastores clusters with load distribution but you may already be using vCenter’s Storage DRS capabilities. Storage DRS allows you to manage the aggregated resources of a datastore cluster. If you’re using Storage DRS, OpenNebula can delegate the decision of selecting a datastore to the Storage DRS cluster (SDRS) but as this behavior interferes with OpenNebula’s scheduler and vSphere’s API impose some restrictions, there will be some limitations in StorageDRS support in OpenNebula.

When you import a SDRS cluster using onevcenter or Sunstone:

- The cluster will be imported as a SYSTEM datastore only. vSphere’s API does not provide a way to upload or create files directly into the SDRS cluster so it can’t be used as an IMAGE datastore.
- OpenNebula detects the datastores grouped by the SDRS cluster so you can still import those datastores as both IMAGE and SYSTEM datastores.
- Non-persistent images are not supported by a SDRS as vSphere’s API does not provide a way to create, copy or delete files to a SDRS cluster as a whole, however you can use persistent and volatile images with the VMs backed by your SDRS.
- Linked clones over SDRS are not supported by OpenNebula, so when a VM clone is created a full clone is performed.

In order to delegate the datastore selection to the SDRS cluster you must inform OpenNebula’s scheduler that you want to use specifically the SYSTEM datastore representing the storage cluster. You can edit a VM template and

add the following expression: ID=DATASTORE_ID to the attribute SCHED_DS_REQUIREMENTS, where DATASTORE_ID must be replaced with the numeric id assigned by OpenNebula to the datastore. Thanks to this attribute OpenNebula will always use this datastore when deploying a VM. There's an alternative if you don't want to use SCHED_DS_REQUIREMENTS if you have several SYSTEM datastores in the same OpenNebula cluster associated to the vCenter cluster, you can disable all SYSTEM datastores but the one that represents your StorageDRS cluster as the scheduler will not use disabled datastores.



6.3.10 Marketplace with vCenter Datastores

The vCenter datastores are compatible with OpenNebula HTTP and S3 marketplaces. It's necessary a generic VM Template. More information about OpenNebula marketplaces can be found [here](#).

6.3.11 Tuning and Extending

Drivers can be easily customized please refer to the specific guide for each datastore driver or to the Storage subsystem developer's guide.

However you may find the files you need to modify here:

- /var/lib/one/remotes/datastore/vcenter
- /var/lib/one/remotes/tm/vcenter

6.4 vCenter Networking Overview

Virtual Networks from vCenter can be represented using OpenNebula virtual networks, where a one-to-one relationship exists between an OpenNebula's virtual network and a vSphere's port group. When adding NICs in a VM template or when attaching a NIC (hot-plugging) to a running VM in OpenNebula, a network interface can be attached to an OpenNebula's Virtual Network.

OpenNebula can consume port groups or create port groups.

In vSphere's terminology, a port group can be seen as a template for creating virtual ports with particular sets of specifications such as VLAN tagging. The VM's network interfaces connect to vSphere's virtual switches through port groups. vSphere provides two types of port groups:

- Port Group (or Standard Port Group). The port group is connected to a vSphere Standard Switch.
- Distributed Port Group. The port group is connected to a vSphere Distributed Switch.

According to [VMWare's vSphere Networking Guide](#) we have two virtual switches types:

- vSphere Standard Switch. It works much like a physical Ethernet switch. A vSphere standard switch can be connected to physical switches by using physical Ethernet adapters, also referred to as uplink adapters, to join virtual networks with physical networks. You create and configure the virtual standard switch on each ESXi host where you want that virtual switch to be available.
- vSphere Distributed Switch. It acts as a single switch across all associated hosts in a datacenter to provide centralized provisioning, administration, and monitoring of virtual networks. You configure a vSphere distributed switch on the vCenter Server system and the configuration is populated across all hosts that are associated with the switch. This lets virtual machines to maintain consistent network configuration as they migrate across multiple hosts.

Note: The vSphere Distributed Switch is only available for VMWare's vSphere Enterprise Plus licence.

If you want to associate OpenNebula's virtual networks to vSphere's port groups:

- You can create the port groups using vSphere's Web Client and then consume them using the import tools or,
- You can create port groups directly from OpenNebula using a virtual network definition, adding the attribute `VN_MAD=vcenter` to the network template and letting OpenNebula create the network elements for you.

6.4.1 Consuming existing vCenter port groups

Existing vCenter networks can be represented using OpenNebula Virtual Networks, taking into account that the `BRIDGE` attribute of the Virtual Network needs to match the name of the Network (port group) defined in vCenter.

OpenNebula supports both "Port Groups" and "Distributed Port Groups", and as such can **create or consume** any vCenter defined network resource.

Networks can be created using vSphere's web client, with any specific configuration like for instance VLANs. OpenNebula will use these networks with the defined characteristics representing them as Virtual Networks. OpenNebula additionally can handle on top of these networks three types of Address Ranges: Ethernet, IPv4 and IPv6.

vCenter VM Templates can define their own NICs, and OpenNebula will manage them and its information (IP, MAC, etc) is known by OpenNebula. Any NIC present in the OpenNebula VM Template, or added through the `attach_nic` operation, will be handled by OpenNebula, and as such it is subject to be detached.

OpenNebula Virtual Networks which consume existing port groups will have the attribute `VN_MAD=dummy`.

You can easily consume vCenter networks using the import tools as explained in the *Importing vCenter Networks* section.

6.4.2 Creating Port Groups from OpenNebula

OpenNebula can create a vCenter network from a Virtual Network template if the vCenter network driver is used (thanks to the attribute `VN_MAD=vcenter`).

This is the workflow when OpenNebula needs to create a vCenter network:

1. Enable the VNET hooks in OpenNebula's oned configuration file.
2. Create a new OpenNebula Virtual Network template. Add the required attributes to the template including the OpenNebula's Host ID which represents the vCenter cluster where the network elements will be created.
3. When the Virtual Network is created, a hook will create the network elements required on each ESX host that are members of the specified vCenter cluster.

4. The Virtual Network will be automatically assigned to the OpenNebula cluster which includes the vCenter cluster represented as an OpenNebula host.
5. The hooks works asynchronously so you may have to refresh the Virtual Network information until you find the VCENTER_NET_STATE attribute. If it completes the actions successfully that attribute will be set to READY and hence you can use it from VMs and templates. If the hook fails VCENTER_NET_STATE will be set to ERROR and the VCENTER_NET_ERROR attribute will offer more information.

6.4.3 Hooks information

As soon as the first vCenter cluster is created, two hooks are registered in OpenNebula to deal with network creation and deletion.

- vcenter_net_create
- vcenter_net_delete

These hooks are the scripts responsible of creating the vCenter network elements and deleting them when the OpenNebula Virtual Network template is deleted.

The creation hook performs the following actions for each ESX host found in the cluster assigned to the template if a standard port group has been chosen:

- If the port group does not exist, it will create it.
- If the port group or switch name exist, **they won't be updated** ignoring new attributes to protect you from unexpected changes that may break your connectivity.

The creation hook performs the following actions if a distributed port group has been chosen:

- OpenNebula creates the distributed switch if it doesn't exist. If the switch exists, it's not updated ignoring any attribute you've set.
- OpenNebula creates the distributed port group if it doesn't exist in the datacenter associated with the vCenter cluster. If the distributed port group already exists **it won't be updated** to protect you from unexpected changes.
- For each ESX host found in the cluster assigned to the template, it adds the ESX host to the distributed switch.

Creation hook is asynchronous which means that you'll have to check if the VCENTER_NET_STATE attribute has been set. Once the hook finishes you'll find the VCENTER_NET_STATE either with the READY value or the ERROR value. If an error was found you can check what was wrong.

Here's a screenshot once the hook has finished and the network is ready:

vCenter information	
VCENTER_INSTANCE_ID	8C3875CD-275B-4718-BFE4-99739AE06F78
VCENTER_NET_ERROR	
VCENTER_NET_REF	network-1131
VCENTER_NET_STATE	READY
VCENTER_ONE_HOST_ID	66
VCENTER_PORTGROUP_TYPE	Port Group
VCENTER_SWITCH_NAME	[REDACTED]

The removal hook performs the following actions:

- OpenNebula contacts with the vCenter server.
- For each ESX host found in the vCenter cluster assigned to the template, it tries to remove both the port group and the switch. If the switch has no more port groups left then the switch will be removed too.

In this case the hook is also asynchronous. If you want to know if it succeeded or failed you can run the following command:

```
grep EXECUTE /var/log/one/oned.log | grep vcenter_net_delete
```

If the script failed, you can check the lines before EXECUTE FAILURE in the /var/log/one/oned.log to get more information on the failure. If the removal hook fails you may have to check your vCenter server and delete those resources that could not be deleted automatically.

Warning: If a port group or switch is in use e.g a VM is running and have a NIC attached to that port group the remove operation will fail so please ensure that you have no VMs or templates using that port group before trying to remove the Virtual Network representation.

6.4.4 vCenter Network attributes

You can easily create a Virtual Network definition from Sunstone but you can also create a template and apply it with the `onevnet` command. Here's the table with the attributes that must be added inside a TEMPLATE section:

Attribute	Type	Mandatory	Description
VN_MAC	string	Yes	Must be set to vcenter
BRIDGE	string	Yes	It's the port group name.
PHYDEVICES	string	No	If you want to assign uplinks to your switch you can specify the names of the physical network interface cards of your ESXi hosts that will be used. You can use several physical NIC names using a comma between them e.g vmnic0,vmnic1. Note that two switches cannot share the same physical nics and that you must be sure that the same physical interface name exists and it's available for every ESX host in the cluster. This attribute will be ignored if the switch already exists.
VCENTER	string	YESGROUP	There are two possible values Port Group and Distributed Port Group. Port Group means a Standard Port Group
VCENTERHOST	in-integer	Yes	The OpenNebula host id which represents the vCenter cluster where the nework will be created.
VCENTERNAME	string	YES	The name of the virtual switch where the port group will be created. If the vcenter switch already exists it won't update it to avoid accidental connectivity issues
VCENTERPORTS	in-integer	NO	The number of ports assigned to a virtual standard switch or the number of uplink ports assigned to the Uplink port group in a Distributed Virtual Switch. This attribute will be ignored if the switch already exists.
MTU	integer	No	The maximum transmission unit setting for the virtual switch. This attribute will be ignored if the switch already exists.
VLAN_ID	integer	Yes (unless AUTOMATIC_VLAN_ID)	The VLAN ID, will be generated if not defined and AUTOMATIC_VLAN_ID is set to YES (unless VLAN_ID)
AUTOMATIC_VLAN_ID	boolean	Yes (unless VLAN_ID)	Mandatory and must be set to YES if VLAN_ID hasn't been defined so OpenNebula created a VLAN ID automatically
VCENTERHOOK	hook	NO	This attribute is a protection mechanism to prevent accidental deletion with vcenter_vnet_delete hook

6.4.5 Settings applied to virtual switches and port groups created by OpenNebula

OpenNebula uses the following values when creating virtual switches and port groups in vCenter according to what the vSphere's Web Client uses in the same operations:

- VLAN ID is set to 0, which means that no VLANs are used.
- MTU value is set to 1500.

Standard port groups created by OpenNebula have the following settings:

- Number of ports is set to Elastic. According to VMWare's documentation, the Elastic mode is used to ensure efficient use of resources on ESXi hosts where the ports of virtual switches are dynamically scaled up and down. In any case, the default port number for standard switches is 128.
- Security - Promiscuous mode is set to Reject, which means that the virtual network adapter only receives frames that are meant for it.
- Security - MAC Address Changes is set to Accept, so the ESXi host accepts requests to change the effective MAC address to other than the initial MAC address.
- Security - Forged transmits is set to Accept, which means that the ESXi host does not compare source and effective MAC addresses.
- Traffic Shaping policies to control the bandwidth and burst size on a port group are disabled. You can still set QoS for each NIC in the template.
- Physical NICs. The physical NICs used as uplinks are bridged in a bond bridge with teaming capabilities.

Distributed port groups created by OpenNebula have the following settings:

- Number of ports is set to Elastic. According to VMWare's documentation, the Elastic mode is used to ensure efficient use of resources on ESXi hosts where the ports of virtual switches are dynamically scaled up and down. The default port number for distributed switches is 8.
- Static binding. When you connect a virtual machine to a distributed port group, a port is immediately assigned and reserved for it, guaranteeing connectivity at all times. The port is disconnected only when the virtual machine is removed from the port group.
- Auto expand is enabled. When the port group is about to run out of ports, the port group is expanded automatically by a small predefined margin.
- Early Bindind is enabled. A free DistributedVirtualPort will be selected to assign to a Virtual Machine when the Virtual Machine is reconfigured to connect to the port group.

6.4.6 OpenNebula Virtual Network template (Sunstone)

In this section we will explain how a Virtual Network definition can be created using the Sunstone user interface, and we will introduce the available attributes for the vcenter network driver.

The first step requires you to introduce the virtual network's name:


Create Virtual Network

General Conf Addresses Security QoS Context

Name: vcenter_network_test

Description:

In the Conf tab, select vCenter from the Network Mode menu, so the vcenter network driver is used (the VN_MAD=vcenter attribute will be added to OpenNebula's template). The Bridge name will be the name of the port group, and by default it's the name of the Virtual Network but you can choose a different port group name.



Once you've selected the vCenter network mode, Sunstone will show several network attributes that can be defined.

vSphere standard switches or distributed switches with port groups. Security Groups are not applied.

VLAN ID	Physical device	MTU of the interface
Automatic VLAN ID		
Switch name	Number of ports	Port group type
		Port group
OpenNebula's Host ID		
Please select		

You have more information about these attributes in the [vCenter Network attributes](#) section, but we'll comment some of them:

OpenNebula Host's ID

In order to create a Virtual Network using the vcenter driver we must select which vCenter cluster, represented as an OpenNebula host, this virtual network will be associated to. OpenNebula will act on each of the ESX hosts which are members of the vCenter cluster.

Physical device

If you want to assign uplinks to your switch you can specify the names of the physical network interface cards of your ESXi hosts that will be used. You can use several physical NIC names using a comma between them e.g vmnic0,vmnic1. Note that you must check that two switches cannot share the same physical NIC and that you must be sure that the same physical interface name exists and it's available for every ESX host in the cluster.

Let's see an example. If you want to create a port group in a new virtual switch, we'll first check what physical adapters are free and unassigned in the hosts of my vCenter cluster. I've two hosts in my cluster:


In my first host, the vmnic1 adapter is free and is not assigned to any vSwitch:

Device	Actual Speed	Configured Speed	Switch	MAC Address
Intel Corporation 82576 Gigabit Network Connection				
vmnic0	1000 Mb	Auto negotiate	vSwitch0	78:e3:b5:11:ab:4a
vmnic1	1000 Mb	Auto negotiate	--	78:e3:b5:11:ab:4b

In my second host, the vmnic1, vmnic2 and vmnic3 interfaces are free:

Device	Actual Speed	Configured Speed	Switch	MAC Address
Intel Corporation 82571EB Gigabit Ethernet Controller				
vmnic2	Down	Auto negotiate	--	00:23:8b:ce:a8:7e
vmnic3	Down	Auto negotiate	--	00:23:8b:ce:a8:7f
Intel Corporation 80003ES2LAN Gigabit Ethernet Controller				
vmnic0	1000 Mb	Auto negotiate	vSwitch0	00:23:8b:ce:a8:7c
vmnic1	Down	Auto negotiate	--	00:23:8b:ce:a8:7d

So if I want to specify an uplink, the only adapter that I could use in both ESX hosts would be **vmnic1** and OpenNebula will create the switches and uplinks as needed:



Number of ports

This attribute is optional. With this attribute we can specify the number of ports that the virtual switch is configured to use. If you set a value here please make sure that you know and understand the [maximums supported by your vSphere platform](#).

VLAN ID

This attribute is optional. You can set a manual VLAN ID, force OpenNebula to generate an automatic VLAN ID or set that no VLANs are used. This value will be assigned to the `VLAN_ID` attribute.

Address Ranges

In order to create your Virtual Network you must also add an Address Range in the Addresses tab. Please visit the Virtual Network Definition section.

6.4.7 Limitations

OpenNebula won't sync ESX hosts. OpenNebula won't create or delete port groups or switches on ESX hosts that are added/removed after the Virtual Network was created. For example, if you're using vMotion and DPM and an ESX host is powered on, that ESX host won't have the switch and/or port group that was created by OpenNebula hence a VM cannot be migrated to that host.

Virtual Network Update is not supported. If you update a Virtual Network definition, OpenNebula won't update the attributes in existing port groups or switches so you should remove the virtual network and create a new one with the new attributes.

Security groups. Security Groups are not supported by the vSphere Switch mode.

Network alias. It is possible to use network interface alias with vCenter, however if you attach an alias when the vm is running the action will take action on the next reboot (OpenNebula deploy). If you do not want to reboot the machine you can manually execute the next command on the machine prompt:

```
$ /usr/sbin/one-contextd all reconfigure
```

Importing networks. OpenNebula won't import a network if it not belongs to any host. In the case of distributed port groups if DVS has no host attached to it.

6.4.8 Network monitoring

OpenNebula gathers network monitoring info for each VM. Real-time data is retrieved from vCenter thanks to the Performance Manager which collects data every 20 seconds and maintains it for one hour. Real-time samples are used so no changes have to be applied to vCenter's Statistics settings. Network metrics for transmitted and received traffic are provided as an average using KB/s unit.

The graphs provided by Sunstone are different from those found in vCenter under the Monitor -> Performance Tab when selecting Realtime in the Time Range drop-down menu or in the Advanced view selecting the Network View. The reason is that Sunstone uses polling time as time reference while vCenter uses sample time on their graphs, so an approximation to the real values aggregating vCenter's samples between polls is needed. As a result, upload and download peaks will be different in value and different peaks between polls won't be depicted. Sunstone's graphs will provide a useful information about networking behaviour which can be examined on vCenter later with greater detail.

6.5 NSX Setup

NSX is the Network and Security software from VMware that enables a virtual cloud network to connect and protect applications across data centers, multi-clouds, bare metal, and container infrastructures. VMware NSX Data Center delivers a complete L2-L7 networking and security virtualization platform — providing agility, automation, and dramatic cost savings that come with a software-only solution.

OpenNebula can manage NSX-V and NSX-T logical switches in the following ways:

- Creating new logical switches into existing Transport Zones.
- Importing logical switches from imported vCenter clusters.
- Deleting logical switches created or imported into OpenNebula.
- Attaching logical switches, created or imported, to VMs.
- Detaching logical switches, created or imported to VMs.

6.5.1 Requirements

NSX Manager

The NSX appliance must be deployed with only one IP Address. OpenNebula installation must be able to connect to NSX Manager with the needed credentials.

Controller nodes

At least one controller node must be deployed.

ESXi Hosts

All ESXi of the cluster must be prepared for NSX.

Transport Zone

At least one transport zone must be created.

Warning: Transport zone names can only contain alphanumeric characters (a-z, A-Z, 0-9) and underscores (_).

Logical Switches

It is not mandatory to have any logical switch before start using opennebula NSX-V integration, but is recommendable to test that logical switches are working properly, creating a logical switch from vCenter into a Transport Zone, and attaching it into two VMs to test that overlay network is working.

6.5.2 NSX Driver Limitations

- Cannot create/modify/delete Transport Zones
- All parameters are not available when creating Logical Switches
- Universal Logical Switches are not supported
- Only support one NSX Manager per vCenter Server
- The process of preparing a NSX cluster must be done from NSX Manager
- Imported networks work with vcenter id instead of nsx id
- Transport zone names can only contain alphanumeric characters and underscores

6.5.3 Adding NSX Manager into OpenNebula

This is a semi-automatic process. When vCenter is connected to a NSX Manager, OpenNebula in the next monitoring execution will detect it and a new tab called “NSX” will show in the UI allowing the configuration of the credentials (User and Password) needed to connect to NSX Manager. The same process is applied when importing a new vcenter cluster that is prepared to work with NSX-V or NSX-T.

This section details how to configure OpenNebula to start working with NSX, doing the complete process ranging from importing a vCenter Cluster to checking that OpenNebula gets NSX information correctly

Adding vCenter cluster into OpenNebula

The first step is to add a ESXi cluster to OpenNebula, this cluster must have all the requirements to work with NSX-V or NSX-T. You can add the cluster in two ways, as usual:

Import from Sunstone

The screenshot shows the 'Create Host' page in the OpenNebula Sunstone interface. The left sidebar has a 'Clusters' section under Infrastructure. The main form is for a 'VMWare vCenter' host. The 'vCenter' tab is active. The 'Hostname' field is set to 'vcenter.vcenter67-nsx2', 'User' is 'administrator@vsphere.local', and 'Password' is masked. The 'Import' button is highlighted with a cursor. Below the form, a message indicates 'Host created successfully, ID: 0'. The table below shows one cluster imported:

<input type="checkbox"/> Cluster	vCenter ref	Location
<input type="checkbox"/>	StandardCluster	/
<input checked="" type="checkbox"/>	NSXvCluster	/

Import from CLI:

```
$ onevcenter hosts --vcenter <vcenter_fqdn> --vuser <vcenter_user> --vpass <vcenter_
˓→password>
```

Check hooks

Once a vCenter cluster is imported into OpenNebula, two hooks are created:

- vcenter_net_create
- vcenter_net_delete

For more information about list, create and delete these vCenter hooks go to [vCenter Hooks](#).

Check NSX Manager autodiscovered attributes

After a vCenter cluster is imported and monitor cycle finalises, the NSX Manager registered for that cluster is detected. You can read that information going to:

Infrastructure > Hosts

And clicking on the desired OpenNebula Host, the following information is available under Attributes section

In particular the following attributes are retrieved:

- **NSX_MANAGER**: Containing the url for that NSX Manager
- **NSX_TYPE**: Indicating if it's NSX-V or NSX-T

Attributes

AVAILHOST	3	 
CPUSPEED	2100.0	 
CUSTOMIZATION		 
NAME	customLinux01	 
TYPE	Linux	 
HYPERSVISOR	vcenter	 
IM_MAD	vcenter	 
NSX_LABEL	NSX Manager	 
NSX_MANAGER	https://10.0.1.30:443	 
NSX_STATUS	Missing NSX_USER	 
NSX_TYPE	NSX-V	 
NSX_VERSION	6.4.5.13282012	 
STATUS	green	 
TOTALHOST	3	 
TOTAL_WILDS	17	 
VM_MAD	vcenter	 

- **NSX_VERSION**: Version of that NSX Manager
- **NSX_STATUS**: Describing the status of the last nsx manager check

You have a more detailed explanation of these parameters in the [NSX attributes section](#).

Setting NSX Manager Credentials

Once a vCenter cluster is imported as an OpenNebula Host, the next step is to introduce the NSX credentials. A new tab called “NSX” is showing now into the Host:

Infrastructure > Hosts

After clicking on the relevant host:

Information	Capacity
ID: 0	Allocated Memory: OKB / 96GB (0%)
Name: NSXvCluster	Allocated CPU: 0 / 1200 (0%)
Cluster: NSXvCluster	Real Memory: 16.6GB / 96GB (17%)
State: MONITORED	Real CPU: 366 / 1200 (31%)
IM MAD: vccenter	
VM MAD: vccenter	

Overcommitment	Update
CPU: 1200	1200
Memory: 96GB	96GB

vCenter information	
VCENTER_CCR_REF	domain-c40
VCENTER_DRS	true
VCENTER_DS_REF	datastore-29
VCENTER_DS_REF	datastore-39
VCENTER_DS_REF	datastore-35
VCENTER_DS_REF	datastore-42
VCENTER_HA	true
VCENTER_HOST	vccenter.vcenter67-nsx2
VCENTER_INSTANCE_ID	2f1a1d52-8ed5-4c89-899c-eb583a22088d
VCENTER_LAST_PERF_POLL	1567428618

Click on NSX tab and introduce NSX credentials:

And click on Submit, after which credentials are validated against NSX Manager.

- If the credentials are valid a message is shown and credentials are saved.
- If the credentials are invalid an error is shown

Now NSX credentials are saved in two new attributes:

- **NSX_USER:** NSX Manager user
- **NSX_PASSWORD:** NSX Manager Encrypted password

Remind that Transport Zones cannot be created from OpenNebula and it's a requirement having them created. However, adding Transport Zones in NSX Manager is supported, OpenNebula will detect them after the following monitor cycle.

Checking NSX Status

To check NSX status, proceed to:

Infrastructure > Hosts

And click on desired host and look into "Attributes" section

If everything works properly the next two attributes will show up:

- **NSX_STATUS = OK**
- **NSX_TRANSPORT_ZONES** = Containing the Transport zones available.

6.5.4 NSX non editable attributes

These attributes are autodiscovered and they cannot be modified manually.

Attributes

AVAILHOST	3	 
CPUSPEED	2100.0	 
CUSTOMIZATION		
NAME	customLinux01	 
TYPE	Linux	 
HYPERSVISOR	vcenter	 
IM_MAD	vcenter	 
NSX_LABEL	NSX Manager	 
NSX_MANAGER	https://10.0.1.30:443	 
NSX_PASSWORD	019WN+Ga8YIBwwLTnynbMg==	 
NSX_STATUS	Missing NSX_USER	 
NSX_TYPE	NSX-V	 
NSX_USER	admin	 
NSX_VERSION	6.4.5.13282012	 
STATUS	green	 
TOTALHOST	3	 
TOTAL_WILDS	17	 
VM_MAD	vcenter	 

Attributes

AVAILHOST	3		
CPUSPEED	2100.0		
CUSTOMIZATION			
NAME	customLinux01		
TYPE	Linux		
HYPERVERISOR	vcenter		
IM_MAD	vcenter		
NSX_LABEL	NSX Manager		
NSX_MANAGER	https://10.0.1.30:443		
NSX_PASSWORD	53COGSQER2U5oesUZ3ZEUQ==		
NSX_STATUS	OK		
NSX_TRANSPORT_ZONES			
TZ	vdnscope-3		
TZ2	vdnscope-4		
TZ3	vdnscope-5		
NSX_TYPE	NSX-V		
NSX_USER	admin		
NSX_VERSION	6.4.5.13282012		
STATUS	green		
TOTALHOST	3		
TOTAL_WILDS	17		
VM_MAD	vcenter		



Attribute	Type	Value	Description
NSX_LABEL	STRING	“NSX - Manager” “NSX-T Manager”	Label for NSX Manager type
NSX_MANAGER	STRING	URL of endpoint	Endpoint containing the NSX Manager URL. OpenNebula must reach that url to send commands
NSX_STATUS	STRING	Possible values are:	Describe the latest NSX status
		OK	NSX_USER and NSX_PASSWORD are correct and a validation query has been made successfully
		Missing NSX_USER	Attribute NSX_USER is not configured
		Missing NSX_PASSWORD	Attribute NSX_PASSWORD is not configured
		Missing NSX_TYPE	Attribute NSX_TYPE has not been discovered
		Missing NSX_MANAGER	Attribute NSX_MANAGER has not been discovered
		Response code incorrect	Validation query had a bad response, usually is due to an invalid user or password
		Error connecting to NSX_MANAGER	NSX_MANAGER has an incorrect IP or there is a problem to communicate with NSX Manager
NSX_TRANSPORT	THZONEARRAZ_NAME => TZ_ID, ...]		List with all the Transport Zones detected
NSX_TYPE	STRING		Determine if is a NSX-V or NSX-T installation
NSX_VERSION	STRING		NSX Installed version

6.5.5 NSX editable attributes

These parameters have to be introduced manually from NSX tab

Parameter	Type	Mandatory	Description
NSX_USER	STRING	YES	NSX Manager user
NSX_PASSWORD	STRING	YES	NSX Manager password

6.5.6 Driver tuning

Drivers can be easily customized please refer to NSX Driver Section in the Integration Guide.

OPEN CLOUD HOST SETUP

7.1 Overview

The Hosts are servers with a hypervisor installed (KVM or LXD) which execute the running Virtual Machines. These Hosts are managed by the KVM or LXD Driver, which will perform the actions needed to manage the VM and its life-cycle. This chapter analyses the KVM or LXD driver in detail, and will give you, amongst other things, the tools to configure and add KVM or LXD hosts into the OpenNebula Cloud.

7.1.1 How Should I Read This Chapter

Before reading this chapter, you should have already installed your *Frontend*, the *KVM Hosts* and/or *LXD Hosts* and have an OpenNebula cloud up and running with at least one virtualization node.

This chapter will focus on the configuration options for the Hosts.

- Read the *KVM driver* section in order to understand the procedure of configuring and managing KVM Hosts.
- Read the *LXD driver* section in order to understand the procedure of configuring and managing LXD Hosts.
- In the *Monitoring* section, you can find information about how OpenNebula is monitoring its Hosts and Virtual Machines, and changes you can make in the configuration of that subsystem.
- You can read this section if you are interested in performing *PCI Passthrough*.

After reading this chapter, you should read the *Open Cloud Storage* chapter.

7.1.2 Hypervisor Compatibility

This chapter applies to KVM and LXD.

Follow the *vCenter Node* section for a similar guide for vCenter.

7.2 KVM Driver

KVM (Kernel-based Virtual Machine) is the hypervisor for OpenNebula's *Open Cloud Architecture*. KVM is a complete virtualization system for Linux. It offers full virtualization, where each Virtual Machine interacts with its own virtualized hardware. This guide describes the use of the KVM with OpenNebula.

7.2.1 Requirements

The Hosts will need a CPU with Intel VT or AMD's AMD-V features, in order to support virtualization. KVM's Preparing to use KVM guide will clarify any doubts you may have regarding if your hardware supports KVM.

KVM will be installed and configured after following the [KVM Host Installation](#) section.

7.2.2 Considerations & Limitations

Try to use *virtio* whenever possible, both for networks and disks. Using emulated hardware, both for networks and disks, will have an impact in performance and will not expose all the available functionality. For instance, if you don't use *virtio* for the disk drivers, you will not be able to exceed a small number of devices connected to the controller, meaning that you have a limit when attaching disks, and it will not work while the VM is running (live disk-attach).

7.2.3 Configuration

KVM Configuration

The OpenNebula packages will configure KVM automatically, therefore you don't need to take any extra steps.

Drivers

The KVM driver is enabled by default in OpenNebula:

```
#-----
#   KVM Virtualization Driver Manager Configuration
#   -r number of retries when monitoring a host
#   -t number of threads, i.e. number of hosts monitored at the same time
#   -l <actions[=command_name]> actions executed locally, command can be
#       overridden for each action.
#       Valid actions: deploy, shutdown, cancel, save, restore, migrate, poll
#       An example: "-l migrate=migrate_local,save"
#   -p more than one action per host in parallel, needs support from hypervisor
#   -s <shell> to execute remote commands, bash by default
#
# Note: You can use type = "qemu" to use qemu emulated guests, e.g. if your
# CPU does not have virtualization extensions or use nested Qemu-KVM hosts
#-----
VM_MAD = [
    NAME      = "kvm",
    SUNSTONE_NAME = "KVM",
    EXECUTABLE = "one_vmm_exec",
    ARGUMENTS  = "-t 15 -r 0 kvm",
    DEFAULT    = "vmm_exec/vmm_exec_kvm.conf",
    TYPE       = "kvm",
    KEEP_SNAPSHOTS= "no",
    IMPORTED_VMS_ACTIONS = "terminate, terminate-hard, hold, release, suspend,
                            resume, delete, reboot, reboot-hard, resched, unresched, disk-attach,
                            disk-detach, nic-attach, nic-detach, snap-create, snap-delete"
]
```

The configuration parameters: `-r`, `-t`, `-l`, `-p` and `-s` are already preconfigured with sane defaults. If you change them you will need to restart OpenNebula.

Read the Virtual Machine Drivers Reference for more information about these parameters, and how to customize and extend the drivers.

Driver Defaults

There are some attributes required for KVM to boot a VM. You can set a suitable defaults for them so, all the VMs get needed values. These attributes are set in `/etc/one/vmm_exec/vmm_exec_kvm.conf`. The following can be set for KVM:

- **EMULATOR**: path to the kvm executable.
- **OS**: attributes KERNEL, INITRD, BOOT, ROOT, KERNEL_CMD, MACHINE, ARCH and SD_DISK_BUS.
- **VCPU**
- **FEATURES**: attributes ACPI, PAE.
- **CPU_MODEL**: attribute MODEL.
- **DISK**: attributes DRIVER and CACHE. All disks will use that driver and caching algorithm.
- **NIC**: attribute FILTER.
- **RAW**: to add libvirt attributes to the domain XML file.
- **HYPERV**: to enable hyperv extensions.
- **SPICE**: to add default devices for SPICE.

Warning: These values are only used during VM creation, for other actions like nic or disk attach/detach the default values must be set in `/var/lib/one/remotes/etc/vmm/kvm/kvmrc`. For more info check [Files and Parameters](#) section.

For example:

```
OS      = [ ARCH = "x86_64" ]
FEATURES = [ PAE = "no", ACPI = "yes", APIC = "no", HYPERV = "no", GUEST_AGENT = "no" ]
DISK    = [ DRIVER = "raw" , CACHE = "none"]
HYPERV_OPTIONS="

```

Note: These values can be overridden in the Cluster, Host and VM Template

Live-Migration for Other Cache settings

In case you are using disks with a cache setting different to none you may have problems with live migration depending on the libvirt version. You can enable the migration adding the --unsafe parameter to the virsh command. The file to change is /var/lib/one/remotes/etc/vmm/kvm/kvmrc. Uncomment the following line, and execute onehost sync --force afterwards:

```
MIGRATE_OPTIONS=--unsafe
```

Configure the Timeouts (Optional)

Optionally, you can set a timeout for the VM Shutdown operation can be set up. This feature is useful when a VM gets stuck in Shutdown (or simply does not notice the shutdown command). By default, after the timeout time the VM will return to Running state but it can also be configured so the VM is destroyed after the grace time. This is configured in /var/lib/one/etc/remotes/vmm/kvm/kvmrc:

```
# Seconds to wait after shutdown until timeout
export SHUTDOWN_TIMEOUT=300

# Uncomment this line to force VM cancellation after shutdown timeout
#export FORCE_DESTROY=yes
```

Working with cgroups (Optional)

Cgroups is a kernel feature that allows to control the number of resources allocated to a given process (among other things). It can be used to enforce the amount of CPU assigned to a VM, as defined in its OpenNebula template (i.e., a VM with CPU=0.5 will get half of the physical CPU cycles than a VM with CPU=1.0). The cgroups are configured **on each hypervisor host (where required), not on the front-end**.

Note: In current operating systems running the systemd, the cgroups are enabled and used by libvirt/KVM automatically. No configuration is necessary. The tool lscgroup (included in distribution package libcgrouptools on RHEL/CentOS or cgrouptools on Debian/Ubuntu) can be used to check the cgroups state on your system. The cgroups aren't available if you get an error output of the tool, e.g.:

```
$ lscgroup
cgroups can't be listed: Cgroup is not mounted
```

Follow the documentation of your operating system to enable and configure the cgroups.

Cgroups can be used to limit the overall amount of physical RAM that the VMs can use, so you can leave always a fraction to the host OS. In this case, you may want to set also the RESERVED_MEM parameter in host or cluster templates.

OpenNebula automatically generates a number of CPU shares proportional to the CPU attribute in the VM template. For example, the host running 2 VMs (ID 73 and 74, with CPU=0.5 and CPU=1) should be configured following way:

```
/sys/fs/cgroup/cpu,cpuacct/machine.slice/
|-- cgroup.clone_children
|-- cgroup.event_control
...
|-- cpu.shares
|-- cpu.stat
|-- machine-qemu\x2d1\x2done\x2d73.scope
```

```

|   |-- cgroup.clone_children
|   |-- cgroup.event_control
|   |-- cgroup.procs
|   |-- cpu.shares
|
|   ...
|
|   '-- vcpu0
|       |-- cgroup.clone_children
|
|       ...
|
|-- machine-qemu\x2d2\x2done\x2d74.scope
|   |-- cgroup.clone_children
|   |-- cgroup.event_control
|   |-- cgroup.procs
|   |-- cpu.shares
|
|   ...
|
|   '-- vcpu0
|       |-- cgroup.clone_children
|
|       ...
|
|-- notify_on_release
`-- tasks

```

with the CPU shares for each VM:

```

$ cat '/sys/fs/cgroup/cpu,cpuacct/machine.slice/machine-qemu\x2d1\x2done\x2d73.scope/
˓→cpu.shares'
512
$ cat '/sys/fs/cgroup/cpu,cpuacct/machine.slice/machine-qemu\x2d2\x2done\x2d74.scope/
˓→cpu.shares'
1024

```

Note: The cgroups (directory) layout can be different based on your operating system and configuration. The [libvirt documentation](#) describes all the cases and a way the cgroups are managed by libvirt/KVM.

VCPUs are not pinned so most probably the virtual machine's process will be changing the physical cores it is using. In an ideal case where the VM is alone in the physical host the total amount of CPU consumed will be equal to VCPU plus any overhead of virtualization (for example networking). In case there are more VMs in that physical node and is heavily used then the VMs will compete for physical CPU time. In this case, the cgroups will provide a fair share of CPU time between VMs (a VM with CPU=2 will get double the time as a VM with CPU=1).

In case you are not overcommitting (CPU=VCPU) all the virtual CPUs will have one physical CPU (even if it's not pinned) so they could consume the number of VCPU assigned minus the virtualization overhead and any process running in the host OS.

7.2.4 Usage

KVM Specific Attributes

The following are template attributes specific to KVM, please refer to the template reference documentation for a complete list of the attributes supported to define a VM.

DISK

- **TYPE:** This attribute defines the type of the media to be exposed to the VM, possible values are: `disk` (default) or `cdrom`. This attribute corresponds to the `media` option of the `-driver` argument of the `kvm` command.

- DRIVER: specifies the format of the disk image; possible values are `raw`, `qcow2`... This attribute corresponds to the `format` option of the `-driver` argument of the `kvm` command.
- CACHE: specifies the optional cache mechanism, possible values are `default`, `none`, `writethrough` and `writeback`.
- IO: set IO policy possible values are `threads` and `native`.
- DISCARD: controls what to do with trim commands, the options are `ignore` or `unmap`. It can only be used with `virtio-scsi`.
- IO Throttling support: You can limit TOTAL/READ/WRITE throughput or IOPS. Also burst control for this IO operations can be set for each disk. See the reference guide for the attribute names and purpose.

NIC

- TARGET: name for the tun device created for the VM. It corresponds to the `ifname` option of the '`-net`' argument of the `kvm` command.
- SCRIPT: name of a shell script to be executed after creating the tun device for the VM. It corresponds to the `script` option of the '`-net`' argument of the `kvm` command.
- QoS to control the network traffic. We can define different kind of controls over network traffic:
 - `INBOUND_AVG_BW`
 - `INBOUND_PEAK_BW`
 - `INBOUND_PEAK_KW`
 - `OUTBOUND_AVG_BW`
 - `OUTBOUND_PEAK_BW`
 - `OUTBOUND_PEAK_KW`
- MODEL: ethernet hardware to emulate. You can get the list of available models with this command:

```
$ kvm -net nic,model=? -nographic /dev/null
```

- FILTER to define a network filtering rule for the interface. Libvirt includes some predefined rules (e.g. `clean-traffic`) that can be used. [Check the Libvirt documentation](#) for more information, you can also list the rules in your system with:

```
$ virsh -c qemu:///system nwfilter-list
```

- `VIRTIO_QUEUES` to define how many queues will be used for the communication between CPUs and Network drivers. This attribute only is available with `MODEL = 'virtio'`.

Graphics

If properly configured, libvirt and KVM can work with SPICE ([check this for more information](#)). To select it, just add to the `GRAPHICS` attribute:

- `TYPE = SPICE`

Enabling spice will also make the driver inject specific configuration for these machines. The configuration can be changed in the driver configuration file, variable `SPICE_OPTIONS`.

Virtio

Virtio is the framework for IO virtualization in KVM. You will need a linux kernel with the virtio drivers for the guest, check [the KVM documentation for more info](#).

If you want to use the virtio drivers add the following attributes to your devices:

- DISK, add the attribute `DEV_PREFIX="vd"`
- NIC, add the attribute `MODEL="virtio"`

For disks you can also use SCSI bus (`sd`) and it will use virtio-scsi controller. This controller also offers high speed as it is not emulating real hardware but also adds support to trim commands to free disk space when the disk has the attribute `DISCARD="unmap"`. If needed, you can change the number of vCPU queues this way:

```
FEATURES = [
    VIRTIO_SCSI_QUEUES = 4
]
```

Additional Attributes

The `raw` attribute offers the end user the possibility of passing by attributes not known by OpenNebula to KVM. Basically, everything placed here will be written literally into the KVM deployment file ([use libvirt xml format and semantics](#)).

```
RAW = [ type = "kvm",
        data = "<devices><serial type=\"pty\"><source path=\"/dev/pts/5\"/><target_"
        ↪port=\"0\"/></serial><console type=\"pty\" tty=\"/dev/pts/5\"><source path=\"/dev/
        ↪pts/5\"/><target port=\"0\"/></console></devices>" ]
```

Libvirt metadata

The following OpenNebula information is added to the metadata section of the Libvirt domain, the specific attributes are listed below:

- `system_datastore`
- `name`
- `uname`
- `uid`
- `gname`
- `gid`
- `opennebula_version`
- `stime`
- `deployment_time`

They correspond to their values OpenNebula equivalents for the XML representation of the VM. `opennebula_version` and `deployment_time` are the OpenNebula version used during the deployment and deployment time at epoch format, respectively.

Also the VM name is included at Libvirt XML `title` field, so if the `--title` option is used for listing the Libvirt domains the VM name will be shown with the domain name.

Disk/Nic Hotplugging

KVM supports hotplugging to the `virtio` and the `SCSI` buses. For disks, the bus the disk will be attached to is inferred from the `DEV_PREFIX` attribute of the disk template.

- `vd: virtio` (recommended).
- `sd: SCSI` (default).
- `hd: IDE`

Note: Hotplugging is not supported for CDROM and floppy.

If `TARGET` is passed instead of `DEV_PREFIX` the same rules apply (what happens behind the scenes is that OpenNebula generates a `TARGET` based on the `DEV_PREFIX` if no `TARGET` is provided).

The defaults for the newly attached disks and NICs are in `/var/lib/one/remotes/etc/vmm/kvm/kvmrc`. The relevant parameters are prefixed with `DEFAULT_ATTACH_` and explained in the [Files and Parameters](#) below.

For Disks and NICs, if the guest OS is a Linux flavor, the guest needs to be explicitly tell to rescan the PCI bus. This can be done issuing the following command as root:

```
# echo 1 > /sys/bus/pci/rescan
```

Enabling QEMU Guest Agent

QEMU Guest Agent allows the communication of some actions with the guest OS. This agent uses a `virtio serial` connection to send and receive commands. One of the interesting actions is that it allows to freeze the filesystem before doing an snapshot. This way the snapshot won't contain half written data. Filesystem freeze will only be used with `CEPH` and `qcow2` storage drivers.

The agent package needed in the Guest OS is available in most distributions. Is called `qemu-guest-agent` in most of them. If you need more information you can follow these links:

- https://access.redhat.com/documentation/en-US/Red_Hat_Enterprise_Linux/7/html/Virtualization_Deployment_and_Administration_Guide/chap-QEMU_Guest_Agent.html
- http://wiki.libvirt.org/page/Qemu_guest_agent
- <http://wiki.qemu.org/Features/QAPI/GuestAgent>

The communication channel with guest agent is enabled in the domain XML when the `GUEST_AGENT` feature is selected in the VM Template.

Importing VMs

VMs running on KVM hypervisors that were not launched through OpenNebula can be imported in OpenNebula. It is important to highlight that, besides the limitations explained in the host guide, the “Poweroff” operation is not available for these imported VMs in KVM.

7.2.5 Tuning & Extending

Multiple Actions per Host

Warning: This feature is experimental. Some modifications to the code must be done before this is a recommended setup.

By default the drivers use a unix socket to communicate with the libvirt daemon. This method can only be safely used by one process at a time. To make sure this happens the drivers are configured to send only one action per host at a time. For example, there will be only one deployment done per host at a given time.

This limitation can be solved configuring libvirt to accept TCP connections and OpenNebula to use this communication method.

Libvirt configuration

Here is described how to configure libvirdt to accept unencrypted and unauthenticated TCP connections in a CentOS 7 machine. For other setup check your distribution and libvirt documentation.

Change the file `/etc/libvirt/libvirtd.conf` in each of the hypervisors and make sure that these parameters are set and have the following values:

```
listen_tls = 0
listen_tcp = 1
tcp_port = "16509"
auth_tcp = "none"
```

You will also need to modify `/etc/sysconfig/libvirtd` and uncomment this line:

```
LIBVIRTD_ARGS="--listen"
```

After modifying these files the libvirt daemon must be restarted:

```
$ sudo systemctl restart libvirtd
```

OpenNebula configuration

The VMM driver must be configured so it allows more than one action to be executed per host. This can be done adding the parameter `-p` to the driver executable. This is done in `/etc/one/oned.conf` in the VM_MAD configuration section:

```
VM_MAD = [
    name      = "kvm",
    executable = "one_vmm_exec",
    arguments  = "-t 15 -r 0 kvm -p",
    default    = "vmm_exec/vmm_exec_kvm.conf",
    type       = "kvm" ]
```

Change the file `/var/lib/one/remotes/etc/vmm/kvm/kvmrc` so set a TCP endpoint for libvirt communication:

```
export LIBVIRT_URI=qemu+tcp://localhost/system
```

The scheduler configuration should also be changed to let it deploy more than one VM per host. The file is located at `/etc/one/sched.conf` and the value to change is `MAX_HOST`. For example, to let the scheduler submit 10 VMs per host use this line:

```
MAX_HOST = 10
```

After this update the remote files in the nodes and restart opennebula:

```
$ onehost sync --force
$ sudo systemctl restart opennebula
```

Files and Parameters

The driver consists of the following files:

- `/usr/lib/one/mads/one_vmm_exec`: generic VMM driver.
- `/var/lib/one/remotes/vmm/kvm`: commands executed to perform actions.

And the following driver configuration files:

- `/etc/one/vmm_exec/vmm_exec_kvm.conf`: This file is home for default values for domain definitions (in other words, OpenNebula templates).

It is generally a good idea to place defaults for the KVM-specific attributes, that is, attributes mandatory in the KVM driver that are not mandatory for other hypervisors. Non mandatory attributes for KVM but specific to them are also recommended to have a default. Changes on this file **require opennebula to be restarted**.

- `/var/lib/one/remotes/etc/vmm/kvmrc`: This file holds instructions to be executed before the actual driver load to perform specific tasks or to pass environmental variables to the driver. The syntax used for the former is plain shell script that will be evaluated before the driver execution. For the latter, the syntax is the familiar:

```
ENVIRONMENT_VARIABLE=VALUE
```

The parameters that can be changed here are as follows:

Parameter	Description
<code>LIBVIRT_URI</code>	Connection string to libvirt
<code>QEMU_PROTOCOL</code>	Protocol used for live migrations
<code>SHUTDOWN_TIMEOUT</code>	Seconds to wait after shutdown until timeout
<code>VIRSH_RETRIES</code>	Number of “virsh” command retries when required. Currently used in
<code>SYNC_TIME</code>	Trigger VM time synchronization from RTC on resume and after mig
<code>FORCE_DESTROY</code>	Force VM cancellation after shutdown timeout
<code>CANCEL_NO_ACPI</code>	Force VM’s without ACPI enabled to be destroyed on shutdown
<code>MIGRATE_OPTIONS</code>	Set options for the virsh migrate command
<code>DEFAULT_ATTACH_CACHE</code>	This parameter will set the default cache type for new attached disks.
<code>DEFAULT_ATTACH_DISCARD</code>	Default dicard option for newly attached disks, if the attribute is miss
<code>DEFAULT_ATTACH_IO</code>	Default I/O policy for newly attached disks, if the attribute is missing
<code>DEFAULT_ATTACH_TOTAL_BYTES_SEC</code>	Default total bytes/s I/O throttling for newly attached disks, if the attr
<code>DEFAULT_ATTACH_TOTAL_BYTES_SEC_MAX</code>	Default Maximum total bytes/s I/O throttling for newly attached disks
<code>DEFAULT_ATTACH_TOTAL_BYTES_SEC_MAX_LENGTH</code>	Default Maximum length total bytes/s I/O throttling for newly attached
<code>DEFAULT_ATTACH_READ_BYTES_SEC</code>	Default read bytes/s I/O throttling for newly attached disks, if the attr
<code>DEFAULT_ATTACH_READ_BYTES_SEC_MAX</code>	Default Maximum read bytes/s I/O throttling for newly attached disks
<code>DEFAULT_ATTACH_READ_BYTES_SEC_MAX_LENGTH</code>	Default Maximum length read bytes/s I/O throttling for newly attached

Table 7.1 – continued

Parameter	Description
DEFAULT_ATTACH_WRITE_BYTES_SEC	Default write bytes/s I/O throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_WRITE_BYTES_SEC_MAX	Default Maximum write bytes/s I/O throttling for newly attached disk
DEFAULT_ATTACH_WRITE_BYTES_SEC_MAX_LENGTH	Default Maximum length write bytes/s I/O throttling for newly attached disk
DEFAULT_ATTACH_TOTAL_IOPS_SEC	Default total IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_TOTAL_IOPS_SEC_MAX	Default Maximum total IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_TOTAL_IOPS_SEC_MAX_LENGTH	Default Maximum length total IOPS throttling for newly attached disk
DEFAULT_ATTACH_READ_IOPS_SEC	Default read IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_READ_IOPS_SEC_MAX	Default Maximum read IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_READ_IOPS_SEC_MAX_LENGTH	Default Maximum length read IOPS throttling for newly attached disk
DEFAULT_ATTACH_WRITE_IOPS_SEC	Default write IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_WRITE_IOPS_SEC_MAX	Default Maximum write IOPS throttling for newly attached disks, if the attribute is missing
DEFAULT_ATTACH_WRITE_IOPS_SEC_MAX_LENGTH	Default Maximum length write IOPS throttling for newly attached disk
DEFAULT_ATTACH_NIC_MODEL	Default NIC model for newly attached NICs, if the attribute is missing
DEFAULT_ATTACH_NIC_FILTER	Default NIC libvirt filter for newly attached NICs, if the attribute is missing

See the Virtual Machine drivers reference for more information.

7.2.6 Troubleshooting

image magic is incorrect

When trying to restore the VM from a suspended state this error is returned:

```
libvirtd1021: operation failed: image magic is incorrect
```

It can be fixed by applying:

```
options kvm_intel nested=0
options kvm_intel emulate_invalid_guest_state=0
options kvm ignore_msrs=1
```

7.3 LXD Driver

LXD is a daemon which provides a REST API to drive LXC containers. Containers are lightweight OS-level Virtualization instances, they behave like Virtual Machines but don't suffer from hardware emulation processing penalties by sharing the kernel with the host.

7.3.1 Requirements

The LXD driver support using LXD through snap packages, if there is a snap installed, it will detect it and use that installation path.

The host needs to be an Ubuntu system > 1604 or Debian > 10.

7.3.2 Considerations & Limitations

The guest OS will share the Linux kernel with the virtualization node, so you won't be able to launch any non-Linux OS.

There are a number of regular features that are not implemented yet:

- snapshots
- live migration
- save/restore
- live disk resize
- LVM datastore
- PCI Passthrough
- volatile filesystems
- **offline disk resize:**
 - not supported on multiple partition images
 - only supported **xfs** and **ext4** filesystems
- **datablocks:** Datablocks created on OpenNebula will need to be formatted before being attached to a container
- **multiple partition images:** One of the partitions must have a valid */etc/fstab* to mount the partitions
- `lxc exec $container -- login` in a centos container doesn't outputs the login shell

7.3.3 Configuration

There are some interaction options between LXD and OpenNebula configured in `/var/lib/one/remotes/etc/vmm/lxd/lxdrc`

```
#####
# VNC Options
#####
#
# Options to customize the VNC access to the container:
#   - :command: to be executed in the VNC terminal.
#   - :width: of the terminal
#   - :height: of the terminal
#   - :timeout: seconds to close the terminal if no input has been received
:vnc:
:command: /bin/login
:width: 800
:height: 600
:timeout: 300

#####
# OpenNebula Configuration Options
#####
#
# Default path for the datastores. This only need to be change if the
# corresponding value in oned.conf has been modified.
: datastore_location: /var/lib/one/datastores
```

In case of a more complex cgroup configuration the containers cgroup could be placed in separate slice instead of default root cgroup. You can configure it via an environmental variable

```
export LXC_CGROUP_PREFIX=system.slice
```

LXD daemon

Every existing container should have defined the following limits: `limits.cpu.allowance`, `limits.cpu` and `limits.memory`. The `opennebula-node-lxd` package sets the default profile with these limits to 100%, 1 and 512MB.

Drivers

The LXD driver is enabled by default in OpenNebula:

```
#-----
# LXD Virtualization Driver Manager Configuration
# -r number of retries when monitoring a host
# -t number of threads, i.e. number of hosts monitored at the same time
# -l <actions[=command_name]> actions executed locally, command can be
# overridden for each action.
# Valid actions: deploy, shutdown, cancel, save, restore, migrate, poll
# An example: "-l migrate=migrate_local,save"
# -p more than one action per host in parallel, needs support from hypervisor
# -s <shell> to execute remote commands, bash by default
# -w Timeout in seconds to execute external commands (default unlimited)
#
#-----
VM_MAD = [
    NAME          = "lxd",
    SUNSTONE_NAME = "LXD",
    EXECUTABLE    = "one_vmm_exec",
    ARGUMENTS     = "-t 15 -r 0 lxd",
    # DEFAULT      = "vmm_exec/vmm_exec_lxd.conf",
    TYPE          = "xml",
    KEEP_SNAPSHOTS = "no",
    IMPORTED_VMS_ACTIONS = "terminate, terminate-hard, reboot, reboot-hard, poweroff,_
    ↪poweroff-hard, suspend, resume, stop, delete, nic-attach, nic-detach"
]
```

The configuration parameters: `-r`, `-t`, `-l`, `-p` and `-s` are already preconfigured with sane defaults. If you change them you will need to restart OpenNebula.

Read the Virtual Machine Drivers Reference for more information about these parameters, and how to customize and extend the drivers.


7.3.4 Usage

LXD Specific Attributes

The following are template attributes specific to LXD, please refer to the template reference documentation for a complete list of the attributes supported to define a VM.

VNC

The VNC connection seen on Sunstone is the output of the execution of a command run via `lxc exec`, by default this command is `login` and it's configured on a per-node basis by the `lxdrc` file. In order to change it you can set it under `GRAPHICS` with the `COMMAND` key.



The screenshot shows the OpenNebula web interface for managing VM templates. At the top, there's a header with a lock icon, the text "VM Template", and a reference "723 Copy of ubuntu_bionic - LXD". Below the header is a toolbar with several buttons: a blue one with a left arrow and three horizontal lines, a green one with a plus sign and a dropdown arrow, a grey refresh button, a blue "Update" button, a blue "Instantiate" button, a blue "Clone" button, a grey lock and dropdown button, a grey user and dropdown button, a grey gear and dropdown button, and a red trash can button. Underneath the toolbar, there are two tabs: "Info" (disabled) and "Template" (selected). The main content area displays the "CONTEXT" section of the template configuration, which includes settings for NETWORK, SET_HOSTNAME, SSH_PUBLIC_KEY, CPU, DISK, GRAPHICS, LXD_SECURITY_PRIVILEGED, and MEMORY.

```

CONTEXT = [
    NETWORK = "YES",
    SET_HOSTNAME = "$NAME",
    SSH_PUBLIC_KEY = "$USER[SSH_PUBLIC_KEY]" ]
CPU = "1"
DISK = [
    IMAGE_ID = "14" ]
GRAPHICS = [
    COMMAND = "bash",
    LISTEN = "0.0.0.0",
    TYPE = "vnc" ]
LXD_SECURITY_PRIVILEGED = "true"
MEMORY = "768"

```

Security

Containers can be either **privileged** or **unprivileged** and can also allow nested containers. In order to define this setting in the OpenNebula template you should add:

```
LXD_SECURITY_PRIVILEGED=true
LXD_SECURITY_NESTING=true
```

By default OpenNebula will create unprivileged images

Profiles

The LXD daemon may hold several defined profiles. Every container inherits properties by default from the default profile. However you can set a custom profile to inherit from, in the VM template.

```
LXD_PROFILE=<profile_name>
```

Bear in mind that the template will override any matching key with the profile. If the profile is not found on the node, the default profile will be applied and an error will appear on the VM log.

A probe will run in each node reporting to the frontend which profiles exist on the node in order for them to be easily applied without having to manually look for them.

Disks

Attached disks are handled by `type`: disk devices in the container, this works different from KVM in such a way that the disk is mounted on the LXD host and then the mountpoint is passed-through the container in an user defined mountpoint .

The `disk_attach` process, on a high level descriptions follows:

- There is an image file whose contents should be visible inside a container directory
- In order to tell LXD to handle a disk, this file should be mounted on a host directory, `$DATASTORE_LOCATION/$system_datastore_id/$vm_id/mapper/disk.$disk_id`
- The disk can be of different types, currently, the supported ones are `raw` and `qcow2` image files, and ceph `rbd`.
- In order to be mounted, first, each image needs to be mapped to a host device
- Depending on the image type, a different utility will be used, `losetup` for `raw` images, `qemu-nbd` for `qcow2` images and `rbd-nbd` for ceph `rbd`.
- If the image has multiple partitions, each partition will be mounted until an `/etc/fstab` file is found and each partition with a valid filesystem will be mounted accordingly.

Additional Attributes

The `raw` attribute offers the end user the possibility of passing by attributes not known by OpenNebula to LXD. Basically, everything placed here will be written literally into the LXD deployment file.

```
RAW = [ type = "lxd",
        "boot.autostart": "true", "limits.processes": "10000" ]
```

Importing VMs

LXD can deploy containers without any resource limitation, however, OpenNebula cannot create a VM without a stated capacity, thus the wild containers should have these keys defined. Once imported, the containers will benefit from:

- start
- stop *hard also*
- restart *hard also*
- attach/detach_nic
- vnc connection

Containers won't get any benefit from storage related actions since they don't have a valid image in the datastore. If you delete the imported container it will become wild again.

7.3.5 Tuning & Extending

Multi-hypervisor

Since LXD doesn't require virtualization extensions, it can peacefully coexist alongside KVM or other HVM hypervisor in the same virtualization node.

Images

The LXD drivers can create containers from images in the same format as KVM, ex. a qcow2 image.

Create your own image

Basically you create a file, map it into a block device, format the device and create a partition, dump data into it and voilá, you have an image.

We will create a container using the LXD CLI and dump it into a block device in order to use it later in OpenNebula datastores. It could be a good time to *contextualize <kvm_contextualization>* the container, the procedure is the same as KVM.

```
# truncate -s 2G container.img
# block=$(losetup --find --show container.img)
# mkfs.ext4 $block
# mount $block /mnt
# lxc init my-container ubuntu:18.04
# cp -rpa /var/lib/lxd/containers/my-container/rootfs/* /mnt
# umount $block
# losetup -d $block
```

Now the image is ready to be used, you can also use `qemu-img` to convert the image format. Note that you can use any linux standard filesystem / partition layout as a base image for the container. This enables you to easily import images from raw lxc, root partitions from KVM images or proxmox templates.

Use a [linuxcontainers.org Marketplace](#)

Every regular LXD setup comes by default with a public image server read access in order to pull container images from.

```
# lxc remote list
+-----+-----+-----+-----+
|      NAME      |          URL          | PROTOCOL | AUTH |
+-----+-----+-----+-----+
| images        | https://images.linuxcontainers.org | simplestreams |      |
|   | YES       | NO     |           |
+-----+-----+-----+-----+
| local (default) | unix:// | lxd | tls |
|   | NO       | YES    |           |
+-----+-----+-----+-----+
| ubuntu         | https://cloud-images.ubuntu.com/releases | simplestreams |      |
|   | YES       | YES    |           |
+-----+-----+-----+-----+
| ubuntu-daily    | https://cloud-images.ubuntu.com/daily   | simplestreams |      |
|   | YES       | YES    |           |
+-----+-----+-----+-----+
```

OpenNebula can leverage the existing **images** server by using it as a backend for a Marketplace..

Use a KVM disk image

The LXD driver can create a container from an image with a partition table, as long as this image has valid fstab file. LXD containers security is based on this uuid mapping, when you start a container its uuids are mapped according to the LXD config. However, sometimes the container rootfs cannot be mapped, this issue happens with the marketplace images, and in order to use the you need to set the `LXD_SECURITY_PRIVILEGED` to true in the container VM template.

You can get this type of images directly from the OpenNebula Marketplace.

Custom storage backends

If you want to customize the supported images ex. `vmdk` files, the LXD driver has some modules called mappers which allow the driver to interact with several image formats like `raw`, `qcow2` and `rbd` devices.

The mapper basically is a ruby class with two methods defined, a `do_map` method, which loads a disk file into a system block device, and an `do_unmap` method, which reverts this ex.

```
disk.qcow2      -> map -> /dev/nbd0
disk.raw        -> map -> /dev/loop0
one/one-7-54-0 -> map -> /dev/nbd0
```

However things can get tricky when dealing with images with a partition table, you can check the code of the mapper devices [here](#).

7.3.6 Troubleshooting

- The oneadmin user has his `$HOME` in a non `/home/$USER` location. This prevents the oneadmin account from properly using the LXD CLI due to a snap limitation. You can use sudo to use other account to run lxd commands.
- The command parameter in the VNC configuration dictates which command will appear in noVNC when entering a container. Having `/bin/bash` will skip the user login and gain root access on the container.
- If you experience [reboot issues](#) you can apply a network hook patch by copying the file `/usr/share/one/examples/network_hooks/99-lxd_clean.rb` to `/var/lib/one/remotes/vnm/<network_driver>/clean.d` and issuing `onehost sync --force`. This have to be done for all network drivers used in your cloud.


7.4 Monitoring

This section provides an overview of the OpenNebula monitoring subsystem. The monitoring subsystem gathers information relative to the Hosts and the Virtual Machines, such as the Host status, basic performance indicators, as well as Virtual Machine status and capacity consumption. This information is collected by executing a set of static probes provided by OpenNebula. The output of these probes is sent to OpenNebula using a push mechanism.

7.4.1 Overview

Each host periodically sends monitoring data via UDP to the Frontend which collects it and processes it in a dedicated module. This distributed monitoring system resembles the architecture of dedicated monitoring systems, using a lightweight communication protocol, and a push model.

OpenNebula starts a `collectd` daemon running in the Front-end that listens for UDP connections on port 4124. In the first monitoring cycle the OpenNebula connects to the host using `ssh` and starts a daemon that will execute the probe scripts and sends the collected data to the `collectd` daemon in the Frontend every specific amount of seconds (configurable with the `-i` option of the `collectd` `IM_MAD`). This way the monitoring subsystem doesn't need to make new `ssh` connections to receive data.



If the agent stops in a specific Host, OpenNebula will detect that no monitorization data is received from that hosts and will restart the probe with SSH.

Apart from the periodical monitoring some specific drivers (SSH and LVM transfer managers) will trigger sending the data instantly when an action is finished. This is done by sending the HUP signal to the `collectd` client on the host. You can trigger the information update manually with the `'onehost forceupdate'` command.

7.4.2 Requirements

- The firewall of the Frontend (if enabled) must allow UDP packages incoming from the hosts on port 4124.

7.4.3 OpenNebula Configuration

Enabling the Drivers

To enable this monitoring system `/etc/one/oned.conf` must be configured with the following snippets:

`collectd` must be enabled both for KVM:

Note: every setting is also applicable to LXD

```

#-----
# Information Collector for KVM IM's.
#-----

```

```
# This driver CANNOT BE ASSIGNED TO A HOST, and needs to be used with KVM
# -h prints this help.
# -a Address to bind the collectd socket (defaults 0.0.0.0)
# -p UDP port to listen for monitor information (default 4124)
# -f Interval in seconds to flush collected information (default 5)
# -t Number of threads for the server (defult 50)
# -i Time in seconds of the monitorization push cycle. This parameter must
#       be smaller than MONITORING_INTERVAL_HOST, otherwise push monitorization will
#       not be effective.
#-----
IM_MAD = [
    NAME      = "collectd",
    EXECUTABLE = "collectd",
    ARGUMENTS  = "-p 4124 -f 5 -t 50 -i 20" ]
#-----
```

Valid arguments for this driver are:

- **-a:** Address to bind the collectd socket (defaults 0.0.0.0)
- **-p:** port number
- **-f:** Interval in seconds to flush collected information to OpenNebula (default 5)
- **-t:** Number of threads for the collectd server (defult 50)
- **-i:** Time in seconds of the monitorization push cycle. This parameter must be smaller than MONITORING_INTERVAL_HOST (see below), otherwise push monitorization will not be effective.

KVM:

```
#-----
# KVM UDP-push Information Driver Manager Configuration
# -r number of retries when monitoring a host
# -t number of threads, i.e. number of hosts monitored at the same time
#-----
IM_MAD = [
    NAME      = "kvm",
    SUNSTONE_NAME = "KVM",
    EXECUTABLE = "one_im_ssh",
    ARGUMENTS  = "-r 3 -t 15 kvm" ]
#-----
```

The arguments passed to this driver are:

- **-r:** number of retries when monitoring a host
- **-t:** number of threads, i.e. number of hosts monitored at the same time

Monitoring Configuration Parameters

OpenNebula allows to customize the general behavior of the whole monitoring subsystem:

Parameter	Description
MONITOR- ING_INTERVAL_HOST	Time in seconds between host monitorization. It must have a value greater than the manager timer
MONITOR- ING_INTERVAL_DB_UPDATE	Time in seconds between DB writes of VM monitoring information. -1 to disable EDB updating and 0 to write every update
MONITOR- ING_INTERVAL_VM	Time in seconds between VM monitorization. It must have a value greater than the manager timer
MONITOR- ING_INTERVAL_DATASTORE	Time in seconds between Datastore monitorization. It must have a value greater than the manager timer
MONITOR- ING_INTERVAL_MARKET	Time in seconds between marketplace monitorization. It must have a value greater than the manager timer
HOST_PER_INTERVAL	Number of hosts monitored in each interval.

7.4.4 Troubleshooting

Healthy Monitoring System

Every (approximately) monitoring_push_cycle of seconds OpenNebula is receiving the monitoring data of every Virtual Machine and of a host like such:

```
Tue May 24 16:21:47 2016 [Z0] [InM] [D]: Host thost087 (0) successfully monitored.
Tue May 24 16:21:47 2016 [Z0] [VMM] [D]: VM 0 successfully monitored: STATE=a CPU=0.0 ↴
    ↵MEMORY=113404 NETRX=648 NETTX=398
Tue May 24 16:22:07 2016 [Z0] [InM] [D]: Host thost087 (0) successfully monitored.
Tue May 24 16:22:07 2016 [Z0] [VMM] [D]: VM 0 successfully monitored: STATE=a CPU=0.0 ↴
    ↵MEMORY=113516 NETRX=648 NETTX=468
Tue May 24 16:22:11 2016 [Z0] [VMM] [D]: VM 0 successfully monitored: DISK_SIZE=[ID=0,
    ↴SIZE=27] DISK_SIZE=[ID=1,SIZE=1]
Tue May 24 16:22:27 2016 [Z0] [InM] [D]: Host thost087 (0) successfully monitored.
Tue May 24 16:22:27 2016 [Z0] [VMM] [D]: VM 0 successfully monitored: STATE=a CPU=0.0 ↴
    ↵MEMORY=113544 NETRX=648 NETTX=468
```

However, if in oned.log a host is being monitored **actively** periodically (every MONITORING_INTERVAL_HOST seconds) then the monitorization is **not** working correctly:

```
Tue May 24 16:24:23 2016 [Z0] [InM] [D]: Monitoring host thost087 (0)
Tue May 24 16:25:23 2016 [Z0] [InM] [D]: Monitoring host thost087 (0)
Tue May 24 16:26:23 2016 [Z0] [InM] [D]: Monitoring host thost087 (0)
```

If this is the case it's probably because OpenNebula is receiving probes faster than it can process. See the Tuning section to fix this.

Monitoring Probes

For the troubleshooting of errors produced during the execution of the monitoring probes, please refer to the [troubleshooting](#) section.

7.4.5 Tuning & Extending

Adjust Monitoring Interval Times

In order to tune your OpenNebula installation with appropriate values of the monitoring parameters you need to adjust the **-i** option of the `collectd IM_MAD` (the monitoring push cycle).

If the system is not working healthily it will be due to the database throughput since OpenNebula will write the monitoring information to a database, an amount of ~4KB per VM. If the number of virtual machines is too large and the monitoring push cycle too low, OpenNebula will not be able to write that amount of data to the database.

Driver Files

The probes are specialized programs that obtain the monitor metrics. Probes are defined for each hypervisor, and are located at `/var/lib/one/remotes/im/kvm-probes.d` for KVM.

You can easily write your own probes or modify existing ones, please see the Information Manager Drivers guide. Remember to synchronize the monitor probes in the hosts using `onehost sync` as described in the Managing Hosts guide.

7.5 PCI Passthrough

It is possible to discover PCI devices in the Hosts and assign them to Virtual Machines for the KVM hypervisor.

The setup and environment information is taken from [here](#). You can safely ignore all the VGA related sections, for PCI devices that are not graphic cards, or if you don't want to output video signal from them.

Warning: The overall setup state was extracted from a preconfigured Fedora 22 machine. **Configuration for your distro may be different.**

7.5.1 Requirements

- The host that is going to be used for virtualization needs to support **I/O MMU**. For Intel processors this is called VT-d and for AMD processors is called AMD-Vi. The instructions are made for Intel branded processors but the process should be very similar for AMD.
- kernel >= 3.12

7.5.2 Machine Configuration (Hypervisor)

Kernel Configuration

The kernel must be configured to support I/O MMU and to blacklist any driver that could be accessing the PCI's that we want to use in our VMs. The parameter to enable I/O MMU is:

```
intel_iommu=on
```

We also need to tell the kernel to load the vfio-pci driver and blacklist the drivers for the selected cards. For example, for nvidia GPUs we can use these parameters:

```
rd.driver.pre=vfio-pci rd.driver.blacklist=nouveau
```

Loading vfio Driver in initrd

The modules for vfio must be added to initrd. The list of modules are `vfio vfio_iommu_type1 vfio_pci vfio_virqfd`. For example, if your system uses dracut add the file `/etc/dracut.conf.d/local.conf` with this line:

```
add_drivers+="vfio vfio_iommu_type1 vfio_pci vfio_virqfd"
```

and regenerate initrd:

```
# dracut --force
```

Driver Blacklisting

The same blacklisting done in the kernel parameters must be done in the system configuration. `/etc/modprobe.d/blacklist.conf` for nvidia GPUs:

```
blacklist nouveau
blacklist lbm-nouveau
options nouveau modeset=0
alias nouveau off
alias lbm-nouveau off
```

Alongside this configuration vfio driver should be loaded passing the id of the PCI cards we want to attach to VMs. For example, for nvidia Grid K2 GPU we pass the id `10de:11bf`. File `/etc/modprobe.d/local.conf`:

```
options vfio-pci ids=10de:11bf
```

vfio Device Binding

I/O MMU separates PCI cards into groups to isolate memory operation between devices and VMs. To add the cards to vfio and assign a group to them we can use the scripts shared in the [aforementioned web page](#).

This script binds a card to vfio. It goes into `/usr/local/bin/vfio-bind`:

```
#!/bin/sh
modprobe vfio-pci
for dev in "$@"; do
    vendor=$(cat /sys/bus/pci/devices/$dev/vendor)
    device=$(cat /sys/bus/pci/devices/$dev/device)
    if [ -e /sys/bus/pci/devices/\$dev/driver ]; then
        echo $dev > /sys/bus/pci/devices/$dev/driver/unbind
    fi
    echo $vendor $device > /sys/bus/pci/drivers/vfio-pci/new_id
done
```

The configuration goes into `/etc/sysconfig/vfio-bind`. The cards are specified with PCI addresses. Addresses can be retrieved with `lspci` command. Make sure to prepend the domain that is usually `0000`. For example:

```
DEVICES="0000:04:00.0 0000:05:00.0 0000:84:00.0 0000:85:00.0"
```

Here is a systemd script that executes the script. It can be written to `/etc/systemd/system/vfio-bind.service` and enabled:

```
[Unit]
Description=Bounds devices to vfio-pci
After=syslog.target

[Service]
EnvironmentFile=/etc/sysconfig/vfio-bind
Type=oneshot
RemainAfterExit=yes
ExecStart=/usr/local/bin/vfio-bind $DEVICES

[Install]
WantedBy=multi-user.target
```

qemu Configuration

Now we need to give qemu access to the vfio devices for the groups assigned to the PCI cards. We can get a list of PCI cards and its I/O MMU group using this command:

```
# find /sys/kernel/iommu_groups/ -type l
```

In our example our cards have the groups 45, 46, 58 and 59 so we add this configuration to `/etc/libvirt/qemu.conf`:

```
cgroup_device_acl = [
    "/dev/null", "/dev/full", "/dev/zero",
    "/dev/random", "/dev/urandom",
    "/dev/ptmx", "/dev/kvm", "/dev/kqemu",
    "/dev/rtc", "/dev/hpet", "/dev/vfio/vfio",
    "/dev/vfio/45", "/dev/vfio/46", "/dev/vfio/58",
    "/dev/vfio/59"
]
```

7.5.3 Driver Configuration

The only configuration needed is the filter for the monitoring probe that gets the list of PCI cards. By default, the probe doesn't list any cards from a host. To narrow the list, configuration can be changed in `/var/lib/one/remotes/etc/im/kvm-probes.d/pci.conf`. Following configuration attributes are available:

Parameter	Description
filter	List Filters by PCI vendor:device:class patterns (same as for <code>lspci</code>)
short_address	List Filters by short PCI address bus:device.function
device_name	List Filters by device names with case-insensitive regular expression patterns

All filters are applied on the final PCI cards list.

Example:

```
# This option specifies the main filters for PCI card monitoring. The format
# is the same as used by lspci to filter on PCI card by vendor:device(:class)
# identification. Several filters can be added as a list, or separated
# by commas. The NULL filter will retrieve all PCI cards.
#
# From lspci help:
```

```

#      -d [<vendor>]:[<device>][:<class>]
#                  Show only devices with specified vendor, device and class ID.
#                  The ID's are given in hexadecimal and may be omitted or given
#                  as "*", both meaning "any value"#
#
# For example:
#   :filter:
#     - '10de:*'      # all NVIDIA VGA cards
#     - '10de:11bf'    # only GK104GL [GRID K2]
#     - '*:10d3'       # only 82574L Gigabit Network cards
#     - '8086::0c03'   # only Intel USB controllers
#
# or
#
#   :filter: '*:*'    # all devices
#
# or
#
#   :filter: '0:0'     # no devices
#
:filter: '*:*'

# The PCI cards list restricted by the :filter option above can be even more
# filtered by the list of exact PCI addresses (bus:device.func).
#
# For example:
#   :short_address:
#     - '07:00.0'
#     - '06:00.0'
#
:short_address:
- '00:1f.3'

# The PCI cards list restricted by the :filter option above can be even more
# filtered by matching the device name against the list of regular expression
# case-insensitive patterns.
#
# For example:
#   :device_name:
#     - 'Virtual Function'
#     - 'Gigabit Network'
#     - 'USB.*Host Controller'
#     - '^MegaRAID'
#
:device_name:
- 'Ethernet'
- 'Audio Controller'

```

7.5.4 Usage

The basic workflow is to inspect the host information, either in the CLI or in Sunstone, to find out the available PCI devices, and to add the desired device to the template. PCI devices can be added by specifying VENDOR, DEVICE and CLASS, or simply CLASS. Note that OpenNebula will only deploy the VM in a host with the available PCI device. If no hosts match, an error message will appear in the Scheduler log.

CLI

A new table in `onehost show` command gives us the list of PCI devices per host. For example:

PCI DEVICES

VM	ADDR	TYPE	NAME
	00:00.0	8086:0a04:0600	Haswell-ULT DRAM Controller
	00:02.0	8086:0a16:0300	Haswell-ULT Integrated Graphics Controller
123	00:03.0	8086:0a0c:0403	Haswell-ULT HD Audio Controller
	00:14.0	8086:9c31:0c03	8 Series USB xHCI HC
	00:16.0	8086:9c3a:0780	8 Series HECI #0
	00:1b.0	8086:9c20:0403	8 Series HD Audio Controller
	00:1c.0	8086:9c10:0604	8 Series PCI Express Root Port 1
	00:1c.2	8086:9c14:0604	8 Series PCI Express Root Port 3
	00:1d.0	8086:9c26:0c03	8 Series USB EHCI #1
	00:1f.0	8086:9c43:0601	8 Series LPC Controller
	00:1f.2	8086:9c03:0106	8 Series SATA Controller 1 [AHCI mode]
	00:1f.3	8086:9c22:0c05	8 Series SMBus Controller
	02:00.0	8086:08b1:0280	Wireless 7260

- **VM:** The VM ID using that specific device. Empty if no VMs are using that device.
- **ADDR:** PCI Address.
- **TYPE:** Values describing the device. These are VENDOR:DEVICE:CLASS. These values are used when selecting a PCI device do to passthrough.
- **NAME:** Name of the PCI device.

To make use of one of the PCI devices in a VM a new option can be added selecting which device to use. For example this will ask for a Haswell-ULT HD Audio Controller:

```
PCI = [
    VENDOR = "8086",
    DEVICE = "0a0c",
    CLASS = "0403"
]
```

The device can be also specified without all the type values. For example, to get any PCI Express Root Ports this can be added to a VM template:

```
PCI = [
    CLASS = "0604"
]
```

More than one PCI options can be added to attach more than one PCI device to the VM.

Sunstone

In Sunstone the information is displayed in the **PCI** tab:

The screenshot shows the OpenNebula interface with the PCI tab selected. A table lists PCI devices assigned to a VM, with columns for VM, PCI Address, Type, and Name. Below the table, text instructions say "To add a PCI device to a template, select the **Other** tab:" followed by a screenshot of the "Other" tab configuration screen.

VM	PCI Address	Type	Name
	00:00.0	8086:1604:0600	Broadwell-U Host Bridge -OPI
	00:02.0	8086:1616:0300	Broadwell-U Integrated Graphics
	00:03.0	8086:160c:0403	Broadwell-U Audio Controller
	00:04.0	8086:1603:1180	Broadwell-U Camarillo Device
	00:14.0	8086:9cb1:0c03	Wildcat Point-LP USB xHCI Controller
	00:16.0	8086:9cba:0780	Wildcat Point-LP MEI Controller #1
	00:1b.0	8086:9ca0:0403	Wildcat Point-LP High Definition Audio Controller
	00:1c.0	8086:9c90:0604	Wildcat Point-LP PCI Express Root Port #1
	00:1c.3	8086:9c96:0604	Wildcat Point-LP PCI Express Root Port #4
	00:1d.0	8086:9ca6:0c03	Wildcat Point-LP USB EHCI Controller

To add a PCI device to a template, select the **Other** tab:

The "Other" tab configuration screen shows fields for "TYPE" and "DATA". Below it, the "PCI Devices" section has columns for "Vendor", "Device", and "Class". A button at the bottom says "+ Add PCI device".

7.5.5 Usage as Network Interfaces

It is possible use a PCI device as a NIC interface directly in OpenNebula. In order to do so you will need to follow the configuration steps mentioned in this guide, namely changing the device driver.

When defining a Network that will be used for PCI passthrough nics, please use either the `dummy` network driver or the `802.1Q` if you are using VLAN. In any case, type any random value into the `BRIDGE` field, and it will be ignored. For `802.1Q` you can also leave `PHYDEV` blank.

The context packages support the configuration of the following attributes:

- **MAC**: It will change the mac address of the corresponding network interface to the MAC assigned by OpenNebula.
- **IP**: It will assign an IPv4 address to the interface, assuming a /24 netmask.
- **IPv6**: It will assign an IPv6 address to the interface, assuming a /128 netmask.
- **VLAN_ID**: If present, it will create a tagged interface and assign the IPs to the tagged interface.

CLI

When a PCI in a template contains the attribute `TYPE="NIC"`, it will be treated as a NIC and OpenNebula will assign a MAC address, a `VLAN_ID`, an IP, etc, to the PCI device.

This is an example of the PCI section of an interface that will be treated as a NIC:

```
PCI=[  
    NETWORK="passthrough",  
    NETWORK_UNAME="oneadmin",  
    TYPE="NIC",  
    CLASS="0200",  
    DEVICE="10d3",  
    VENDOR="8086" ]
```

Note that the order of appearance of the PCI elements and NIC elements in the template is relevant. They will be mapped to nics in the order they appear, regardless if they're NICs or PCIs.

Sunstone

In the Network tab, under advanced options check the **PCI Passthrough** option and fill in the PCI address. Use the rest of the dialog as usual by selecting a network from the table.

Hardware

PCI passthrough

Device name	Vendor	Device	Class
82574L Gigabit Network Connection ▾	8086	10d3	0200

OPEN CLOUD STORAGE SETUP

8.1 Overview

8.1.1 Datastore Types

OpenNebula storage is structured around the Datastore concept. A Datastore is any storage medium to store disk images. OpenNebula features three different datastore types:

- The **Images Datastore**, stores the images repository.
- The **System Datastore** holds disk for running virtual machines. Disk are moved, or cloned to/from the Images datastore when the VMs are deployed or terminated; or when disks are attached or snapshotted.
- The **Files & Kernels Datastore** to store plain files and not disk images. The plain files can be used as kernels, ram-disks or context files. *See details here*.




Image Datastores

There are different Image Datastores depending on how the images are stored on the underlying storage technology:

- *Filesystem*, to store images in a file form.
- *LVM*, to store images in LVM logical volumes.
- *Ceph*, to store images using Ceph block devices.
- *Raw Device Mapping*, to direct attach to the virtual machine existing block devices in the nodes.
- *iSCSI - Libvirt Datastore*, to access iSCSI devices through the built-in qemu support.

Disk images are transferred between the Image and System datastores by the transfer manager (TM) drivers. These drivers are specialized pieces of software that perform low-level storage operations. The following table summarizes the available transfer modes for each datastore:

Datastore	Image to System Datastore disk transfers methods
Filesystem	<ul style="list-style-type: none"> • shared, images are exported in a shared filesystem • ssh, images are copied using the ssh protocol • qcow2, like <i>shared</i> but specialized for the qcow2 format
Ceph	<ul style="list-style-type: none"> • ceph, all images are exported in Ceph pools • shared, volatile & context disks exported in a shared FS.
LVM	<ul style="list-style-type: none"> • fs_lvm, images exported in a shared FS but dumped to a LV
Raw Devices	<ul style="list-style-type: none"> • dev, images are existing block devices in the nodes
iSCSI libvirt	<ul style="list-style-type: none"> • iscsi, images are iSCSI targets

8.1.2 How Should I Read This Chapter

Before reading this chapter make sure you have read the *Open Cloud Host* chapter. After that, proceed to the specific section for the Datastores you may be interested in.

After reading this chapter you should read the *Open Cloud Networking* chapter.

8.1.3 Hypervisor Compatibility

This chapter applies to KVM and LXD.

Note: LXD Drivers only support Filesystem and Ceph

Follow the *vCenter Storage* section for a similar guide for vCenter.

8.2 Filesystem Datastore

The Filesystem Datastore lets you store VM images in a file form. The use of file-based disk images presents several benefits over device backed disks (e.g. easily backup images, or use of shared FS) although it may not perform as well in some cases.

Usually it is a good idea to have multiple filesystem datastores to:

- Balancing I/O operations between storage servers
- Use different datastores for different cluster hosts
- Apply different transfer modes to different images

- Different SLA policies (e.g. backup) can be applied to different VM types or users
- Easily add new storage to the cloud

The Filesystem datastore can be used with three different transfer modes, described below:

- **shared**, images are exported in a shared filesystem
- **ssh**, images are copied using the ssh protocol
- **qcow2**, like *shared* but specialized for the qcow2 format

Warning: Bind mounts for datastores aren't supported on LXD deployments.

8.2.1 Datastore Layout

Images are saved into the corresponding datastore directory (`/var/lib/one/datastores/<DATASTORE_ID>`). Also, for each running virtual machine there is a directory (named after the VM ID) in the corresponding System Datastore. These directories contain the VM disks and additional files, e.g. checkpoint or snapshots.

For example, a system with an Image Datastore (1) with three images and 3 Virtual Machines (VM 0 and 2 running, and VM 7 stopped) running from System Datastore 0 would present the following layout:

```
/var/lib/one/datastores
|-- 0/
|   |-- 0/
|   |   |-- disk.0
|   |   `-- disk.1
|   |-- 2/
|   |   |-- disk.0
|   `-- 7/
|       |-- checkpoint
|       `-- disk.0
`-- 1
    |-- 05a38ae85311b9dbb4eb15a2010f11ce
    |-- 2bbec245b382fd833be35b0b0683ed09
    `-- d0e0df1fb8cfa88311ea54dfbcfc4b0c
```

Note: The canonical path for `/var/lib/one/datastores` can be changed in `oned.conf` with the `DATASTORE_LOCATION` configuration attribute

Shared & Qcow2 Transfer Modes


The shared transfer driver assumes that the datastore is mounted in all the hosts of the cluster. Typically this is achieved through a distributed FS like NFS, GlusterFS or Lustre.

When a VM is created, its disks (the `disk.i` files) are copied or linked in the corresponding directory of the system datastore. These file operations are always performed remotely on the target host.

This transfer mode usually reduces VM deployment times and **enables live-migration**, but it can also become a bottleneck in your infrastructure and degrade your Virtual Machines performance if the virtualized services perform disk-intensive workloads. Usually this limitation may be overcome by:


- Using different file-system servers for the images datastores, so the actual I/O bandwidth is balanced

- Using an ssh System Datastore instead, the images are copied locally to each host
- Tuning or improving the file-system servers



SSH Transfer Mode

In this case the System Datastore is distributed among the hosts. The ssh transfer driver uses the hosts' local storage to place the images of running Virtual Machines. All the operations are then performed locally but images have to be copied always to the hosts, which in turn can be a very resource demanding operation. Also this driver prevents the use of live-migrations between hosts.



8.2.2 Frontend Setup

The Frontend needs to prepare the storage area for:

- The Image Datastores, to store the images.
- The System Datastores, will hold temporary disks and files for VMs stopped and undeployed.

Shared & Qcow2 Transfer Modes

Simply mount the **Image** Datastore directory in the front-end in `/var/lib/one/datastores/<datastore_id>`. Note that if all the datastores are of the same type you can mount the whole `/var/lib/one/datastores` directory.

Warning: The frontend only needs to mount the Image Datastores and **not** the System Datastores.

Note: NFS volumes mount tips. The following options are recommended to mount a NFS shares:soft, intr, rsize=32768, wsize=32768. With the documented configuration of libvirt/kvm the image files are accessed as oneadmin user. In case the files must be read by root the option no_root_squash must be added.

SSH Transfer Mode

Simply make sure that there is enough space under `/var/lib/one/datastores` to store Images and the disks of the stopped and undeployed virtual machines. Note that `/var/lib/one/datastores` **can be mounted from any NAS/SAN server in your network**.

8.2.3 Node Setup

Shared & Qcow2 Transfer Modes

The configuration is the same as for the Frontend above, simply mount in each node the datastore directories in `/var/lib/one/datastores/<datastore_id>`.

SSH Transfer Mode

Just make sure that there is enough space under `/var/lib/one/datastores` to store the disks of running VMs on that host.

Warning: Make sure all the hosts, including the frontend, can ssh to any other host (including themselves). Otherwise migrations will not work.

8.2.4 OpenNebula Configuration

Once the Filesystem storage is setup, the OpenNebula configuration comprises two steps:

- Create a System Datastore

- Create an Image Datastore

Create a System Datastore

To create a new System Datastore you need to specify its type as system datastore and transfer mode:

Attribute	Description
NAME	The name of the datastore
TYPE	SYSTEM_DS
TM_MAD	shared for shared transfer mode qcow2 for qcow2 transfer mode ssh for ssh transfer mode

This can be done either in Sunstone or through the CLI, for example to create a System Datastore using the shared mode simply:

```
$ cat systemds.txt
NAME      = nfs_system
TM_MAD   = shared
TYPE     = SYSTEM_DS

$ onedatastore create systemds.txt
ID: 101
```

Note: When different system datastore are available the TM_MAD_SYSTEM attribute will be set after picking the datastore.

Create an Image Datastore

In the same way, to create an Image Datastore you need to set:

Attribute	Description
NAME	The name of the datastore
DS_MAD	fs
TM_MAD	shared for shared transfer mode qcow2 for qcow2 transfer mode ssh for ssh transfer mode

For example, the following illustrates the creation of a filesystem datastore using the shared transfer drivers.

```
$ cat ds.conf
NAME      = nfs_images
DS_MAD   = fs
TM_MAD   = shared

$ onedatastore create ds.conf
ID: 100
```

Also note that there are additional attributes that can be set, check the datastore template attributes.

Warning: Be sure to use the same TM_MAD for both the System and Image datastore. When combining different transfer modes, check the section below.

Additional Configuration

- CONVERT: yes (default) or no. If DRIVER is set on the image datastore, this option controls whether the images in different formats are internally converted into the DRIVER format on import.
- QCOW2_OPTIONS: Custom options for the qemu-img clone action. The qcow2 drivers are a specialization of the shared drivers to work with the qcow2 format for disk images. Images are created and through the qemu-img command using the original image as backing file. Custom options can be sent to qemu-img clone action through the variable QCOW2_OPTIONS in /etc/one/tmrc.
- DD_BLOCK_SIZE: Block size for dd operations (default: 64kB) could be set in /var/lib/one/remotes/etc/datastore/fs/fs.conf.

Combining the shared & SSH Transfer Modes

When using the shared mode, you can improve VM performance by placing the disks in the host local storage area. In this way, you will have a repository of images (distributed across the hosts using a shared FS) but the VMs running from the local disks. This effectively combines shared and SSH modes above.

Important: You can still use the pure shared mode in this case. In this way the same image can be deployed in a shared mode or a ssh mode (per VM).

Warning: This setup will increase performance at the cost of increasing deployment times.

To configure this scenario, simply configure a shared Image and System datastores as described above (TM_MAD=shared). Then add a SSH system datastore (TM_MAD=ssh). Any image registered in the Image datastore can now be deployed using the shared or SSH system datastores.

Warning: If you added the shared datastores to cluster, you need to add the new SSH system datastore to the very same clusters.

To select the (alternate) deployment mode, add the following attribute to the Virtual Machine template:

- TM_MAD_SYSTEM="ssh"

8.3 Ceph Datastore

The Ceph datastore driver provides OpenNebula users with the possibility of using Ceph block devices as their Virtual Images.

Warning: This driver requires that the OpenNebula nodes using the Ceph driver must be Ceph clients of a running Ceph cluster. More information in [Ceph documentation](#).

8.3.1 Datastore Layout

Images are stored in a Ceph pool, named after its OpenNebula id `one-<IMAGE ID>`. Virtual machine disks are stored by default in the same pool (Ceph Mode). You can also choose to export the Image rbd to the hypervisor local storage using the SSH Mode.

Important: Only is necessary to register each image once, then it can be deployed using any mode, ceph or ssh.

Ceph Mode (Default)

In this mode, virtual machines will use the same Image rbd volumes for its disks (persistent images), or a new snapshots of the image created in the form `one-<IMAGE ID>-<VM ID>-<DISK ID>` (non-persistent images).

For example, consider a system using an Image and System Datastore backed by a Ceph pool named `one`. The pool with one Image (ID 0) and two Virtual Machines 14 and 15 using this Image as virtual disk 0 would be similar to:

```
$ rbd ls -l -p one --id libvirt
NAME      SIZE PARENT      FMT PROT LOCK
one-0     10240M          2
one-0@snap 10240M          2 yes
one-0-14-0 10240M one/one-0@snap 2
one-0-15-0 10240M one/one-0@snap 2
```

Note: In this case context disk and auxiliar files (deployment description and checkpoints) are stored locally in the nodes.

SSH Mode

In this mode, the associated rbd file for each disk is exported to a file and stored in the local file system of the hypervisor.

For example, in the previous example if the VM 14 is set to be deployed in a SSH system datastore (e.g. 100), the layout of the datastore in the hypervisor would be similar to:

```
$ ls -l /var/lib/one/datastores/100/14
total 609228
-rw-rw-r-- 1 oneadmin oneadmin 1020 Dec 20 14:41 deployment.0
-rw-r--r-- 1 oneadmin oneadmin 10737418240 Dec 20 15:19 disk.0
-rw-rw-r-- 1 oneadmin oneadmin 372736 Dec 20 14:41 disk.1
```

Note: In this case `disk.0` is generated with a command similar to `rbd export one/one-0@snap disk.0`

8.3.2 Ceph Cluster Setup

This guide assumes that you already have a functional Ceph cluster in place. Additionally you need to:

- Create a pool for the OpenNebula datastores. Write down the name of the pool to include it in the datastore definitions.

```
$ ceph osd pool create one 128
$ ceph osd lspools
0 data,1 metadata,2 rbd,6 one,
```

- Define a Ceph user to access the datastore pool; this user will also be used by libvirt to access the disk images. For example, create a user libvirt:

On the **Ceph Jewel** (v10.2.x) and before:

```
$ ceph auth get-or-create client.libvirt \
    mon 'allow r' osd 'allow class-read object_prefix rbd_children, allow rwx_
    ↪pool=one'
```

On the **Ceph Luminous** (v12.2.x) and later:

```
$ ceph auth get-or-create client.libvirt \
    mon 'profile rbd' osd 'profile rbd pool=one'
```

Warning: Ceph Luminous release comes with simplified RBD capabilities (more information about user management and authorization capabilities is in the Ceph [documentation](#)). When **upgrading existing Ceph deployment to the Luminous and later**, please ensure the selected user has proper new capabilities. For example, for above user libvirt by running:

```
$ ceph auth caps client.libvirt \
    mon 'profile rbd' osd 'profile rbd pool=one'
```

- Get a copy of the key of this user to distribute it later to the OpenNebula nodes.

```
$ ceph auth get-key client.libvirt | tee client.libvirt.key
$ ceph auth get client.libvirt -o ceph.client.libvirt.keyring
```

- Although RBD format 1 is supported it is strongly recommended to use Format 2. Check that `ceph.conf` includes:

```
[global]
rbd_default_format = 2
```

- Pick a set of client nodes of the cluster to act as storage bridges. These nodes will be used to import images into the Ceph Cluster from OpenNebula. These nodes must have `qemu-img` command installed.

Note: For production environments it is recommended to **not co-allocate** ceph services (monitor, osds) with OpenNebula nodes or front-end

8.3.3 Frontend and Node Setup

In order to use the Ceph cluster the nodes need to be configured as follows:

- The ceph client tools must be available in the machine
- The mon daemon must be defined in the `ceph.conf` for all the nodes, so `hostname` and `port` doesn't need to be specified explicitly in any Ceph command.

- Copy the Ceph user keyring (`ceph.client.libvirt.keyring`) to the nodes under `/etc/ceph`, and the user key (`client.libvirt.key`) to the oneadmin home.

```
$ scp ceph.client.libvirt.keyring root@node:/etc/ceph
$ scp client.libvirt.key oneadmin@node:
```

8.3.4 Node Setup

Nodes need extra steps to setup credentials in libvirt:

- Generate a secret for the Ceph user and copy it to the nodes under oneadmin home. Write down the UUID for later use.

```
$ UUID=`uuidgen`; echo $UUID
c7bdeabf-5f2a-4094-9413-58c6a9590980

$ cat > secret.xml <<EOF
<secret ephemeral='no' private='no'>
<uuid>$UUID</uuid>
<usage type='ceph'>
    <name>client.libvirt secret</name>
</usage>
</secret>
EOF

$ scp secret.xml oneadmin@node:
```

- Define the a libvirt secret and remove key files in the nodes:

```
$ virsh -c qemu:///system secret-define secret.xml

$ virsh -c qemu:///system secret-set-value --secret $UUID --base64 $(cat client.
↳libvirt.key)

$ rm client.libvirt.key
```

- The oneadmin account needs to access the Ceph Cluster using the libvirt Ceph user defined above. This requires access to the ceph user keyring. Test that Ceph client is properly configured in the node.

```
$ ssh oneadmin@node
$ rbd ls -p one --id libvirt
```

You can read more information about this in the Ceph guide [Using libvirt with Ceph](#).

- Ancillary virtual machine files like context disks, deployment and checkpoint files are created at the nodes under `/var/lib/one/datastores/`, make sure that enough storage for these files is provisioned in the nodes.
- If you are going to use the SSH mode, you have to take into account the space needed for the system datastore `/var/lib/one/datastores/<ds_id>` where `ds_id` is the ID of the System Datastore.

LXD Node settings

Skip these steps if your virtualization node is KVM.

Install rbd-nbd

```
apt install rbd-nbd
```

Warning: The rbd backend of the LXD drivers requires ceph Luminous and kernel 4.15

8.3.5 OpenNebula Configuration

To use your Ceph cluster with the OpenNebula, you need to define a System and Image datastores. Each Image/System Datastore pair will share same following Ceph configuration attributes:

Attribute	Description	Mandatory
NAME	The name of the datastore	YES
POOL_NAME	The Ceph pool name	YES
CEPH_USER	The Ceph user name, used by libvirt and rbd commands.	YES
CEPH_KEY	Key file for user, if not set default locations are used	NO
CEPH_CONF	Non default ceph configuration file if needed.	NO
RBD_FORMAT	By default RBD Format 2 will be used.	NO
BRIDGE_LIST	List of storage bridges to access the Ceph cluster	YES
CEPH_HOST	Space-separated list of Ceph monitors. Example: host1 host2:port2 host3 host4:port4.	YES
CEPH_SECRET	The UUID of the libvirt secret.	YES
EC_POOL_NAME	Name of Ceph erasure coded pool	NO
CEPH_TRASH	Enables <i>trash</i> feature on given datastore (Luminous+), values: yes no	NO

Note: You may add another Image and System Datastores pointing to other pools with different allocation/replication policies in Ceph.

Note: Ceph Luminous release allows use of erasure coding for RBD images. In general, erasure coded images take up less space, but have worse I/O performance. Erasure coding can be enabled on Image and/or System Datastores by configuring EC_POOL_NAME with the name of the erasure coded data pool. Regular replicated Ceph pool POOL_NAME is still required for image metadata. More information in [Ceph documentation](#).

Create a System Datastore

System Datastore also requires these attributes:

Attribute	Description	Mandatory
TYPE	SYSTEM_DS	YES
TM_MAD	ceph (to use the full ceph mode, see above) ssh (to use local host storage, ssh mode above)	YES

Create a System Datastore in Sunstone or through the CLI, for example:

```
$ cat systemds.txt
NAME      = ceph_system
TM_MAD    = ceph
TYPE      = SYSTEM_DS

POOL_NAME   = one
CEPH_HOST   = "host1 host2:port2"
CEPH_USER   = libvirt
CEPH_SECRET = "6f88b54b-5dae-41fe-a43e-b2763f601cfcc"

BRIDGE_LIST = cephfrontend

$ onedatastore create systemds.txt
ID: 101
```

Note: When different system datastore are available the TM_MAD_SYSTEM attribute will be set after picking the datastore.

Create an Image Datastore

Apart from the previous attributes, that need to be the same as the associated System Datastore, the following can be set for an Image Datastore:

Attribute	Description	Mandatory
NAME	The name of the datastore	YES
DS_MAD	ceph	YES
TM_MAD	ceph	YES
DISK_TYPE	RBD	YES
STAGING_DIR	Default path for image operations in the bridges	NO

An example of datastore:

```
> cat ds.conf
NAME = "cephds"
DS_MAD = ceph
TM_MAD = ceph

DISK_TYPE = RBD

POOL_NAME   = one
CEPH_HOST   = "host1 host2:port2"
CEPH_USER   = libvirt
CEPH_SECRET = "6f88b54b-5dae-41fe-a43e-b2763f601cfcc"

BRIDGE_LIST = cephfrontend

> onedatastore create ds.conf
ID: 101
```

Warning: If you are going to use the TM_MAD_SYSTEM attribute with SSH mode, you need to have an *SSH type system Datastore* configured.

Note: See quotas for more information about quotas over Ceph backend storage.

Additional Configuration

Default values for the Ceph drivers can be set in `/var/lib/one/remotes/etc/datastore/ceph/ceph.conf`:

- `POOL_NAME`: Default volume group
- `STAGING_DIR`: Default path for image operations in the storage bridges
- `RBD_FORMAT`: Default format for RBD volumes.
- `DD_BLOCK_SIZE`: Block size for *dd* operations (default: 64kB).

Using different modes

When creating a VM Template you can choose to deploy the disks using the default Ceph mode or the SSH on. Note that the same mode will be used for all disks of the VM. To set the deployment mode add the following attribute to the VM template:

- `TM_MAD_SYSTEM="ssh"`


When using Sunstone, the deployment mode needs to be set in Storage tab.

8.4 LVM Datastore

The LVM datastore driver provides OpenNebula with the possibility of using LVM volumes instead of plain files to hold the Virtual Images. This reduces the overhead of having a file-system in place and thus it may increase I/O performance.

8.4.1 Datastore Layout

Images are stored as regular files (under the usual path: `/var/lib/one/datastores/<id>`) in the Image Datastore, but they will be dumped into a Logical Volumes (LV) upon virtual machine creation. The virtual machines will run from Logical Volumes in the node.



This is the recommended driver to be used when a high-end SAN is available. The same LUN can be exported to all the hosts, Virtual Machines will be able to run directly from the SAN.

Note: The LVM datastore does **not** need CLVM configured in your cluster. The drivers refresh LVM meta-data each time an image is needed in another host.

For example, consider a system with two Virtual Machines (9 and 10) using a disk, running in a LVM Datastore, with ID 0. The nodes have configured a shared LUN and created a volume group named vg-one-0, the layout of the datastore would be:

```
# lvs
LV      VG      Attr      LSize Pool Origin Data%  Meta%  Move
lv-one-10-0  vg-one-0  -wi-----  2.20g
lv-one-9-0   vg-one-0  -wi-----  2.20g
```

Warning: Images are stored in a shared storage in file form (e.g. NFS, GlusterFS...) the datastore directories and mount points needs to be configured as a regular shared image datastore, [please refer to FileSystem Datastore guide](#). It is a good idea to first deploy a shared FileSystem datastore and once it is working replace the associated System datastore with the LVM one maintaining the shared mount point as described below.

8.4.2 Frontend Setup

- The frontend needs to have access to the images datastore, mounting the associated directory.

8.4.3 Node Setup

Nodes needs to meet the following requirements:

- LVM2 must be available in the Hosts.
- lvmtd must be disabled. Set this parameter in /etc/lvm/lvm.conf: use_lvmtd = 0, and disable the lvm2-lvmtd.service if running.
- oneadmin needs to belong to the disk group.

- All the nodes needs to have access to the same LUNs.
- A LVM VG needs to be created in the shared LUNs for each datastore following name: `vg-one-<system_ds_id>`. This just need to be done in one node.
- Virtual Machine disks are symbolic links to the block devices. However, additional VM files like checkpoints or deployment files are stored under `/var/lib/one/datastores/<id>`. Be sure that enough local space is present.
- All the nodes needs to have access to the images and system datastores, mounting the associated directories.

Note: In case of the virtualization host reboot, the volumes need to be activated to be available for the hypervisor again. If the `node package` is installed, the activation is done automatically. Otherwise, each volume device of the virtual machines running on the host before the reboot needs to be activated manually by running `lvchange -ay $DEVICE` (or, activation script `/var/tmp/one/tm/fs_lvm/activate` from the remote scripts may be executed on the host to do the job).

8.4.4 OpenNebula Configuration

Once the storage is setup, the OpenNebula configuration comprises two steps:

- Create a System Datastore
- Create an Image Datastore

Create a System Datastore

LVM System Datastores needs to be created with the following values:

Attribute	Description
NAME	The name of the Datastore
TM_MAD	<code>fs_lvm</code>
TYPE	<code>SYSTEM_DS</code>
BRIDGE_LIST	List of nodes with access to the LV to monitor it

For example:

```
> cat ds.conf
NAME      = lvm_system
TM_MAD   = fs_lvm
TYPE     = SYSTEM_DS
BRIDGE_LIST = "node1.kvm.lvm node2.kvm.lvm"

> onedatastore create ds.conf
ID: 100
```

Create an Image Datastore

To create an Image Datastore you just need to define the name, and set the following:

Attribute	Description
NAME	The name of the datastore
TYPE	IMAGE_DS
DS_MAD	fs
TM_MAD	fs_lvm
DISK_TYPE	BLOCK

For example, the following examples illustrates the creation of an LVM datastore using a configuration file. In this case we will use the host `host01` as one of our OpenNebula LVM-enabled hosts.

```
> cat ds.conf
NAME = production
DS_MAD = fs
TM_MAD = fs_lvm
DISK_TYPE = "BLOCK"
TYPE = IMAGE_DS
SAFE_DIRS="/var/tmp /tmp"

> onedatastore create ds.conf
ID: 101
```

Driver Configuration

By default the LVM driver will zero any LVM volume so VM data cannot leak to other instances. However, this process takes some time and may delay the deployment of a VM. The behavior of the driver can be configured in the file `/var/lib/one/remotes/etc/fs_lvm/fs_lvm.conf`, in particular:

Attribute	Description
ZERO_LVM_ON_CREATE	Zero LVM volumes when they are created/resized
ZERO_LVM_ON_DELETE	Zero LVM volumes when VM disks are deleted
DD_BLOCK_SIZE	Block size for <code>dd</code> operations (default: 64kB)

Example:

```
# Zero LVM volumes on creation or resizing
ZERO_LVM_ON_CREATE=no

# Zero LVM volumes on delete, when the VM disks are disposed
ZERO_LVM_ON_DELETE=yes

# Block size for the dd commands
DD_BLOCK_SIZE=32M
```

8.5 Raw Device Mapping (RDM) Datastore

The RDM Datastore is an Image Datastore that enables raw access to node block devices. This datastore enables fast VM deployments due to a non-existent transfer operation from the image datastore to the system datastore.

Warning: The datastore should only be usable by the administrators. Letting users create images in this datastore will cause security problems. For example, register an image `/dev/sda` and reading the host filesystem.

8.5.1 Datastore Layout

The RDM Datastore is used to register already existent block devices in the nodes. The devices should be already setup and available and, VMs using these devices must be fixed to run in the nodes ready for them. Additional virtual machine files, like deployment files or volatile disks are created as regular files.

8.5.2 Frontend Setup

No additional setup is required. Make sure `/etc/one/oned.conf` has the following configuration for the RDM datastore:

```
TM_MAD_CONF = [
    NAME = "dev", LN_TARGET = "NONE", CLONE_TARGET = "NONE", SHARED = "YES",
    TM_MAD_SYSTEM = "ssh,shared", LN_TARGET_SSH = "SYSTEM", CLONE_TARGET_SSH = "SYSTEM",
    DISK_TYPE_SSH = "BLOCK", LN_TARGET_SHARED = "NONE",
    CLONE_TARGET_SHARED = "SELF", DISK_TYPE_SHARED = "BLOCK"
]
```

8.5.3 Node Setup

The devices you want to attach to a VM should be accessible by the hypervisor. As KVM usually runs as oneadmin, make sure this user is in a group with access to the disk (like disk) and has read write permissions for the group.

8.5.4 OpenNebula Configuration

Once the storage is setup, the OpenNebula configuration comprises two steps:

- Create a System Datastore
- Create an Image Datastore

Create a System Datastore

The RDM Datastore can work with the following System Datastores:

- Filesystem, shared transfer mode
- Filesystem, ssh transfer mode

Please refer to the [Filesystem Datastore section](#) for more details. Note that the System Datastore is only used for volatile disks and context devices.

Create an Image Datastore

To create an Image Datastore you just need to define the name, and set the following:

Attribute	Description
NAME	The name of the datastore
TYPE	IMAGE_DS
DS_MAD	dev
TM_MAD	dev
DISK_TYPE	BLOCK

An example of datastore:

```
> cat rdm.conf
NAME      = rdm_datastore
TYPE      = "IMAGE_DS"
DS_MAD    = "dev"
TM_MAD    = "dev"
DISK_TYPE = "BLOCK"

> onedatastore create rdm.conf
ID: 101
```

8.5.5 Datastore Usage

New images can be added as any other image specifying the path. As an example here is an image template to add a node disk /dev/sdb:

```
cat image.tpl

NAME=scsi_device
PATH=/dev/sdb
PERSISTENT=YES

oneimage create image.tpl -d 101
```

If you are using the CLI shorthand parameters define the image using source:

```
oneimage create -d 101 --name nbd --source /dev/sdc --driver raw --prefix vd --
→persistent --type OS --size 0MB
```

Note: As this datastore does is just a container for existing devices images does not take any size from it. All devices registered will render size of 0 and the overall devices datastore will show up with 1MB of available space

8.6 iSCSI - Libvirt Datastore

This datastore is used to register already existing iSCSI volume available to the hypervisor nodes

Warning: The datastore should only be usable by the administrators. Letting users create images in this datastore can cause security problems.

8.6.1 Frontend Setup

No additional configuration is needed

8.6.2 Node Setup

The nodes need to meet the following requirements:

- * The devices you want to attach to a VM should be accessible by the hypervisor.
- * Qemu needs to be compiled with Libiscsi support.

iSCSI CHAP Authentication

In order to use CHAP authentication, you will need to create a libvirt secret in **all** the hypervisors. Follow this [Libvirt Secret XML format](#) guide to register the secret. Take this into consideration:

- `incominguser` field on the iSCSI authentication file should match the Datastore's `ISCSI_USER` parameter.
- `<target>` field in the secret XML document will contain the `ISCSI_USAGE` parameter.
- Do this in all the hypervisors.

8.6.3 OpenNebula Configuration

Once the storage is setup, the OpenNebula configuration comprises two steps:

- Create a System Datastore
- Create an Image Datastore

Create a System Datastore

The RDM Datastore can work with the following System Datastores:

- Filesystem, shared transfer mode
- Filesystem, ssh transfer mode

Please refer to the [Filesystem Datastore section](#) for more details. Note that the System Datastore is only used for volatile disks and context devices.

Create an Image Datastore

To create an Image Datastore you just need to define the name, and set the following:

Attribute	Description
NAME	The name of the datastore
TYPE	IMAGE_DS
DS_MAD	iscsi_libvirt
TM_MAD	iscsi_libvirt
DISK_TYPE	ISCSI
ISCSI_HOST	iSCSI Host. Example: host or host:port.

If you need to use CHAP authentication (optional) add the following attributes to the datastore:

Attribute	Description
ISCSI_USAGE	Usage of the secret with the CHAP Auth string.
ISCSI_USER	user the iSCSI CHAP authentication.

An example of datastore:

```
> cat iscsi.ds
NAME = iscsi
DISK_TYPE = "ISCSI"
```

```

DS_MAD = "iscsi_libvirt"
TM_MAD = "iscsi_libvirt"

ISCSI_HOST = "the_iscsi_host"
ISCSI_USER = "the_iscsi_user"
ISCSI_USAGE = "the_iscsi_usage"

> onedatastore create iscsi.ds
ID: 101

```

Warning: Images created in this datastore should be persistent. Making the images non persistent allows more than one VM use this device and will probably cause problems and data corruption.

8.6.4 Datastore Usage

New images can be added as any other image specifying the path. If you are using the CLI **do not use the shorthand parameters** as the CLI check if the file exists and the device most provably won't exist in the frontend.

As an example here is an image template to add a node disk iqn.1992-01.com.example:storage:diskarrays-sn-a8675309:

```

NAME = iscsi_device
PATH = iqn.1992-01.com.example:storage:diskarrays-sn-a8675309
PERSISTENT = YES

```

Warning: As this datastore does is just a container for existing devices images does not take any size from it. All devices registered will render size of 0 and the overall devices datastore will show up with 1MB of available space

Note: You may override the any of the following: ISCSI_HOST, ISCSI_USER, ISCSI_USAGE and ISCSI_IQN parameters in the image template. These overridden parameters will come into effect for new Virtual Machines.

Here is an example of an iSCSI LUN template that uses the iSCSI transfer manager.

```

oneadmin@onedv:~/exampletemplates$ more iscsimage.tpl
NAME=iscsi_device_with_lun
PATH=iqn.2014.01.192.168.50.61:test:7cd2cc1e/0
ISCSI_HOST=192.168.50.61
PERSISTENT=YES

```

Note the explicit “/0” at the end of the IQN target path. This is the iSCSI LUN ID.

8.7 The Kernels & Files Datastore

The Files Datastore lets you store plain files to be used as VM kernels, ramdisks or context files. The Files Datastore does not expose any special storage mechanism but a simple and secure way to use files within VM templates. There is a Files Datastore (datastore ID: 2) ready to be used in OpenNebula.

8.7.1 Requirements

There are no special requirements or software dependencies to use the Files Datastore. The recommended drivers make use of standard filesystem utils (cp, ln, mv, tar, mkfs...) that should be installed in your system.

8.7.2 Configuration

Most of the configuration considerations used for disk images datastores do apply to the Files Datastore (e.g. driver setup, cluster assignment, datastore management...).

The specific attributes for this datastore driver are listed in the following table, you will also need to complete with the common datastore attributes:

Attribute	Description
TYPE	Use FILE_DS to setup a Files datastore
DS_MAD	The DS type, use fs to use the file-based drivers
TM_MAD	Transfer drivers for the datastore, use ssh to transfer the files

For example, the following illustrates the creation of File Datastore.

```
> cat kernels_ds.conf
NAME = kernels
DS_MAD = fs
TM_MAD = ssh
TYPE = FILE_DS
SAFE_DIRS = /var/tmp/files

> onedatastore create kernels_ds.conf
ID: 100

> onedatastore list
      ID NAME          CLUSTER      IMAGES TYPE DS      TM
      0  system        -           0  sys  -
      1  default       -           0  img  dummy
      2  files         -           0  fil  fs      ssh
  100  kernels       -           0  fil  fs      ssh
```

The DS and TM MAD can be changed later using the `onedatastore update` command. You can check more details of the datastore by issuing the `onedatastore show` command.

8.7.3 Host Configuration

The recommended ssh driver for the File Datastore does not need any special configuration for the hosts. Just make sure that there is enough space under `$DATASTORE_LOCATION` to hold the VM files in the front-end and hosts.

For more details [refer to the *Filesystem Datastore* guide](#), as the same configuration guidelines applies.

OPEN CLOUD NETWORKING SETUP

9.1 Overview

When a new Virtual Machine is launched, OpenNebula will connect its network interfaces (defined by NIC attribute) to hypervisor physical devices as defined in the Virtual Network. This will allow the VM to have access to different networks, public or private.

OpenNebula supports four different networking modes:

- *Bridged*. The Virtual Machine is directly attached to an existing bridge in the hypervisor. This mode can be configured to use security groups and network isolation.
- *VLAN*. Virtual Networks are implemented through 802.1Q VLAN tagging.
- *VXLAN*. Virtual Networks implements VLANs using the VXLAN protocol that relies on a UDP encapsulation and IP multicast.
- *Open vSwitch*. Similar to the VLAN mode but using an openvswitch instead of a Linux bridge.
- *Open vSwitch on VXLAN*. Similar to the VXLAN mode but using an openvswitch instead of a Linux bridge.

When you create a new network you will need to add the attribute VN_MAD to the template, specifying which of the above networking modes you want to use.

Note: Security Groups are not supported by the Open vSwitch mode.

Each network driver has 3 different configuration actions executed before (*pre*) and after(*post*) the VM is booted, and when the VM leaves (*clean*) the host. Each one of those driver actions can be extended with custom programs by placing executable files inside the corresponding action folders (*pre.d*, *post.d* and *clean.d*) within the network driver directory.

Finally, the networking stack of OpenNebula can be integrated with an external IP address manager (IPAM). To do so, you need to develop the needed glue, for more details refer to the IPAM driver guide.

9.1.1 How Should I Read This Chapter

Before reading this chapter make sure you have read the *Open Cloud Storage* chapter.

Start by reading the common *Node Setup* section to learn how to configure your hosts, and then proceed to the specific section for the networking mode that you are interested in.

After reading this chapter you can complete your OpenNebula installation by optionally enabling an *External Authentication* or configuring *Sunstone*. Otherwise you are ready to Operate your Cloud.

9.1.2 Hypervisor Compatibility

This chapter applies to KVM and LXD.

9.2 Node Setup

This guide includes specific node setup steps to enable each network mode. You **only need** to apply the corresponding section to the select mode.

9.2.1 Bridged Networking Mode

Requirements

- The OpenNebula node packages has been installed, see [the KVM node installation section](#) for more details.
- By default, network isolation is provided through `ebtables`, this package needs to be installed in the nodes.

Configuration

- Create a linux bridge for each network that would be exposed to Virtual Machines. Use the same name in all the nodes.
- Add the physical network interface to the bridge.

For example, a node with two networks one for public IP addresses (attached to `eth0`) and another one for private traffic (NIC `eth1`) should have two bridges:

```
$ ip link show type bridge
4: br0: ...
5: br1: ...

$ ip link show master br0
2: eth0: ...

$ ip link show master br1
3: eth1: ...
```

Note: It is recommended that this configuration is made persistent. Please refer to the network configuration guide of your system to do so.

9.2.2 VLAN Networking Mode

Requirements

- The OpenNebula node packages has been installed, see [the KVM node installation section](#) for more details.
- The `8021q` module must be loaded in the kernel.
- A network switch capable of forwarding VLAN tagged traffic. The physical switch ports should be VLAN trunks.

Configuration

No additional configuration is needed.

9.2.3 VXLAN Networking Mode

Requirements

- The OpenNebula node packages has been installed, see [the KVM node installation section](#) for more details.
- The node must run a Linux kernel (>3.7.0) that natively supports the VXLAN protocol and the associated iproute2 package.
- When all the nodes are connected to the same broadcasting domain be sure that the multicast traffic is not filtered by any iptable rule in the nodes. Note that if the multicast traffic needs to traverse routers a multicast protocol like IGMP needs to be configured in your network.

Configuration

No additional configuration is needed.

9.2.4 Open vSwitch Networking Mode

Requirements

- The OpenNebula node packages has been installed, see [the KVM node installation section](#) for more details.
- You need to install Open vSwitch on each node. Please refer to the Open vSwitch documentation to do so.

For example, a node that forwards Virtual Networks traffic through the `enp0s8` network interface should create an openvswitch like:

```
# ovs-vsctl show
c61ba96f-fc11-4db9-9636-408e763f529e
    Bridge "ovsbr0"
        Port "ovsbr0"
            Interface "ovsbr0"
            type: internal
        Port "enp0s8"
            Interface "enp0s8"
```

Configuration

- Create a openvswitch for each network that would be expose to Virtual Machines. Use the same name in all the nodes.
- Add the physical network interface to the openvswitch.

Note: It is recommended that this configuration is made persistent. Please refer to the network configuration guide of your system to do so.

9.3 Bridged Networking

This guide describes how to deploy Bridged networks. In this mode, the virtual machine traffic is directly bridged through the Linux bridge in the nodes. Bridged networks can operate in four different modes depending on the additional traffic filtering made by the OpenNebula:

- **Dummy Bridged**, no filtering, no bridge setup (legacy no-op driver).
- **Bridged**, no filtering is made, managed bridge.
- **Bridged with Security Groups**, iptables rules are installed to implement security groups rules.
- **Bridged with ebtables VLAN**, same as above plus additional ebtables rules to isolate (L2) each Virtual Networks.

9.3.1 Considerations & Limitations

The following needs to be considered regarding traffic isolation:

- In the **Dummy Bridged**, **Bridged** and **Bridged with Security Groups** modes you can add tagged network interfaces to achieve network isolation. This is the **recommended** deployment strategy in production environments in this mode.
- The **Bridged with ebtables VLAN** mode is targeted to small environments without proper hardware support to implement VLANS. Note that it is limited to /24 networks and that IP addresses cannot overlap between Virtual Networks. This mode is only recommended for testing purposes.

9.3.2 OpenNebula Configuration

The following configuration attributes can be adjusted in `/var/lib/one/remotes/etc/vnm/OpenNebulaNetwork.conf`:

Parameter	Description
<code>ipset_maxelem</code>	Maximal number of entries in the IP set (used for the security group rules)
<code>keep_empty_bridge</code>	Set to true to preserve bridges with no virtual interfaces left.
<code>bridge_conf</code>	<i>Hash</i> Options for <code>brctl</code> (deprecated, will be translated to <code>ip-route2</code> options)
<code>ip_bridge_conf</code>	<i>Hash</i> Options for <code>ip-route2 ip link add <bridge> type bridge ...</code>

9.3.3 Defining a Bridged Network

To create a virtual network include the following information:

Attribute	Value	Mandatory
VN_MAD	<ul style="list-style-type: none"> • dummy for the Dummy Bridged mode • bridge for the Bridged mode • fw for Bridged with Security Groups • ebtables for Bridged with ebtables isolation 	YES
BRIDGE	Name of the linux bridge in the nodes	YES
PHYDEV	Name of the physical network device that will be attached to the bridge (does not apply for dummy driver)	NO

The following example defines Bridged network with the Security Groups mode:

```
NAME      = "bridged_net"
VN_MAD   = "fw"
BRIDGE   = vbr1
...
```

9.3.4 ebtables VLAN Mode: default rules

This section lists the ebtables rules that are created, in case you need to debug your setup

```
# Drop packets that don't match the network's MAC Address
-s ! <mac_address>/ff:ff:ff:ff:ff:0 -o <tap_device> -j DROP
# Prevent MAC spoofing
-s ! <mac_address> -i <tap_device> -j DROP
```

9.4 802.1Q VLAN Networks

This guide describes how to enable Network isolation provided through host-managed VLANs. This driver will create a bridge for each OpenNebula Virtual Network and attach an VLAN tagged network interface to the bridge. This mechanism is compliant with [IEEE 802.1Q](#).

The VLAN id will be the same for every interface in a given network, automatically computed by OpenNebula. It may also be forced by specifying an `VLAN_ID` parameter in the Virtual Network template.

9.4.1 OpenNebula Configuration

The `VLAN_ID` is calculated according to this configuration option of `oned.conf`:

```
# VLAN_IDS: VLAN ID pool for the automatic VLAN_ID assignment. This pool
# is for 802.1Q networks (Open vSwitch and 802.1Q drivers). The driver
# will try first to allocate VLAN_IDS[START] + VNET_ID
# start: First VLAN_ID to use
```

```
#      reserved: Comma separated list of VLAN_IDs or ranges. Two numbers
#      separated by a colon indicate a range.

VLAN_IDS = [
    START      = "2",
    RESERVED   = "0, 1, 4095"
]
```

By modifying that parameter you can reserve some VLANs so they aren't assigned to a Virtual Network. You can also define the first VLAN_ID. When a new isolated network is created, OpenNebula will find a free VLAN_ID from the VLAN pool. This pool is global, and it's also shared with the [Open vSwitch](#) network mode.

The following configuration attributes can be adjusted in `/var/lib/one/remotes/etc/vnm/OpenNebulaNetwork.conf`:

Parameter	Description
<code>validate_vlan_id</code>	Set to true to check that no other vlans are connected to the bridge
<code>keep_empty_bridge</code>	Set to true to preserve bridges with no virtual interfaces left.
<code>bridge_conf</code>	<i>Hash</i> Options for <code>brctl</code> (deprecated, will be translated to <code>ip-route2</code> options)
<code>ip_bridge_conf</code>	<i>Hash</i> Options for <code>ip route2 ip link add <bridge> type bridge ...</code>
<code>ip_link_conf</code>	<i>Hash</i> Arguments passed to <code>ip link add</code>

Example:

```
# Following options will be added when creating bridge. For example:
#
#      ip link add name <bridge name> type bridge stp_state 1
#
#:ip_bridge_conf:
#:stp_state: on

# These options will be added to the ip link add command. For example:
#
#      sudo ip link add lxcbr0.260 type vxlan id 260 group 239.0.101.4 \
#          ttl 16 dev lxcbr0 udp6zerocsumrx tos 3
#
:ip_link_conf:
:udp6zerocsumrx:
:tos: 3
```

9.4.2 Defining a 802.1Q Network

To create a 802.1Q network include the following information:

Attribute	Value	Mandatory
VN_MAD	802.1Q	YES
PHYDEV	Name of the physical network device that will be attached to the bridge.	YES
BRIDGE	Name of the linux bridge, defaults to onebr<net_id> or onebr.<vlan_id>	NO
VLAN_ID	The VLAN ID, will be generated if not defined and AUTOMATIC_VLAN_ID is set to YES	YES (unless AUTOMATIC_VLAN_ID)
AUTOMATIC_VLAN_ID	Mandatory and must be set to YES if VLAN_ID hasn't been defined	YES (unless VLAN_ID)
MTU	The MTU for the tagged interface and bridge	NO

The following example defines a 802.1Q network

```
NAME      = "hmnet"
VN_MAD   = "802.1Q"
PHYDEV   = "eth0"
VLAN_ID  = 50          # optional. If not setting VLAN_ID set AUTOMATIC_VLAN_ID = "YES"
BRIDGE   = "brhm"       # optional
```

In this scenario, the driver will check for the existence of the brhm bridge. If it doesn't exist it will be created. eth0 will be tagged (eth0.50) and attached to brhm (unless it's already attached).

9.5 VXLAN Networks

This guide describes how to enable Network isolation provided through the VXLAN encapsulation protocol. This driver will create a bridge for each OpenNebula Virtual Network and attach a VXLAN tagged network interface to the bridge.

The VLAN id will be the same for every interface in a given network, calculated automatically by OpenNebula. It may also be forced by specifying an VLAN_ID parameter in the Virtual Network template.

Additionally each VLAN has associated a multicast address to encapsulate L2 broadcast and multicast traffic. This address is assigned by default to the 239.0.0.0/8 range as defined by RFC 2365 (Administratively Scoped IP Multicast). In particular the multicast address is obtained by adding the VLAN_ID to the 239.0.0.0/8 base address.

9.5.1 Considerations & Limitations

This driver works with the default UDP server port 8472.

VXLAN traffic is forwarded to a physical device, this device can be set (optionally) to be a VLAN tagged interface, but in that case you must make sure that the tagged interface is manually created first in all the hosts.

The physical device that will act as the physical device **must** have an IP.

Concurrent VXLANs host limit

Each VXLAN is associated with one multicast group. There is a limit on how many multicast groups can be a physical host member of at the same time. That also means, how many **different** VXLANs can be used on a physical host concurrently. The default value is 20 and can be changed via sysctl through kernel runtime parameter net.ipv4.igmp_max_memberships.

For permanent change to e.g. 150, place following settings inside the /etc/sysctl.conf:

```
net.ipv4.igmp_max_memberships=150
```

and reload the configuration

```
$ sudo sysctl -p
```

9.5.2 OpenNebula Configuration

It is possible specify the start VLAN ID by configuring /etc/one/oned.conf:

```
# VXLAN_IDS: Automatic VXLAN Network ID (VNI) assigment. This is used
# for vxlan networks.
#     start: First VNI to use

VXLAN_IDS = [
    START = "2"
]
```

The following configuration attributes can be adjusted in /var/lib/one/remotes/etc/vnm/OpenNebulaNetwork.conf:

Parameter	Description
vxlan_mc	Base multicast address for each VLAN. The multicas sddress is vxlan_mc + vlan_id
vxlan_ttl	Time To Live (TTL) should be > 1 in routed multicast networks (IGMP)
validate_vlan_id	Set to true to check that no other vlans are connected to the bridge
keep_empty_bridge	Set to true to preserve bridges with no virtual interfaces left.
bridge_conf	Hash Options for brctl (deprecated, will be translated to ip-route2 options)
ip_bridge_conf	Hash Options for ip-route2 ip link add <bridge> type bridge ...
ip_link_conf	Hash Arguments passed to ip link add

Example:

```
# Following options will be added when creating bridge. For example:
#
#     ip link add name <bridge name> type bridge stp_state 1
#
# :ip_bridge_conf:
#   :stp_state: on

# These options will be added to the ip link add command. For example:
#
#     sudo ip link add lxcbr0.260 type vxlan id 260 group 239.0.101.4 \
#       ttl 16 dev lxcbr0 udp6zerocsumrx tos 3
#
#:ip_link_conf:
:udp6zerocsumrx:
:tos: 3
```

9.5.3 Defining a VXLAN Network

To create a VXLAN network include the following information:

Attribute	Value	Mandatory
VN_MAD	vxlan	YES
PHYDEV	Name of the physical network device that will be attached to the bridge.	YES
BRIDGE	Name of the linux bridge, defaults to onebr<net_id> or onebr.<vlan_id>	NO
VLAN_ID	The VLAN ID, will be generated if not defined	NO
AUTO-MATIC_VLAN_ID	Mandatory if VLAN_ID is not defined, in order to get OpenNebula to assign an ID	NO
MTU	The MTU for the tagged interface and bridge	NO

The following example defines a VXLAN network

```
NAME      = "vxlan_net"
VN_MAD   = "vxlan"
PHYDEV   = "eth0"
VLAN_ID  = 50          # optional
BRIDGE   = "vxlan50" # optional
...
```

In this scenario, the driver will check for the existence of the vxlan50 bridge. If it doesn't exist it will be created. eth0 will be tagged (eth0.50) and attached to vxlan50 (unless it's already attached). Note that eth0 can be a 802.1Q tagged interface if you want to isolate the OpenNebula VXLAN traffic.

9.5.4 Using VXLAN with BGP EVPN

By default VXLAN relies on multicast to discover tunnel endpoints, alternatively you can use MP-BGP EVPN for the control plane and hence increase the scalability of your network. This section describes the main configuration steps to deploy such setup.

Configuring the Hypervisors

The hypervisor needs to run a BGP EVPN capable routing software like [FFRouting \(FRR\)](#). Its main purpose is to send BGP updates with the MAC address and IP (optional) for each VXLAN tunnel endpoint (i.e. the VM interfaces in the VXLAN network) running in the host. The updates needs to be distributed to all other hypervisors in the cloud to achieve full route reachability. This second step is usually performed by one or more BGP route reflectors.

As an example, consider two hypervisors 10.4.4.11 and 10.4.4.12, and a route reflector at 10.4.4.13. The FRR configuration file for the hypervisors could be (to announce all VXLAN networks):

```
router bgp 7675
bgp router-id 10.4.4.11
no bgp default ipv4-unicast
neighbor 10.4.4.13 remote-as 7675
neighbor 10.4.4.13 capability extended-nexthop
address-family l2vpn evpn
  neighbor 10.4.4.13 activate
  advertise-all-vni
exit-address-family
exit
```

And the reflector for our AS 7675, and hypervisors in 10.4.4.0/24:

```

router bgp 7675
  bgp router-id 10.4.4.13
  bgp cluster-id 10.4.4.13
  no bgp default ipv4-unicast
  neighbor kvm_hosts peer-group
  neighbor kvm_hosts remote-as 7675
  neighbor kvm_hosts capability extended-nexthop
  neighbor kvm_hosts update-source 10.4.4.13
  bgp listen range 10.4.4.0/24 peer-group kvm_hosts
  address-family l2vpn evpn
    neighbor fabric activate
    neighbor fabric route-reflector-client
  exit-address-family
exit

```

Note that this a simple scenario using the same configuration for all the VNIs. Once the routing software is configured you should see the updates in each hypervisor for the VMs running in it, for example:

Network	Next Hop	Metric	LocPrf	Weight	Path
Route Distinguisher: 10.4.4.11:2					
*> [2]:[0]:[0]:[48]:[02:00:0a:03:03:c9]	10.4.4.11			32768	i
*> [3]:[0]:[32]:[10.4.4.11]	10.4.4.11			32768	i
Route Distinguisher: 10.4.4.12:2					
*>i[2]:[0]:[0]:[48]:[02:00:0a:03:03:c8]	10.4.4.12	0	100	0	i
*>i[3]:[0]:[32]:[10.4.4.12]	10.4.4.12	0	100	0	i

Configuring OpenNebula

You need to update `/var/lib/one/remotes/vnm/OpenNebulaNetwork.conf` file to:

1. Set BGP EVPN as the control plane for your BUM traffic, `vxlan_mode`.
2. Select the hypervisor is going to send the traffic to the VTEP. This can be either `dev`, to forward the traffic through the `PHY_DEV` interface defined in the Virtual Network template, or `local_ip` to route the traffic using the first IP configured in `PHY_DEV`.
3. Finally you may want to add the `nolearning` option to the VXLAN link.

```

# Multicast protocol for multi destination BUM traffic. Options:
#   - multicast, for IP multicast
#   - evpn, for BGP EVPN control plane
:vxlan_mode: evpn

# Tunnel endpoint communication type. Only for evpn vxlan_mode.
#   - dev, tunnel endpoint communication is sent to PHYDEV
#   - local_ip, first ip addr of PHYDEV is used as address for the communication
:vxlan_tep: local_ip

# Additional ip link options, uncomment the following to disable learning for
# EVPN mode
:ip_link_conf:
  :nolearning:

```

After updating the configuration file do not forget to run `onehost sync -f` to distribute the changes.

9.6 Open vSwitch Networks

This guide describes how to use the [Open vSwitch](#) network drivers. They provide network isolation using VLANs by tagging ports and basic network filtering using OpenFlow. Other traffic attributes that may be configured through Open vSwitch are not modified.

The VLAN id will be the same for every interface in a given network, calculated automatically by OpenNebula. It may also be forced by specifying an `VLAN_ID` parameter in the Virtual Network template.

Warning: This driver is not compatible with Security Groups.

9.6.1 OpenNebula Configuration

The `VLAN_ID` is calculated according to this configuration option of `oned.conf`:

```
# VLAN_IDS: VLAN ID pool for the automatic VLAN_ID assignment. This pool
# is for 802.1Q networks (Open vSwitch and 802.1Q drivers). The driver
# will try first to allocate VLAN_IDS[START] + VNET_ID
# start: First VLAN_ID to use
# reserved: Comma separated list of VLAN_IDS or ranges. Two numbers
# separated by a colon indicate a range.

VLAN_IDS = [
    START      = "2",
    RESERVED   = "0, 1, 4095"
]
```

By modifying that parameter you can reserve some VLANs so they aren't assigned to a Virtual Network. You can also define the first `VLAN_ID`. When a new isolated network is created, OpenNebula will find a free `VLAN_ID` from the `VLAN` pool. This pool is global, and it's also shared with the [802.1Q VLAN](#) network mode.

The following configuration attributes can be adjusted in `/var/lib/one/remotes/etc/vnm/OpenNebulaNetwork.conf`:

Parameter	Description
<code>arp_cache_poisoning</code>	Enable ARP Cache Poisoning Prevention Rules (effective only if Virtual Network IP/MAC spoofing filters are enabled).
<code>keep_empty_bridge</code>	Set to true to preserve bridges with no virtual interfaces left.
<code>ovs_bridge_conf</code>	Hash Options for Open vSwitch bridge creation

Note: Remember to run `onehost sync` to deploy the file to all the nodes.

9.6.2 Defining an Open vSwitch Network

To create an Open vSwitch network, include the following information:

Attribute	Value	Mandatory
VN_MAD	ovswitch	YES
PHYDEV	Name of the physical network device that will be attached to the bridge	NO
BRIDGE	Name of the Open vSwitch bridge to use	YES
VLAN_ID	The VLAN ID. If this attribute is not defined a VLAN ID will be generated if AUTOMATIC_VLAN_ID is set to YES.	NO
AUTO-MATIC_VLAN_ID	If VLAN_ID has been defined, this attribute is ignored. Set to YES if you want OpenNebula to generate an automatic VLAN ID.	NO

The following example defines an Open vSwitch network

```
NAME      = "ovswitch_net"
VN_MAD   = "ovswitch"
BRIDGE   = vbr1
VLAN_ID  = 50 # optional
...
```

Multiple VLANs (VLAN trunking)

VLAN trunking is also supported by adding the following tag to the NIC element in the VM template or to the virtual network template:

- **VLAN_TAGGED_ID**: Specify a range of VLANs to tag, for example: 1,10,30,32,100-200.

9.6.3 Using Open vSwitch on VXLAN Networks

This section describes how to use [Open vSwitch](#) on VXLAN networks. To use VXLAN you need to use a specialized version of the Open vSwitch driver that incorporates the features of the [VXLAN](#) driver. It's necessary to be familiar with these two drivers, their configuration options, benefits, and drawbacks.

The VXLAN overlay network is used as a base with the Open vSwitch (instead of regular Linux bridge) on top. Traffic on the lowest level is isolated by the VXLAN encapsulation protocol, and Open vSwitch still allows to use the second level isolation by 802.1Q VLAN tags **inside the encapsulated traffic**. Main isolation is always provided by VXLAN, not 802.1Q VLANs. If 802.1Q is required to isolate the VXLAN, the driver needs to be configured with user-created 802.1Q tagged physical interface.

This hierarchy is important to understand.

OpenNebula Configuration

There is no configuration specific to this driver, except the options specified above and in the [VXLAN guide](#).

Defining an Open vSwitch - VXLAN Network

To create a network include the following information:

Attribute	Value	Mandatory
VN_MAD	ovswitch_vxlan	YES
PHYDEV	Name of the physical network device that will be attached to the bridge.	YES
BRIDGE	Name of the Open vSwitch bridge to use	NO
OUTER_VLAN_ID	The outer VXLAN network ID.	NO
AUTO-MATIC_OUTER_VLAN_ID	If OUTER_VLAN_ID has been defined, this attribute is ignored. Set to YES if you want OpenNebula to generate an automatic ID.	NO
VLAN_ID	The inner 802.1Q VLAN ID. If this attribute is not defined a VLAN ID will be generated if AUTOMATIC_VLAN_ID is set to YES.	NO
AUTO-MATIC_VLAN_ID	If VLAN_ID has been defined, this attribute is ignored. Set to YES if you want OpenNebula to generate an automatic VLAN ID.	NO
MTU	The MTU for the VXLAN interface and bridge	NO

The following example defines an Open vSwitch network

```
NAME      = "ovsvx_net"
VN_MAD   = "ovswitch_vxlan"
PHYDEV   = eth0
BRIDGE   = ovsvxbr0.10000
OUTER_VLAN_ID = 10000 # VXLAN VNI
VLAN_ID  = 50          # optional
...
```

In this scenario, the driver will check for the existence of bridge ovsvxbr0.10000. If it doesn't exist, it will be created. Also, the VXLAN interface eth0.10000 will be created and attached to the Open vSwitch bridge ovsvxbr0.10000. When a virtual machine is instantiated, its bridge ports will be tagged with 802.1Q VLAN 50.

9.6.4 Open vSwitch with DPDK

This section describes how to use a DPDK datapath with the Open vSwitch drivers. When using the DPDK backend, the OpenNebula drivers will automatically configure the bridges and ports accordingly.

Warning: This section is only relevant for KVM guests

Requirements & Limitations

Please consider the following when using the DPDK datapath for Open vSwitch:

- An Open vSwitch version compiled with DPDK support is required.
- This mode cannot be combined with non-DPDK switches.
- The VMs need to use the virtio interface for its NICs.
- Although not needed to make it work, you'd probably be interested in configuring NUMA pinning and hugepages in your hosts. You can read more here.

OpenNebula Configuration

Follow these steps to configure OpenNebula:

- **Select the DPDK backend for the switches.** Edit the configuration of the openvswitch driver in `/etc/one/oned.conf` to read:

```
VN_MAD_CONF = [
    NAME = "ovswitch",
    BRIDGE_TYPE = "openvswitch_dpdk"
]
```

After making this change you need to restart OpenNebula

- **Set the datapath type for the bridges.** Edit the bridge configuration options in `/var/lib/one/remotes/etc/OpenNebulaNetwork.conf`:

```
:ovs_bridge_conf:
  :datapath_type: netdev
```

After making this change you need to synchronize the changes with your hosts using the `onehost sync` command.

Note that the sockets used by the vhost interface are created in the VM directory (`/var/lib/one/datastores/<ds_id>/<vm_id>`) and named after the switch port.

Using DPDK in your Virtual Networks

There are no additional changes, simply:

- Create your networks using the `ovswitch` driver, *see above*.
- Make sure that the NIC model is set to `virtio`. This setting can be added as a default in `/etc/one/vmm_exec/vmm_exec_kvm.conf`.

You can verify that the VMs are using the vhost interface by looking at their domain definition in the host. You should see something like:

```
<domain type='kvm' id='417'>
  <name>one-10</name>
  ...
  <devices>
    ...
    <interface type='vhostuser'>
      <mac address='02:00:c0:a8:7a:02' />
      <source type='unix' path='/var/lib/one//datastores/0/10/one-10-0' mode='server' />
      <target dev='one-10-0' />
      <model type='virtio' />
      <alias name='net0' />
      <address type='pci' domain='0x0000' bus='0x00' slot='0x03' function='0x0' />
    </interface>
    ...
  </devices>
</domain>
```

And the associated port in the bridge using the qemu vhost interface:

```
Bridge br0
  Port "one-10-0"
    Interface "one-10-0"
      type: dpdkvhostuserclient
      options: {vhost-server-path="/var/lib/one//datastores/0/10/one-10-0"}
```

REFERENCES

10.1 Overview

This Chapter covers references that apply to the configuration of OpenNebula to interact smoothly and efficiently with other datacenter components, as well as information on where are the log files, the database tool, and all the configuration parameters of the OpenNebula core daemon.

10.1.1 How Should I Read This Chapter

The *oned.conf* file is the main OpenNebula configuration file, and it is essential for tweaking the performance and behavior of your OpenNebula installation. The section *Large Deployments* contains more helpful pointers to tune the OpenNebula performance.

Read *Logging and Debugging* for a complete reference on how to use log files, and how to adjust the verbosity and log subsystem.

For database maintenance operations, use the *command line tool onedb*. It can be used to get information from an OpenNebula database, upgrade it, or fix inconsistency problems.

10.1.2 Hypervisor Compatibility

This chapter applies to all the hypervisors.

10.2 ONED Configuration

The OpenNebula daemon `oned` manages the cluster nodes, virtual networks, virtual machines, users, groups and storage datastores. The configuration file for the daemon is called `oned.conf` and it is placed inside the `/etc/one` directory. In this reference document we describe all the format and options that can be specified in `oned.conf`.

10.2.1 Daemon Configuration Attributes

- `MANAGER_TIMER`: Time in seconds the core uses to evaluate periodical functions. `MONITORING_INTERVAL` cannot have a smaller value than `MANAGER_TIMER`.
- `MONITORING_INTERVAL_HOST`: Time in seconds between each HOST monitoring cycle.
- `MONITORING_INTERVAL_VM`: Time in seconds between each VM monitoring cycle.
- `MONITORING_INTERVAL_DATASTORE`: Time in seconds between each DATASTORE monitoring cycle.

- MONITORING_INTERVAL_MARKET: Time in seconds between each MARKETPLACE monitoring cycle.
- MONITORING_INTERVAL_DB_UPDATE: Time in seconds between DB writes of VM monitoring information. -1 to disable DB updating and 0 to write every update.
- DS_MONITOR_VM_DISK: Number of MONITORING_INTERVAL_DATASTORE intervals to monitor VM disks. 0 to disable. Only applies to fs and fs_lvm datastores.
- MONITORING_THREADS: Maximum number of threads used to process monitor messages.
- HOST_PER_INTERVAL: Number of hosts monitored in each interval.
- HOST_MONITORING_EXPIRATION_TIME: Time, in seconds, to expire monitoring information. Use 0 to disable HOST monitoring recording.
- VM_INDIVIDUAL_MONITORING: VM monitoring information is normally obtained along with the host information. Set this TO "YES" if you use a custom monitor driver that needs to activate the VM monitoring process separately.
- VM_PER_INTERVAL: Number of VMs monitored in each interval.
- VM_MONITORING_EXPIRATION_TIME: Time, in seconds, to expire monitoring information. Use 0 to disable VM monitoring recording.
- SCRIPTS_REMOTE_DIR: Remote path to store the monitoring and VM management script.
- PORT: Port where oned will listen for XML-RPC calls.
- LISTEN_ADDRESS: Host IP to listen on for XML-RPC calls (default: all IPs).
- DB: Vector of configuration attributes for the database back-end.
 - backend: Set to `sqlite` or `mysql`. Please visit the [MySQL configuration guide](#) for more information.
 - server (MySQL only): Host name or IP address of the MySQL server.
 - user (MySQL only): MySQL user's login ID.
 - passwd (MySQL only): MySQL user's password.
 - db_name (MySQL only): MySQL database name.
 - connections (MySQL only): maximum number of connections to the MySQL server.
- VNC_PORTS: VNC port pool for automatic VNC port assignment. If possible, the port will be set to START + VMID. Refer to the VM template reference for further information:
 - start: First port to assign.
 - reserved: Comma-separated list of reserved ports or ranges. Two numbers separated by a colon indicate a range.
- VM_SUBMIT_ON_HOLD: Forces VMs to be created on hold state instead of pending. Values: YES or NO.
- API_LIST_ORDER: Sets order (by ID) of elements in list API calls (e.g. `onevm list`). Values: ASC (ascending order) or DESC (descending order).
- LOG: Configure the logging system
 - SYSTEM: Can be either `file` (default), `syslog` or `std`
 - DEBUG_LEVEL: Sets the verbosity of the log messages. Possible values are:

DEBUG_LEVEL	Meaning
0	ERROR
1	WARNING
2	INFO
3	DEBUG

Example of this section:

```
#*****
# Daemon configuration attributes
#*****

LOG = [
    SYSTEM      = "file",
    DEBUG_LEVEL = 3
]

#MANAGER_TIMER = 15

MONITORING_INTERVAL_HOST = 180
MONITORING_INTERVAL_VMS  = 180
MONITORING_INTERVAL_DATASTORE = 300
MONITORING_INTERVAL_MARKET   = 600

MONITORING_THREADS = 50
#DS_MONITOR_VM_DISK           = 10
#HOST_PER_INTERVAL            = 15
#HOST_MONITORING_EXPIRATION_TIME = 43200

#VM_INDIVIDUAL_MONITORING     = "no"
#VM_PER_INTERVAL               = 5
#VM_MONITORING_EXPIRATION_TIME = 14400

SCRIPTS_REMOTE_DIR=/var/tmp/one

PORT = 2633

LISTEN_ADDRESS = "0.0.0.0"

DB = [ BACKEND = "sqlite" ]

# Sample configuration for MySQL
# DB = [ BACKEND = "mysql",
#        SERVER = "localhost",
#        PORT   = 0,
#        USER   = "oneadmin",
#        PASSWD = "oneadmin",
#        DB_NAME = "opennebula",
#        CONNECTIONS = 50 ]

VNC_PORTS = [
    START      = 5900
#    RESERVED = "6800, 6801, 9869"
]

#VM_SUBMIT_ON_HOLD = "NO"
#API_LIST_ORDER     = "DESC"
```

```
... _oned_conf_federation:
```

10.2.2 Federation Configuration Attributes

Control the federation capabilities of oned. Operation in a federated setup requires a special DB configuration.

- **FEDERATION:** Federation attributes.
 - **MODE:** Operation mode of this oned.
 - * **STANDALONE:** Not federated. This is the default operational mode.
 - * **MASTER:** This oned is the master zone of the federation.
 - * **SLAVE:** This oned is a slave zone.
- **ZONE_ID:** The zone ID, as returned by the `onezone` command.
- **MASTER_ONED:** The XML-RPC endpoint of the master oned, e.g. `http://master.one.org:2633/RPC2`.

```
# ****
# Federation configuration attributes
# ****

FEDERATION = [
    MODE = "STANDALONE",
    ZONE_ID = 0,
    MASTER_ONED = ""
]
```

10.2.3 Raft Configuration Attributes

Opennebula uses the Raft algorithm. It can be tuned by several parameters in the configuration file `/etc/one/oned.conf`. The following options are available:

- **LIMIT_PURGE:** Number of DB log records that will be deleted on each purge.
- **LOG_RETENTION:** Number of DB log records kept. It determines the synchronization window across servers and extra storage space needed.
- **LOG_PURGE_TIMEOUT:** How often applied records are purged according to the log retention value (in seconds).
- **ELECTION_TIMEOUT_MS:** Timeout to start an election process if no heartbeat or log is received from the leader (in milliseconds).
- **BROADCAST_TIMEOUT_MS:** How often heartbeats are sent to followers (in milliseconds).
- **XMLRPC_TIMEOUT_MS:** Timeout for Raft-related API calls (in milliseconds). For an infinite timeout, set this value to 0.

```
RAFT = [
    LIMIT_PURGE      = 100000,
    LOG_RETENTION    = 500000,
    LOG_PURGE_TIMEOUT = 600,
    ELECTION_TIMEOUT_MS = 2500,
    BROADCAST_TIMEOUT_MS = 500,
```

```

XMLRPC_TIMEOUT_MS      = 450
]

```

10.2.4 Default Showback Cost

The following attributes define the default cost for Virtual Machines that don't have a CPU, MEMORY or DISK cost. This is used by the oneshowback calculate method.

```

#*****
# Default showback cost
#***** 

DEFAULT_COST = [
    CPU_COST     = 0,
    MEMORY_COST  = 0,
    DISK_COST    = 0
]

```

10.2.5 XML-RPC Server Configuration

- MAX_CONN: Maximum number of simultaneous TCP connections the server will maintain
- MAX_CONN_BACKLOG: Maximum number of TCP connections the operating system will accept on the server's behalf without the server accepting them from the operating system
- KEEPALIVE_TIMEOUT: Maximum time in seconds that the server allows a connection to be open between RPCs
- KEEPALIVE_MAX_CONN: Maximum number of RPCs that the server will execute on a single connection
- TIMEOUT: Maximum time in seconds the server will wait for the client to do anything while processing an RPC. This timeout will also be used when a proxy calls to the master in a federation.
- RPC_LOG: Create a separate log file for XML-RPC requests, in /var/log/one/one_xmlrpc.log.
- MESSAGE_SIZE: Buffer size in bytes for XML-RPC responses.
- LOG_CALL_FORMAT: Format string to log XML-RPC calls. Interpreted strings:
 - %i – request id
 - %m – method name
 - %u – user id
 - %U – user name
 - %l [number] – parameter list and number of characters (optional) to print each parameter, default is 20.
Example: %l300
 - %p – user password
 - %g – group id
 - %G – group name
 - %a – auth token
 - %% – %

```
*****  
# XML-RPC server configuration  
*****  
  
#MAX_CONN          = 15  
#MAX_CONN_BACKLOG = 15  
#KEEPALIVE_TIMEOUT = 15  
#KEEPALIVE_MAX_CONN = 30  
#TIMEOUT           = 15  
#RPC_LOG            = NO  
#MESSAGE_SIZE       = 1073741824  
#LOG_CALL_FORMAT    = "Req:%i UID:%u %m invoked %l"
```

Warning: This functionality is only available when compiled with xmlrpc-c libraries >= 1.32. Currently only the packages distributed by OpenNebula are linked with this library.

10.2.6 Virtual Networks

- **NETWORK_SIZE**: Here you can define the default size for the virtual networks
 - **MAC_PREFIX**: Default MAC prefix to be used to create the auto-generated MAC addresses. (This can be overwritten by the Virtual Network template.)
 - **VLAN_IDS**: VLAN ID pool for the automatic VLAN_ID assignment. This pool is for 802.1Q networks (Open vSwitch and 802.1Q drivers). The driver will try first to allocate VLAN_IDS[START] + VNET_ID
 - **start**: First VLAN_ID to use
 - **reserved**: Comma-separated list of VLAN_IDs or ranges. Two numbers separated by a colon indicate a range.
 - **VXLAN_IDS**: Automatic VXLAN Network ID (VNI) assignment. This is used for vxlan networks.
 - **start**: First VNI to use
-
- Note:** reserved is not supported by this pool

Sample configuration:

```
*****  
# Physical Networks configuration  
*****  
  
NETWORK_SIZE = 254  
  
MAC_PREFIX   = "02:00"  
  
VLAN_IDS = [  
    START     = "2",  
    RESERVED = "0, 1, 4095"  
]  
  
VXLAN_IDS = [  
    START = "2"  
]
```

10.2.7 Datastores

The *Storage Subsystem* allows users to set up images, which can be operating systems or data, to be used in Virtual Machines easily. These images can be used by several Virtual Machines simultaneously, and also shared with other users.

Here you can configure the default values for the Datastores and Image templates. There is more information about the template syntax here.

- **DATASTORE_LOCATION:** Path for Datastores. It is the same for all the hosts and front-end. It defaults to `/var/lib/one/datastores` (or in self-contained mode defaults to `$ONE_LOCATION/var/datastores`). Each datastore has its own directory (called `BASE_PATH`) of the form: `$DATASTORE_LOCATION/<datastore_id>`. You can symlink this directory to any other path, if needed. `BASE_PATH` is generated from this attribute each time oned is started.
- **DATASTORE_CAPACITY_CHECK:** Check that there is enough capacity before creating a new image. Defaults to Yes.
- **DEFAULT_IMAGE_TYPE:** Default value for TYPE field when it is omitted in a template. Values accepted are:
 - OS: Image file holding an operating system
 - CDROM: Image file holding a CDROM
 - DATABLOCK: Image file holding a datablock, created as an empty block
- **DEFAULT_DEVICE_PREFIX:** Default value for the DEV_PREFIX field when it is omitted in a template. The missing `DEV_PREFIX` attribute is filled when Images are created, so changing this prefix won't affect existing Images. It can be set to:

Prefix	Device type
hd	IDE
sd	SCSI
vd	KVM virtual disk

- **DEFAULT_CDROM_DEVICE_PREFIX:** Same as above but for CDROM devices.
- **DEFAULT_IMAGE_PERSISTENT:** Control the default value for the PERSISTENT attribute on image cloning or saving (`oneimage clone`, `onevm disk-saveas`). If omitted, images will inherit the PERSISTENT attribute from the base image.
- **DEFAULT_IMAGE_PERSISTENT_NEW:** Control the default value for the PERSISTENT attribute on image creation (`oneimage create`). By default images are not persistent if this is not set.

More information on the image repository can be found in the Managing Virtual Machine Images guide.

Sample configuration:

```
#*****
# Image Repository Configuration
#*****
#DATASTORE_LOCATION = /var/lib/one/datastores

DATASTORE_CAPACITY_CHECK = "yes"

DEFAULT_IMAGE_TYPE = "OS"
DEFAULT_DEVICE_PREFIX = "hd"

DEFAULT_CDROM_DEVICE_PREFIX = "hd"
```

```
#DEFAULT_IMAGE_PERSISTENT      = ""
#DEFAULT_IMAGE_PERSISTENT_NEW = "NO"
```

10.2.8 Information Collector

This driver **cannot be assigned to a host**, and needs to be used with KVM drivers. Options that can be set:

- **-a**: Address to bind the collectd socket (default 0.0.0.0)
- **-p**: UDP port to listen for monitor information (default 4124)
- **-f**: Interval in seconds to flush collected information (default 5)
- **-t**: Number of threads for the server (default 50)
- **-i**: Time in seconds of the monitoring push cycle. This parameter must be smaller than MONITORING_INTERVAL, otherwise push monitoring will not be effective.

Sample configuration:

```
IM_MAD = [
    name      = "collectd",
    executable = "collectd",
    arguments  = "-p 4124 -f 5 -t 50 -i 20" ]
```

10.2.9 Information Drivers

The information drivers are used to gather information from the cluster nodes, and they depend on the virtualization you are using. You can define more than one information manager, but make sure they have different names. To define one, the following need to be set:

- **name**: name for this information driver.
- **executable**: path of the information driver executable as an absolute path or relative to /usr/lib/one/mads/
- **arguments**: for the driver executable, usually a probe configuration file as an absolute path or relative to /etc/one/.

For more information on configuring the information and monitoring system and hints to extend it, please check the information driver configuration guide.

Sample configuration:

```
#-----
#  KVM UDP-push Information Driver Manager Configuration
#      -r number of retries when monitoring a host
#      -t number of threads, i.e. number of hosts monitored at the same time
#-----
IM_MAD = [
    NAME      = "kvm",
    SUNSTONE_NAME = "KVM",
    EXECUTABLE = "one_im_ssh",
    ARGUMENTS  = "-r 3 -t 15 kvm" ]
#-----
```

10.2.10 Virtualization Drivers

The virtualization drivers are used to create, control and monitor VMs on the hosts. You can define more than one virtualization driver (e.g. you have different virtualizers in several hosts) but make sure they have different names. To define one, the following need to be set:

- **NAME**: name of the virtualization driver
- **SUNSTONE_NAME**: name displayed in Sunstone
- **EXECUTABLE**: path of the virtualization driver executable as an absolute path or relative to `/usr/lib/one/mads/`
- **ARGUMENTS**: for the driver executable
- **TYPE**: driver type; supported drivers: xen, kvm or xml
- **DEFAULT**: file containing default values and configuration parameters for the driver as an absolute path or relative to `/etc/one/`
- **KEEP_SNAPSHOTS**: do not remove snapshots on power on/off cycles and live migrations if the hypervisor supports that
- **IMPORTED_VMS_ACTIONS**: comma-separated list of actions supported for imported VMs. The available actions are:
 - migrate
 - live-migrate
 - terminate
 - terminate-hard
 - undeploy
 - undeploy-hard
 - hold
 - release
 - stop
 - suspend
 - resume
 - delete
 - delete-recreate
 - reboot
 - reboot-hard
 - resched
 - unresched
 - poweroff
 - poweroff-hard
 - disk-attach
 - disk-detach
 - nic-attach

- nic-detach
- snap-create
- snap-delete

For more information on configuring and setting up the Virtual Machine Manager Driver please check the section that suits you:

- [KVM Driver](#)
- [vCenter Driver](#)

Sample configuration:

```
#-----
# Virtualization Driver Configuration
#-----

VM_MAD = [
    NAME      = "kvm",
    SUNSTONE_NAME = "KVM",
    EXECUTABLE = "one_vmm_exec",
    ARGUMENTS  = "-t 15 -r 0 kvm",
    DEFAULT    = "vmm_exec/vmm_exec_kvm.conf",
    TYPE       = "kvm",
    KEEP_SNAPSHOTS = "no",
    IMPORTED_VMS_ACTIONS = "terminate, terminate-hard, hold, release, suspend,
                             resume, delete, reboot, reboot-hard, resched, unresched, disk-attach,
                             disk-detach, nic-attach, nic-detach, snap-create, snap-delete"
]
```

10.2.11 Transfer Driver

The transfer drivers are used to transfer, clone, remove and create VM images. The default TM_MAD driver includes plugins for all supported storage modes. You may need to modify the TM_MAD to add custom plugins.

- **EXECUTABLE:** path of the transfer driver executable, as an absolute path or relative to /usr/lib/one/mads/
- **ARGUMENTS:** for the driver executable:
 - **-t:** number of threads, i.e. number of transfers made at the same time
 - **-d:** list of transfer drivers separated by commas. If not defined all the drivers available will be enabled

For more information on configuring different storage alternatives *please check the storage configuration guide*.

Sample configuration:

```
#-----
# Transfer Manager Driver Configuration
#-----

TM_MAD = [
    EXECUTABLE = "one_tm",
    ARGUMENTS  = "-t 15 -d dummy,lvm,shared,fs_lvm,qcow2,ssh,ceph,dev,vcenter,iscsi_
                  libvirt"
]
```

The configuration for each driver is defined in the TM_MAD_CONF section. These values are used when creating a new datastore and should not be modified since they define the datastore behavior.

- **NAME:** name of the transfer driver, listed in the `-d` option of the TM_MAD section
- **LN_TARGET:** determines how persistent images will be cloned when a new VM is instantiated:
 - **NONE:** The image will be linked, and no more storage capacity will be used
 - **SELF:** The image will be cloned in the Images datastore
 - **SYSTEM:** The image will be cloned in the System datastore
- **CLONE_TARGET:** determines how non-persistent images will be cloned when a new VM is instantiated:
 - **NONE:** The image will be linked, and no more storage capacity will be used
 - **SELF:** The image will be cloned in the Images datastore
 - **SYSTEM:** The image will be cloned in the System datastore
- **SHARED:** determines if the storage holding the system datastore is shared among the different hosts or not. Valid values: **yes** or **no**.
- **DS_MIGRATE:** set to YES if system datastore migrations are allowed for this TM. Only useful for system datastore TMs.
- **ALLOW_ORPHANS:** Whether snapshots can live without parents. It allows three values: YES, NO and MIXED. The last mode, MIXED, allows creating orphan snapshots, but taking into account some dependencies which can appear after a revert snapshot action on Ceph datastores.

Sample configuration:

```
TM_MAD_CONF = [
    name      = "lvm",
    ln_target = "NONE",
    clone_target = "SELF",
    shared    = "yes",
    allow_orphans = "no"
]

TM_MAD_CONF = [
    name      = "shared",
    ln_target = "NONE",
    clone_target = "SYSTEM",
    shared    = "yes",
    ds_migrate = "yes"
]
```

10.2.12 Datastore Driver

The Datastore Driver defines a set of scripts to manage the storage backend.

- **EXECUTABLE:** path of the transfer driver executable as an absolute path or relative to `/usr/lib/one/mads/`
- **ARGUMENTS:** for the driver executable
 - **-t** number of threads, i.e. number of simultaneous repo operations
 - **-d** datastore MADs, separated by commas
 - **-s** system datastore TM drivers, used to monitor shared system DS

Sample configuration:

```
DATASTORE_MAD = [
    EXECUTABLE = "one_datastore",
    ARGUMENTS  = "-t 15 -d dummy,fs,lvm,ceph,dev,iscsi_libvirt,vcenter -s shared,ssh,
    ↪ceph,fs_lvm"
]
```

For more information on this driver and how to customize it, please visit [its reference guide](#).

10.2.13 Marketplace Driver Configuration

Drivers to manage different marketplaces, specialized for the storage back-end

- **EXECUTABLE:** path of the transfer driver executable as an absolute path or relative to /usr/lib/one/mads/
- **ARGUMENTS:** for the driver executable:
 - **-t** number of threads, i.e. number of simultaneous repo operations
 - **-m** marketplace mads separated by commas
 - **--proxy** proxy URI, if required to access the internet. For example --proxy http://1.2.3.4:5678
 - **-w** timeout in seconds to execute external commands (default unlimited)

Sample configuration:

```
MARKET_MAD = [
    EXECUTABLE = "one_market",
    ARGUMENTS  = "-t 15 -m http,s3,one"
]
```

10.2.14 Hook System

Hooks in OpenNebula are programs (usually scripts) whose execution is triggered by a change in state in Virtual Machines or Hosts. The hooks can be executed either locally or remotely to the node where the VM or Host is running. To configure the Hook System the following need to be set in the OpenNebula configuration file:

- **EXECUTABLE:** path of the hook driver executable as an absolute path or relative to /usr/lib/one/mads/
- **ARGUMENTS:** for the driver executable as an absolute path or relative to /etc/one/

Sample configuration:

```
HM_MAD = [
    executable = "one_nm" ]
```

Virtual Machine Hooks (VM_HOOK) defined by:

- **NAME:** for the hook; useful to track the hook (OPTIONAL).
- **ON:** when the hook should be executed:
 - **CREATE:** when the VM is created (onevm create)
 - **PROLOG:** when the VM is in the prolog state

- **RUNNING**: after the VM is successfully booted
- **UNKNOWN**: when the VM is in the unknown state
- **SHUTDOWN**: after the VM is shutdown
- **STOP**: after the VM is stopped (including VM image transfers)
- **DONE**: after the VM is deleted or shutdown
- **CUSTOM**: user defined specific STATE and LCM_STATE combination of states to trigger the hook
- **COMMAND**: as an absolute path or relative to `/usr/share/one/hooks`
- **ARGUMENTS**: for the hook. You can substitute VM information with:
 - **\$ID**: the ID of the virtual machine
 - **\$TEMPLATE**: the VM template as base64-encoded XML
 - **PREV_STATE**: the previous STATE of the Virtual Machine
 - **PREV_LCM_STATE**: the previous LCM STATE of the Virtual Machine
- **REMOTE**: values:
 - **YES**: The hook is executed in the host where the VM was allocated
 - **NO**: The hook is executed in the OpenNebula server (default)

Host Hooks (HOST_HOOK) defined by:

- **NAME**: for the hook, useful to track the hook (OPTIONAL)
- **ON**: when the hook should be executed,
 - **CREATE**: when the Host is created (`onehost create`)
 - **ERROR**: when the Host enters the error state
 - **DISABLE**: when the Host is disabled
- **COMMAND**: as an absolute path or relative to `/usr/share/one/hooks`
- **ARGUMENTS**: for the hook. You can use the following Host information:
 - **\$ID**: the ID of the host
 - **\$TEMPLATE**: the Host template as base64-encoded XML
- **REMOTE**: values,
 - **YES**: The hook is executed in the host
 - **NO**: The hook is executed in the OpenNebula server (default)

Sample configuration:

```
VM_HOOK = [
    name      = "advanced_hook",
    on        = "CUSTOM",
    state     = "ACTIVE",
    lcm_state = "BOOT_UNKNOWN",
    command   = "log.rb",
    arguments = "$ID $PREV_STATE $PREV_LCM_STATE" ]
```

10.2.15 Auth Manager Configuration

- **AUTH_MAD:** The *driver* that will be used to authenticate and authorize OpenNebula requests. If not defined, OpenNebula will use the built-in auth policies.
 - **EXECUTABLE:** path of the auth driver executable as an absolute path or relative to /usr/lib/one/mads/
 - **AUTHN:** list of authentication modules, separated by commas. If not defined, all the modules available will be enabled
 - **AUTHZ:** list of authorization modules, separated by commas
- **SESSION_EXPIRATION_TIME:** Time in seconds for which an authenticated token is valid. During this time the driver is not used. Use 0 to disable session caching.
- **ENABLE_OTHER_PERMISSIONS:** Whether or not to enable the permissions for ‘other’. Users in the oneadmin group will still be able to change these permissions. Values: YES or NO.
- **DEFAULT_UMASK:** Similar to Unix umask. Sets the default resource permissions. Its format must be 3 octal digits. For example a umask of 137 will set the new object’s permissions to 640 um- u-- ---.

Sample configuration:

```
AUTH_MAD = [
    executable = "one_auth_mad",
    authn = "ssh,x509,ldap,server_cipher,server_x509"
]

SESSION_EXPIRATION_TIME = 900

#ENABLE_OTHER_PERMISSIONS = "YES"

DEFAULT_UMASK = 177
```

The DEFAULT_AUTH can be used to point to the desired default authentication driver, for example ldap:

```
DEFAULT_AUTH = "ldap"
```

10.2.16 VM Operations Permissions

The following parameters define the operations associated with the ADMIN, MANAGE and USE permissions. Note that some VM operations may require additional permissions on other objects. Also some operations refer to a class of actions:

- disk-snapshot: includes create, delete and revert actions
- disk-attach: includes attach and detach actions
- nic-attach: includes attach and detach actions
- snapshot: includes create, delete and revert actions
- resched: includes resched and unresched actions

The list and show operations require USE permission; this is not configurable.

In the following example you need ADMIN rights on a VM to perform migrate, delete, recover... while undeploy, hold, ... need MANAGE rights:

```

VM_ADMIN_OPERATIONS = "migrate, delete, recover, retry, deploy, resched"
VM_MANAGE_OPERATIONS = "undeploy, hold, release, stop, suspend, resume, reboot,
    poweroff, disk-attach, nic-attach, disk-snapshot, terminate, disk-resize,
    snapshot, updateconf, rename, resize, update, disk-saveas"
VM_USE_OPERATIONS = ""

```

10.2.17 Restricted Attributes Configuration

Users outside the oneadmin group won't be able to instantiate templates created by users outside the "oneadmin" group that include attributes restricted by:

- **VM_RESTRICTED_ATTR**: Virtual Machine attribute to be restricted for users outside the oneadmin group
- **IMAGE_RESTRICTED_ATTR**: Image attribute to be restricted for users outside the oneadmin group
- **VNET_RESTRICTED_ATTR**: Virtual Network attribute to be restricted for users outside the oneadmin group when updating a reservation. These attributes are not considered for regular VNET creation.

If the VM template has been created by admins in the oneadmin group, then users outside the oneadmin group **can** instantiate these templates.

Sample configuration:

```

VM_RESTRICTED_ATTR = "CONTEXT/FILES"
VM_RESTRICTED_ATTR = "NIC/MAC"
VM_RESTRICTED_ATTR = "NIC/VLAN_ID"
VM_RESTRICTED_ATTR = "NIC/BRIDGE"
VM_RESTRICTED_ATTR = "NIC_DEFAULT/MAC"
VM_RESTRICTED_ATTR = "NIC_DEFAULT/VLAN_ID"
VM_RESTRICTED_ATTR = "NIC_DEFAULT/BRIDGE"
VM_RESTRICTED_ATTR = "DISK/TOTAL_BYTES_SEC"
VM_RESTRICTED_ATTR = "DISK/READ_BYTES_SEC"
VM_RESTRICTED_ATTR = "DISK/WRITE_BYTES_SEC"
VM_RESTRICTED_ATTR = "DISK/TOTAL_IOPS_SEC"
VM_RESTRICTED_ATTR = "DISK/READ_IOPS_SEC"
VM_RESTRICTED_ATTR = "DISK/WRITE_IOPS_SEC"
#VM_RESTRICTED_ATTR = "DISK/SIZE"
VM_RESTRICTED_ATTR = "DISK/ORIGINAL_SIZE"
VM_RESTRICTED_ATTR = "CPU_COST"
VM_RESTRICTED_ATTR = "MEMORY_COST"
VM_RESTRICTED_ATTR = "DISK_COST"
VM_RESTRICTED_ATTR = "PCI"
VM_RESTRICTED_ATTR = "USER_INPUTS"

#VM_RESTRICTED_ATTR = "RANK"
#VM_RESTRICTED_ATTR = "SCHED_RANK"
#VM_RESTRICTED_ATTR = "REQUIREMENTS"
#VM_RESTRICTED_ATTR = "SCHED_REQUIREMENTS"

IMAGE_RESTRICTED_ATTR = "SOURCE"

VNET_RESTRICTED_ATTR = "VN_MAD"
VNET_RESTRICTED_ATTR = "PHYDEV"
VNET_RESTRICTED_ATTR = "VLAN_ID"
VNET_RESTRICTED_ATTR = "BRIDGE"

```

```
VNET_RESTRICTED_ATTR = "AR/VN_MAD"
VNET_RESTRICTED_ATTR = "AR/PHYDEV"
VNET_RESTRICTED_ATTR = "AR/VLAN_ID"
VNET_RESTRICTED_ATTR = "AR/BRIDGE"
```

OpenNebula evaluates these attributes:

- on VM template instantiate (`onetemplate instantiate`)
- on VM create (`onevm create`)
- on VM attach NIC (`onevm nic-attach`), for example, to prevent using NIC/MAC

10.2.18 Encrypted Attributes Configuration

These attributes are encrypted and decrypted by the OpenNebula core. The supported attributes are:

- **CLUSTER_ENCRYPTED_ATTR**
- **DATASTORE_ENCRYPTED_ATTR**
- **HOST_ENCRYPTED_ATTR**
- **VM_ENCRYPTED_ATTR**: these attributes apply also to the user template.
- **VNET_ENCRYPTED_ATTR**: these attributes apply also to address ranges which belong to the virtual network.

Sample configuration:

```
CLUSTER_ENCRYPTED_ATTR = "PROVISION/PACKET_TOKEN"

DATASTORE_ENCRYPTED_ATTR = "PROVISION/PACKET_TOKEN"

HOST_ENCRYPTED_ATTR = "EC2_ACCESS"
HOST_ENCRYPTED_ATTR = "EC2_SECRET"
HOST_ENCRYPTED_ATTR = "AZ_ID"
HOST_ENCRYPTED_ATTR = "AZ_CERT"
HOST_ENCRYPTED_ATTR = "VCENTER_PASSWORD"
HOST_ENCRYPTED_ATTR = "NSX_PASSWORD"
HOST_ENCRYPTED_ATTR = "ONE_PASSWORD"

VM_ENCRYPTED_ATTR = "ONE_PASSWORD"
VM_ENCRYPTED_ATTR = "CONTEXT/ADMIN_PASSWORD"

VNET_ENCRYPTED_ATTR = "PROVISION/PACKET_TOKEN"
VNET_ENCRYPTED_ATTR = "PROVISION/PACKET_PROJECT"

VNET_ENCRYPTED_ATTR = "AR/PROVISION/PACKET_PROJECT"
```

OpenNebula encrypts these attributes:

- on object create (`onecluster/onedatastore/onehost/onevm/onevnet create`)
- on object update (`onecluster/onedatastore/onehost/onevm/onevnet update`)

To decrypt the attribute you need to use the `info` API method with `true` as a parameter. You can decrypt the attributes using the `--decrypt` option for `onevm show`, `onehost show` and `onevnet show`.

10.2.19 Inherited Attributes Configuration

The following attributes will be copied from the resource template to the instantiated VMs. More than one attribute can be defined.

- `INHERIT_IMAGE_ATTR`: Attribute to be copied from the Image template to each VM/DISK.
- `INHERIT_DATASTORE_ATTR`: Attribute to be copied from the Datastore template to each VM/DISK.
- `INHERIT_VNET_ATTR`: Attribute to be copied from the Network template to each VM/NIC.

Sample configuration:

```
#INHERIT_IMAGE_ATTR      = "EXAMPLE"
#INHERIT_IMAGE_ATTR      = "SECOND_EXAMPLE"
#INHERIT_DATASTORE_ATTR  = "COLOR"
#INHERIT_VNET_ATTR       = "BANDWIDTH_THROTTLING"

INHERIT_DATASTORE_ATTR   = "CEPH_HOST"
INHERIT_DATASTORE_ATTR   = "CEPH_SECRET"
INHERIT_DATASTORE_ATTR   = "CEPH_USER"
INHERIT_DATASTORE_ATTR   = "CEPH_CONF"
INHERIT_DATASTORE_ATTR   = "POOL_NAME"

INHERIT_DATASTORE_ATTR   = "ISCSI_USER"
INHERIT_DATASTORE_ATTR   = "ISCSI_USAGE"
INHERIT_DATASTORE_ATTR   = "ISCSI_HOST"

INHERIT_IMAGE_ATTR        = "ISCSI_USER"
INHERIT_IMAGE_ATTR        = "ISCSI_USAGE"
INHERIT_IMAGE_ATTR        = "ISCSI_HOST"
INHERIT_IMAGE_ATTR        = "ISCSI_IQN"

INHERIT_DATASTORE_ATTR   = "GLUSTER_HOST"
INHERIT_DATASTORE_ATTR   = "GLUSTER_VOLUME"

INHERIT_DATASTORE_ATTR   = "DISK_TYPE"
INHERIT_DATASTORE_ATTR   = "ADAPTER_TYPE"

INHERIT_IMAGE_ATTR        = "DISK_TYPE"
INHERIT_IMAGE_ATTR        = "ADAPTER_TYPE"

INHERIT_VNET_ATTR         = "VLAN_TAGGED_ID"
INHERIT_VNET_ATTR         = "FILTER_IP_SPOOFING"
INHERIT_VNET_ATTR         = "FILTER_MAC_SPOOFING"
INHERIT_VNET_ATTR         = "MTU"
```

10.2.20 OneGate Configuration

- `ONEGATE_ENDPOINT`: Endpoint where OneGate will be listening. Optional.

Sample configuration:

```
ONEGATE_ENDPOINT = "http://192.168.0.5:5030"
```

10.2.21 Default Permissions for VDC ACL rules

Default ACL rules created when a resource is added to a VDC. The following attributes configure the permissions granted to the VDC group for each resource type:

- DEFAULT_VDC_HOST_ACL: permissions granted on hosts added to a VDC.
- DEFAULT_VDC_NET_ACL: permissions granted on vnets added to a VDC.
- DEFAULT_VDC_DATASTORE_ACL: permissions granted on datastores to a VDC.
- DEFAULT_VDC_CLUSTER_HOST_ACL: permissions granted to cluster hosts when a cluster is added to the VDC.
- DEFAULT_VDC_CLUSTER_NET_ACL: permissions granted to cluster vnets when a cluster is added to the VDC.
- DEFAULT_VDC_CLUSTER_DATASTORE_ACL: permissions granted to a datastores added to a cluster.

When defining the permissions you can use "" or "--" to avoid adding any rule to that specific resource. Also you can combine several permissions with "+", for example "MANAGE+USE". Valid permissions are USE, MANAGE or ADMIN.

Example:

```
DEFAULT_VDC_HOST_ACL      = "MANAGE"
#Adds @<gid> HOST/#<hid> MANAGE #<zid> when a host is added to the VDC.
onevdc addhost <vdc> <zid> <hid>

DEFAULT_VDC_NET_ACL      = "USE"
#Adds @<gid> NET/#<vnetid> USE #<zid> when a vnet is added to the VDC.
onevdc addvnet <vdc> <zid> <vnetid>

DEFAULT_VDC_DATASTORE_ACL = "USE"
#Adds @<gid> DATASTORE/#<dsid> USE #<zid> when a vnet is added to the VDC.
onevdc adddatastore <vdc> <zid> <dsid>

DEFAULT_VDC_CLUSTER_HOST_ACL      = "MANAGE"
DEFAULT_VDC_CLUSTER_NET_ACL      = "USE"
DEFAULT_VDC_CLUSTER_DATASTORE_ACL = "USE"
#Adds:
#@<gid> HOST/%<cid> MANAGE #<zid>
#@<gid> DATASTORE+NET/%<cid> USE #<zid>
#when a cluster is added to the VDC.
onevdc addcluster <vdc> <zid> <cid>
```

10.3 Logging & Debugging

OpenNebula provides logs for many resources. It supports three logging systems: file based logging systems, syslog logging and logging to the standard error stream.

In the case of file based logging, OpenNebula keeps separate log files for each active component, all of them stored in /var/log/one. To help users and administrators find and solve problems, they can also access some of the error messages from the CLI or the [Sunstone GUI](#).

With syslog or standard error, the logging strategy is almost identical, except that the logging messages slightly change their format following syslog logging conventions and resource information.

10.3.1 Configure the Logging System

The Logging system can be changed in `/etc/one/oned.conf`, specifically under the LOG section. Two parameters can be changed: SYSTEM, which is ‘syslog’, ‘file’ (default) or ‘std’, and the DEBUG_LEVEL is the logging verbosity.

For the scheduler the logging system can be changed in the exact same way. In this case the configuration is in `/etc/one/sched.conf`.

10.3.2 Log Resources

There are different log resources corresponding to different OpenNebula components:

- **ONE Daemon:** The core component of OpenNebula dumps all its logging information onto `/var/log/one/oned.log`. Its verbosity is regulated by DEBUG_LEVEL in `/etc/one/oned.conf`. By default the ONE start up scripts will backup the last `oned.log` file using the current time, e.g. `oned.log.20121011151807`. Alternatively, this resource can be logged to the syslog.
- **Scheduler:** All the scheduler information is collected into the `/var/log/one/sched.log` file. This resource can also be logged to the syslog.
- **Virtual Machines:** The information specific to a VM will be dumped into the log file `/var/log/one/<vmid>.log`. All VMs controlled by OpenNebula have their own directory, `/var/lib/one/vms/<VID>` if syslog/stderr isn’t enabled. You can find the following information in it:
 - **Deployment description files** : Stored in `deployment.<EXECUTION>`, where `<EXECUTION>` is the sequence number in the execution history of the VM (`deployment.0` for the first host, `deployment.1` for the second and so on).
 - **Transfer description files** : Stored in `transfer.<EXECUTION>.<OPERATION>`, where `<EXECUTION>` is the sequence number in the execution history of the VM, and `<OPERATION>` is the stage where the script was used, e.g. `transfer.0.prolog`, `transfer.0.epilog`, or `transfer.1.cleanup`.
- **Drivers:** Each driver can have its **ONE_MAD_DEBUG** variable activated in **RC** files. If so, error information will be dumped to `/var/log/one/name-of-the-driver-executable.log`. Log information from the drivers is in `oned.log`.

Otherwise, the information is sent to syslog/stderr.

10.3.3 Logging Format

The structure of an OpenNebula message for a file based logging system is the following:

```
date [Z<zone_id>] [module] [log_level]: message body
```

In the case of syslog it follows the standard:

```
date hostname process[pid]: [Z<zone_id>] [module] [log_level]: message
```

where the zone_id is the ID of the zone in the federation, 0 for single zone set ups, the module is any of the internal OpenNebula components: VMM, ReM, TM, etc., and the log_level is a single character indicating the log level: I for info, D for debug, etc.

For syslog, OpenNebula will also log the Virtual Machine events like this:

```
date hostname process[pid]: [VM id] [Z<zone_id>] [module] [log_level]: message
```

and similarly for stderr logging.

For oned and VM events the formats are:

```
date [Z<zone_id>] [module] [log_level]: message
date [VM id] [Z<zone_id>] [module] [log_level]: message
```

10.3.4 Virtual Machine Errors

Virtual Machine errors can be checked by the owner or an administrator using the `onevm show` output:

```
$ onevm show 0
VIRTUAL MACHINE 0 INFORMATION
ID : 0
NAME : one-0
USER : oneadmin
GROUP : oneadmin
STATE : ACTIVE
LCM_STATE : PROLOG_FAILED
START TIME : 07/19 17:44:20
END TIME : 07/19 17:44:31
DEPLOY ID : -

VIRTUAL MACHINE MONITORING
NET_TX : 0
NET_RX : 0
USED MEMORY : 0
USED CPU : 0

VIRTUAL MACHINE TEMPLATE
CONTEXT=[  

  FILES=/tmp/some_file,  

  TARGET=hdb ]  

CPU=0.1  

ERROR=[  

  MESSAGE="Error excuting image transfer script: Error copying /tmp/some_file to /var/  

  ↵lib/one/0/images/isofiles",  

  TIMESTAMP="Tue Jul 19 17:44:31 2011" ]  

MEMORY=64  

NAME=one-0  

VMID=0

VIRTUAL MACHINE HISTORY
SEQ      HOSTNAME ACTION          START        TIME        PTIME
  0       host01   none  07/19 17:44:31 00 00:00:00 00 00:00:00
```

Here the error message that it could not copy a file most probably means the file does not exist.

Alternatively you can check the log files for the VM at `/var/log/one/<vmid>.log`.

Note: Check the Virtual Machines High Availability Guide, to learn how to recover a VM in fail state.

10.3.5 Host Errors

Host errors can be checked executing the `onehost show` command:

```
$ onehost show 1
HOST 1 INFORMATION
ID : 1
NAME : host01
STATE : ERROR
IM_MAD : im_kvm
VM_MAD : vmm_kvm
TM_MAD : tm_shared

HOST SHARES
MAX MEM : 0
USED MEM (REAL) : 0
USED MEM (ALLOCATED) : 0
MAX CPU : 0
USED CPU (REAL) : 0
USED CPU (ALLOCATED) : 0
TOTAL VMS : 0

MONITORING INFORMATION
ERROR=[  

MESSAGE="Error monitoring host 1 : MONITOR FAILURE 1 Could not update remotes",  

TIMESTAMP="Tue Jul 19 17:17:22 2011" ]
```

The error message appears in the ERROR value of the monitoring. To get more information you can check `/var/log/one/oned.log`. For example for this error we get in the log file:

```
Tue Jul 19 17:17:22 2011 [InM][I]: Monitoring host host01 (1)
Tue Jul 19 17:17:22 2011 [InM][I]: Command execution fail: scp -r /var/lib/one/
→remotes/. host01:/var/tmp/one
Tue Jul 19 17:17:22 2011 [InM][I]: ssh: Could not resolve hostname host01: nodename →
→nor servname provided, or not known
Tue Jul 19 17:17:22 2011 [InM][I]: lost connection
Tue Jul 19 17:17:22 2011 [InM][I]: ExitCode: 1
Tue Jul 19 17:17:22 2011 [InM][E]: Error monitoring host 1 : MONITOR FAILURE 1 Could →
→not update remotes
```

From the execution output we notice that the host name is not known, probably due to a mistake naming the host.

10.4 Onedb Tool

This section describes the `onedb` CLI tool. It can be used to get information from an OpenNebula database, upgrade it, or fix inconsistency problems.

10.4.1 Connection Parameters

The command `onedb` can connect to any SQLite or MySQL database. Visit the `onedb` man page for a complete reference. These are two examples for the default databases:

```
$ onedb <command> -v --sqlite /var/lib/one/one.db
$ onedb <command> -v -S localhost -u oneadmin -p oneadmin -d opennebula
```

10.4.2 onedb fsck

Checks the consistency of the DB (database), and fixes any problems found. For example, if the machine where OpenNebula is running crashes, or loses connectivity to the database, you may have the wrong number of VMs running in a Host, or incorrect usage quotas for some users.

```
$ onedb fsck --sqlite /var/lib/one/one.db
Sqlite database backup stored in /var/lib/one/one.db.bck
Use 'onedb restore' or copy the file back to restore the DB.

Host 0 RUNNING_VMS has 12 is 11
Host 0 CPU_USAGE has 1200 is 1100
Host 0 MEM_USAGE has 1572864 is 1441792
Image 0 RUNNING_VMS has 6 is 5
User 2 quotas: CPU_USED has 12 is 11.0
User 2 quotas: MEMORY_USED has 1536 is 1408
User 2 quotas: VMS_USED has 12 is 11
User 2 quotas: Image 0 RVMS has 6 is 5
Group 1 quotas: CPU_USED has 12 is 11.0
Group 1 quotas: MEMORY_USED has 1536 is 1408
Group 1 quotas: VMS_USED has 12 is 11
Group 1 quotas: Image 0 RVMS has 6 is 5

Total errors found: 12
```

If onedb fsck shows the following error message:

```
[UNREPAIRED] History record for VM <> seq # <> is not closed (etime = 0)
```

This is due to the fixed bug #4000. It means that when using accounting or showback, the etime (end-time) of that history record was not set, and the VM was considered as still running when it should not have been. To fix this problem, you could locate the time when the VM was shut down in the logs and then execute this patch to edit the times manually:

```
$ onedb patch -v --sqlite /var/lib/one/one.db /usr/lib/one/ruby/onedb/patches/history_
→times.rb
Version read:
Shared tables 4.11.80 : OpenNebula 5.0.1 daemon bootstrap
Local tables 4.13.85 : OpenNebula 5.0.1 daemon bootstrap

Sqlite database backup stored in /var/lib/one/one.db_2015-10-13_12:40:2.bck
Use 'onedb restore' or copy the file back to restore the DB.

> Running patch /usr/lib/one/ruby/onedb/patches/history_times.rb
This tool will allow you to edit the timestamps of VM history records, used to_
→calculate accounting and showback.
VM ID: 1
History sequence number: 0

STIME Start time      : 2015-10-08 15:24:06 UTC
PSTIME Prolog start time : 2015-10-08 15:24:06 UTC
PETIME Prolog end time   : 2015-10-08 15:24:29 UTC
RSTIME Running start time : 2015-10-08 15:24:29 UTC
RETIME Running end time    : 2015-10-08 15:42:35 UTC
ESTIME Epilog start time  : 2015-10-08 15:42:35 UTC
EETIME Epilog end time    : 2015-10-08 15:42:36 UTC
ETIME End time          : 2015-10-08 15:42:36 UTC
```

```
To set new values:
empty to use current value; <YYYY-MM-DD HH:MM:SS> in UTC; or 0 to leave unset (open_
↪history record).
STIME Start time      : 2015-10-08 15:24:06 UTC
New value          :

ETIME End time       : 2015-10-08 15:42:36 UTC
New value          :

The history record # 0 for VM 1 will be updated with these new values:
STIME Start time      : 2015-10-08 15:24:06 UTC
PSTIME Prolog start time : 2015-10-08 15:24:06 UTC
PETIME Prolog end time   : 2015-10-08 15:24:29 UTC
RSTIME Running start time : 2015-10-08 15:24:29 UTC
RETIME Running end time   : 2015-10-08 15:42:35 UTC
ESTIME Epilog start time : 2015-10-08 15:42:35 UTC
EETIME Epilog end time   : 2015-10-08 15:42:36 UTC
ETIME End time       : 2015-10-08 15:42:36 UTC

Confirm to write to the database [Y/n]: y
> Done

> Total time: 27.79s
```

10.4.3 onedb version

Prints the current DB version.

```
$ onedb version --sqlite /var/lib/one/one.db
3.8.0
```

Use the `-v` flag to see the complete version and comment.

```
$ onedb version -v --sqlite /var/lib/one/one.db
Version: 3.8.0
Timestamp: 10/19 16:04:17
Comment: Database migrated from 3.7.80 to 3.8.0 (OpenNebula 3.8.0) by onedb command.
```

If the MySQL database password contains special characters, such as @ or #, the onedb command will fail to connect to it.

The workaround is to temporarily change the oneadmin password to an alphanumeric string. The `set password` statement can be used for this:

```
$ mysql -u oneadmin -p

mysql> SET PASSWORD = PASSWORD('newpass');
```

10.4.4 onedb history

Each time the DB is upgraded, the process is logged. You can use the `history` command to retrieve the upgrade history.

```
$ onedb history -S localhost -u oneadmin -p oneadmin -d opennebula
Version: 3.0.0
Timestamp: 10/07 12:40:49
Comment: OpenNebula 3.0.0 daemon bootstrap

...
Version: 3.7.80
Timestamp: 10/08 17:36:15
Comment: Database migrated from 3.6.0 to 3.7.80 (OpenNebula 3.7.80) by onedb
→ command.

Version: 3.8.0
Timestamp: 10/19 16:04:17
Comment: Database migrated from 3.7.80 to 3.8.0 (OpenNebula 3.8.0) by onedb command.
```

10.4.5 onedb upgrade

The upgrade process is fully documented in the Upgrading from Previous Versions guide.

10.4.6 onedb backup

Dumps the OpenNebula DB to a file.

```
$ onedb backup --sqlite /var/lib/one/one.db /tmp/my_backup.db
Sqlite database backup stored in /tmp/my_backup.db
Use 'onedb restore' or copy the file back to restore the DB.
```

10.4.7 onedb restore

Restores the DB from a backup file. Please note that this tool will only restore backups generated from the same backend, i.e. you cannot backup an SQLite database and then try to populate a MySQL one.

10.4.8 onedb sqlite2mysql

This command migrates from an SQLite database to a MySQL database. The procedure to follow is:

- Stop OpenNebula
- Change the DB directive in /etc/one/oned.conf to use MySQL instead of SQLite
- Bootstrap the MySQL Database: oned -i
- Migrate the Database: onedb sqlite2mysql -s <SQLITE_PATH> -u <MYSQL_USER> -p <MYSQL_PASS> -d <MYSQL_DB>
- Start OpenNebula

10.4.9 onedb purge-history

Deletes all but the last 2 history records from non-DONE VMs. You can specify start and end dates in case you don't want to delete all history:

```
$ onedb purge-history --start 2014/01/01 --end 2016/06/15
```

Warning: This action is done while OpenNebula is running. Make a backup of the database before executing.

10.4.10 onedb purge-done

Deletes information from machines in the DONE state; --start and --end parameters can be used as for purge-history:

```
$ onedb purge-done --end 2016/01
```

Warning: This action is done while OpenNebula is running. Make a backup of the database before executing.

10.4.11 onedb change-body

Changes a value from the body of an object. The possible objects are: vm, host, vnet, image, cluster, document, group, marketplace, marketplaceapp, secgroup, template, vrouter or zone.

You can filter the objects to modify using one of these options:

- **--id:** object id, example: 156
- **--xpath:** xpath expression, example: TEMPLATE [count (NIC)>1]
- **--expr: xpath expression, can use operators =, !=, <, >, <= or >=** examples: UNAME=oneadmin, TEMPLATE/NIC/NIC_ID>0

If you want to change a value, use a third parameter. In case you want to delete it use --delete option.

Change the second network of VMs that belong to “user”:

```
$ onedb change-body vm --expr UNAME=user '/VM/TEMPLATE/NIC[NETWORK="service"]/NETWORK
˓→' new_network
```

Delete the cache attribute for all disks, write XML, but do not modify the DB:

```
$ onedb change-body vm '/VM/TEMPLATE/DISK/CACHE' --delete --dry
```

Delete the cache attribute for all disks in poweroff:

```
$ onedb change-body vm --expr LCM_STATE=8 '/VM/TEMPLATE/DISK/CACHE' --delete
```

Warning: This action is done while OpenNebula is running. Make a backup of the database before executing.

10.5 Scalability Testing and Tuning

Determining the scalability of your cloud, and how to improve it, requires balancing many variables. There are several aspects that can limit the scalability of a cloud, from the storage to the network backend, and no one solution meets

everyone's scalability goals. This guide firstly presents the scale limits of a single OpenNebula instance (single zone), and then provides some recommendations to tune your deployment for large scale.

The general recommendation is to have no more than 2,500 servers and 10,000 VMs managed by a single instance. Better performance and higher scalability can be achieved with specific tuning of other components like the DB, or better hardware. In any case, to grow the size of your cloud beyond these limits, you can horizontally scale your cloud by adding new OpenNebula zones within a federated deployment. The largest OpenNebula deployment consists of 16 data centers and 300,000 cores.

10.5.1 Scalability Testing

Front-end (oned) Scalability

This section focuses on the scale limits of oned, the controller component, for a single OpenNebula zone. The limits recommended here are associated with a given API load; you may consider reducing or increasing the limits based on your actual API requests. Notice that the maximum number of servers (virtualization hosts) that can be managed by a single OpenNebula instance strongly depends on the performance and scalability of the underlying platform infrastructure, mainly the storage subsystem. The following results have been obtained with synthetic workloads that stress oned running on a physical server with the following specifications:

CPU model:	Intel(R) Atom(TM) CPU C2550 @ 2.40GHz, 4 cores, no HT
RAM:	8GB, DDR3, 1600 MT/s, single channel
HDD:	INTEL SSDSC2BB150G7
OS:	Ubuntu 18.04
OpenNebula:	Version 5.8
Database:	MariaDB v10.1 with default configurations

In a single zone, OpenNebula (oned) can work with the following limits:

Number of hosts	2,500
Number of VMs	10,000
Average VM template size	7 KB

In production environments, we do not recommend exceeding in the same installation this number of servers (2,500) and VMs (10,000), as well as a load of 30 API requests/s to avoid excessive slowness of the system. Better performance can be achieved with specific tuning of other components, like the database, or better hardware.

The four most common API calls were used to stress the core at the same time in approximately the same ratio experienced on real deployments. The total numbers of API calls per second used were: 10, 20 and 30. In these conditions, with a host monitoring interval of 20 hosts/second, in a pool with 2,500 hosts and a monitoring period on each host of 125 seconds, the response times in seconds of the oned process for the most common XMLRPC calls are shown below:

Response Time (seconds)			
API Call - ratio	API Load: 10 req/s	API Load: 20 req/s	API Load: 30 req/s
host.info (30%)	0.06	0.50	0.54
Hostpool.info (10%)	0.14	0.41	0.43
vm.info (30%)	0.07	0.57	0.51
vmpool.info (30%)	1.23	2.13	4.18

Hypervisor Scalability

The number of VMs (or containers) a virtualization node can run is limited by the monitoring probes. In this section we have evaluated the performance of the monitoring probes for the KVM and LXD drivers. The host specs are the following:

CPU model:	Intel(R) Atom(TM) CPU C2550 @ 2.40GHz, 4 cores, no HT
RAM:	8GB, DDR3, 1600 MT/s, single channel
HDD:	INTEL SSDSC2BB150G7
OS:	Ubuntu 18.04
Hypervisor:	Libvirt (4.0), Qemu (2.11), lxd (3.03)

Containers and VMs settings used for monitoring tests:

Hypervisor	OS	RAM	CPU	Max. VM/host
KVM	None (empty disk)	32MB	0.1	250
LXD	Alpine	32MB	0.1	250

Note: 250 instances were deployed for both types of hypervisor because both templates were created with the same capacity requirements. This made allocated resources grow at the same rate, so the scheduler instantiated the same number of KVM VMs as LXD containers. It is worth noticing that the overhead on KVM VMs is bigger than on LXD containers, so the latter hypervisor technology allows for bigger density when compared to KVM, as shown in [this report](#).

Monitoring times for each type of instance are shown below:

Hypervisor	Monitoring time (seconds) per instance
KVM	0.42
LXD	0.1

Note that there may be other factors that limit the number of VMs or containers running in a single host.

10.5.2 Tuning for Large Scale

Monitoring Tuning

In KVM environments, OpenNebula supports two native monitoring systems: ssh-pull and udp-push. The former one, ssh-pull is the default monitoring system for OpenNebula <= 4.2, however from OpenNebula 4.4 onwards, the default monitoring system is udp-push. This model is highly scalable, and its limit (in terms of number of VMs monitored per second) is bound by the performance of the server running oned and the database server. Read more in the [Monitoring guide](#).

For vCenter environments, OpenNebula uses the VI API offered by vCenter to monitor the state of the hypervisor and all the Virtual Machines running in all the imported vCenter clusters. The driver is optimized to cache common VM information.

In both environments, our scalability testing achieves monitoring of tens of thousands of VMs in a few minutes.

Core Tuning

OpenNebula keeps the monitoring history for a defined time in a database table. These values are then used to draw the plots in Sunstone. These monitoring entries can take quite a bit of storage in your database. The amount of storage

used will depend on the size of your cloud, and the following configuration attributes in `oned.conf`:

- `MONITORING_INTERVAL_HOST`: Time in seconds between each monitoring cycle. Default: 180. This parameter sets the timeout to pro-actively restart the monitoring probe in the standard udp-push model.
- `collectd IM_MAD -i` argument (KVM only): Time in seconds of the monitoring push cycle. Default: 60.
- `HOST_MONITORING_EXPIRATION_TIME`: Time, in seconds, to expire monitoring information. Default: 12h.
- `VM_MONITORING_EXPIRATION_TIME`: Time, in seconds, to expire monitoring information. Default: 4h.
- `MONITORING_INTERVAL_DB_UPDATE`: Time in seconds between DB writes of VM monitoring information. Default: 0 (write every update).

Important: It is highly recommended to increase the `MONITORING_INTERVAL_DB_UPDATE` and the `IM_MAD-collectd -i` argument when running more than 5K VMs, so as not to overload DB write threads. Usually a slow response time from the API when running a high number of VMs is caused by this.

If you don't use Sunstone, you may want to disable the monitoring history, setting both expiration times to 0.

Each monitoring entry will be around 2 KB for each Host, and 4 KB for each VM. To give you an idea of how much database storage you will need to prepare, here are some examples:

Monitoring interval	Host expiration	# Hosts	Storage
20s	12h	200	850 MB
20s	24h	1,000	8.2 GB

Monitoring interval	VM expiration	# VMs	Storage
20s	4h	2,000	1.8 GB
20s	24h	10,000	7 GB

API Tuning

For large deployments with lots of XML-RPC calls, the default values for the XML-RPC server are too conservative. The values you can modify, and their meaning, are explained in `oned.conf` and the `xmlrpc-c` library documentation. From our experience, these values improve the server behavior with a large number of client calls:

```
MAX_CONN = 240
MAX_CONN_BACKLOG = 480
```

The core is able to paginate some pool answers. This makes the memory consumption decrease, and in some cases makes the parsing faster. By default the pagination value is 2,000 objects, but it can be changed using the environment variable `ONE_POOL_PAGE_SIZE`. It should be bigger than 2. For example, to list VMs with a page size of 5,000 we can use:

```
$ ONE_POOL_PAGE_SIZE=5000 onevm list
```

To disable pagination we can use a non numeric value:

```
$ ONE_POOL_PAGE_SIZE=disabled onevm list
```

This environment variable can be also used for Sunstone. Also, one of the main barriers to scaling OpenNebula is the list operation on large pools. Since OpenNebula 5.8, the VM pool is listed in a *summarized* form. However we

recommend making use of the search operation to reduce the pool size returned by oned. The search operation is available for the VM pool since version 5.8.

Scaling the API SERVER


In order to scale OpenNebula, it is recommended to balance client requests across multiple oned processes. This can be achieved by either using existing RAFT followers or adding oneds in an API server-only mode.

When oned is started in read-only (or cache) mode, it resolves any read-only operation by accessing the database directly. In particular, the following API calls are served directly by the server in cache mode:

one.vmpool.info	one.clusterpool.info	one.group.info
one.vmpool.accounting	one.zonepool.info	one.user.info
one.vmpool.showback	one.secgrouppool.info	one.datastore.info
one.vmpool.monitoring	one.vdcpool.info	one.cluster.info
one.templatepool.info	one.vrouterpool.info	one.document.info
one.vnpool.info	one.marketpool.info	one.zone.info
one.vntemplatepool.info	one.marketapppool.info	one.secgroup.info
one.imagepool.info	one.vmgrouppool.info	one.vdc.info
one.hostpool.info	one.template.info	one.vrouter.info
one.hostpool.monitoring	one.vn.info	one.market.info
one.grouppool.info	one.vntemplate.info	one.marketapp.info
one.userpool.info	one.image.info	one.vmgroup.info
one.datastorepool.info	one.host.info	one.zone.raftstatus

Note: read-only operations enforce any ACL restriction or ownership checks.

Any other API call is forwarded to the active oned process. In this case, the cache server is acting as a simple proxy. The architecture recommended to be used with the cache server is depicted in the following figure:



When the Master oned is actually a RAFT cluster, you can simply point the API servers to the VIP address of the cluster. Note also that the MySQL server in each RAFT server should be configured to listen on the VIP address to let the API servers query the database.

Configuration

To configure an API server you need to:

1. Install the OpenNebula packages in the server
2. Update the `oned.conf` file so it points to the master oned and Database:

```

DB = [ BACKEND = "mysql",
        SERVER = "set IP of mysql server",
        PORT = 0,
        USER = "oneadmin",
        PASSWD = "oneadmin",
        DB_NAME = "opennebula",
        CONNECTIONS = 50

FEDERATION = [
    MODE          = "CACHE",
    ZONE_ID       = 0,
    SERVER_ID     = -1,
    MASTER_ONED   = "set the XML-RPC endpoint of master oned"
]

```

Note also that you may need to tune the number of connections to the DB, increasing it for the MySQL server and adjusting the number of cache servers, considering that the overall number of connections is shared by all the servers.

Load Balancing

Alternatively, you may want to set up a load balancer that balances client requests across API servers. HAProxy is a good fit for this task. In this scenario, we are assuming 1 OpenNebula server plus two OpenNebula cache servers. The load balancer is listening on another server on port 2633, and will forward connections to the three OpenNebula servers comprising the cluster. This is the relevant fragment of the required HAProxy configuration for a scenario like the one described:

```

frontend OpenNebula
bind 0.0.0.0:2633
stats enable
mode tcp
default_backend one_nodes

backend one_nodes
mode tcp
stats enable
balance roundrobin
server opennebula1 10.134.236.10:2633 check
server opennebula2 10.134.236.11:2633 check
server opennebula3 10.134.236.12:2633 check

```

Server entries must be modified, and the stats section is optional.

Optionally, a second load balancer can be added on another server, and an active-passive redundancy protocol, like VRRP, can be set between both load balancer nodes for high availability.

To connect to the cluster from another server you can use one of the two following options, or both:

- Using the CLI: Create a ONE_XMLRPC variable with the new endpoint. E.g.

```
export ONE_XMLRPC=http://ENDPOINT_IP:2633/RPC2
```

- Using Sunstone: Modify one_xmlrpc in /etc/one/sunstone-server.conf

The new endpoint will be the load balancer address.

Driver Tuning

OpenNebula drivers have by default 15 threads. This is the maximum number of actions a driver can perform at the same time; following actions will be queued. You can make this value in [*oned.conf*](#). The driver parameter is `-t`.

Database Tuning

For non-test installations use a MySQL database. SQLite is too slow for more than a couple of hosts and a few VMs.

Be sure to review the [*recommended maintenance procedures*](#) for the MySQL database backend.

Sunstone Tuning

Please refer to the guide about [*Configuring Sunstone for Large Deployments*](#).