- SS64
- CMD >
- How-to >
- Search

RC: Read security information WD: Change security information

DSACLS.exe (installable option via **RSAT/AD DS**)

View or Edit ACLs (access control entries) for objects in Active Directory.

```
Syntax
      DSACLS "[\\Computer\]ObjectDN" [/A] [/D PermissionStatement [PermissionStatement]...]
         [/G PermissionStatement [PermissionStatement]...] [/I:{T | S | P}]
            [/N] [/P:{Y | N}]
               [/R {User | Group} [{User | Group}]...] [/S [/T]]
      PermissionStatements:
         {User | Group}:Permissions[;{ObjectType | Property}][;InheritedObjectType]
Key
   ObjectDN Distinguished name of the object.
             If omitted will be taken from standard input (stdin)
   /A
       Add ownership and auditing information to the results.
   /D
       Deny permissions to a user or group
       Grant permissions to a user or group.
   /G
   /I:
       Inheritance
           T The object and its child objects (default)
           S The child objects only
           P The object and child objects down one level only
        Replace the current ACEs in the ACL.
        By default, dsacls adds the ACE to the ACL.
   /P:
       Inherit permissions from parent objects (Y/N).
        Revoke/Delete all ACEs for the users or groups.
   /R
   /S
        Restore the default security.
        Default security for each object class is defined in the Active Directory schema.
  /S /T Restore the default security on the tree of objects.
Permissions
      GR: Generic Read
      GE: Generic Execute
      GW: Generic Write
      GA: Generic All
      SD: Delete an object
      DT: Delete an object and all of its child objects
```

```
WO: Change owner information
   LC: List the child objects of the object
   CC: Create a child object•
   DC: Delete a child object•
   WS: Write to a self object (group membership) group object + {ObjectType | Property} = "member."
   RP: Read a property•
   WP: Write to a property•
   CA: Control access (normally a specific extended right for control access)
          If you do not specify {ObjectType | Property} this permission will apply to all
          meaningful control accesses on the object.
   LO: List the object access, AD DS does not enforce this permission by default.
          Grant list access to a specific object when List Children (LC) is not granted to the parent.
          Deny list access to a specific object when the user or group has LC permission on the parent.
ObjectType | Property
       Limit the permission to the specified object type or property.
       Enter the display name of the object type or the property.
       Default=all object types and properties.
       For example, Grant the user rights to create all types of child objects:
       /G Domain\User:CC
      Grant the user rights to create only child computer objects:
       /G Domain\User:CC;computer
InheritedObjectType
       Limit inheritance of the permission to the specified object type.
       For example, Grant only User objects to inherit the permission:
       /G Domain\User:CC;;user
Object Types
       User, Contact, Group, Shared Folder, Printer, Computer, Domain Controllers, OU
```

If you do not specify {ObjectType | Property} to define a specific child object type, this permission will apply to all types of child objects; otherwise, it will apply only to the child object type that you specify.

You can Grant, Deny or Delete ACEs for multiple users and groups with a single parameter (/G /D /R), list the users/groups separated with spaces.

Examples

Grant Generic Read (GR) and Generic Execute (GE) on computer objects in the Laptops OU to Jdoe:

```
C:> dsacls "OU=Laptops,OU=AcmeCo,DC=ss64,DC=Com" /G Domain\JDoe:GRGE;computer
```

"If future generations are to remember us with gratitude rather than contempt, we must leave them more than the miracles of technology. We must leave them a glimpse of the world as it was in the beginning, not just after we got through with it" ~ President Lyndon B. Johnson

Related commands

```
<u>DSAdd</u> - Add object.<u>DSMod</u> - Modify object.<u>DSGet</u> - Display object.
```

<u>DSMove</u> - Move object.

DSQuery - Search for objects.

DSdbUtil - Maintenance of AD, Authorative Restore, manage snapshots.

DSAMain - Expose Active Directory data that is stored in a snapshot or backup.

DSMgmt - Configure Directory Services.

Copyright © 1999-2024 <u>SS64.com</u>

Some rights reserved