Travaux pratiques 2.5.3 : dépannage de la configuration PPP

Diagramme de topologie




Table d'adressage

Périphérique	Interface	Adresse IP	Masque de sous-réseau	Passerelle par défaut
R1	Fa0/1	10.0.0.1	255.255.255.128	N/D
	S0/0/0	172.16.0.1	255.255.255.252	N/D
	S0/0/1	172.16.0.9	255.255.255.252	N/D
R2	Lo0	209.165.200.161	255.255.255.224	N/D
	S0/0/0	172.16.0.2	255.255.255.252	N/D
	S0/0/1	172.16.0.5	255.255.255.252	N/D

R3	Fa0/1	10.0.0.129	255.255.255.128	N/D
	S0/0/0	172.16.0.10	255.255.255.252	N/D
	S0/0/1	172.16.0.6	255.255.255.252	N/D
PC1	Carte réseau	10.0.0.10	255.255.255.128	10.0.0.1
PC3	Carte réseau	10.0.0.139	255.255.255.128	10.0.0.129

Objectifs pédagogiques

À l'issue de ces travaux pratiques, vous serez en mesure d'effectuer les tâches suivantes :

- Câbler un réseau conformément au diagramme de topologie
- Supprimer la configuration de démarrage et recharger un routeur pour revenir aux paramètres par défaut
- Charger les routeurs avec les scripts fournis
- Détecter et corriger des erreurs réseau
- Documenter le réseau corrigé

Scénario

Les routeurs de votre société ont été configurés par un ingénieur réseau peu expérimenté. La présence de plusieurs erreurs dans la configuration a provoqué des problèmes de connectivité. Votre responsable vous demande de détecter les erreurs de configuration et de les corriger, puis de décrire le travail réalisé. En utilisant vos connaissances en matière de protocole PPP, ainsi que des méthodes de vérification standard, détectez les erreurs et corrigez-les. Veillez à ce que toutes les liaisons série utilisent l'authentification PPP CHAP et vérifiez que tous les réseaux sont accessibles.

Tâche 1 : chargement des routeurs avec les scripts fournis

R1

```
enable
configure terminal
!
hostname R1
!
!
enable secret class
!
!
!
no ip domain lookup
!
username R2 password 0 cisco
!
!!
interface FastEthernet0/0
ip address 10.0.0.1 255.255.255.128
shutdown
```

```
duplex auto
 speed auto
interface FastEthernet0/1
 duplex auto
 speed auto
interface Serial0/0/0
 ip address 172.16.0.1 255.255.255.248
 no fair-queue
 clockrate 64000
interface Serial0/0/1
 ip address 172.16.0.2 255.255.255.252
 encapsulation ppp
 ppp authentication pap
router ospf 1
log-adjacency-changes
network 10.0.0.0 0.0.0.127 area 0
network 172.16.0.8 0.0.0.3 area 0
!
ip classless
ip http server
!
control-plane
banner motd ^CUnauthorized access strictly prohibited and prosecuted to the
full extent of the law^C
line con 0
 exec-timeout 0 0
password cisco
logging synchronous
login
line aux 0
line vty 0 4
password cisco
login
end
R2
enable
configure terminal
hostname R2
!
enable secret class
1
!
no ip domain lookup
```

```
username R1 password 0 cisco
username R3 password 0 class
!
ļ
interface Loopback0
interface FastEthernet0/0
no ip address
 shutdown
 duplex auto
 speed auto
interface FastEthernet0/1
 ip address 209.165.200.161 255.255.255.224
 shutdown
 duplex auto
 speed auto
1
interface Serial0/0/0
 ip address 172.16.0.2 255.255.255.252
 encapsulation ppp
no fair-queue
ppp authentication chap
interface Serial0/0/1
ip address 172.16.0.2 255.255.255.252
router ospf 1
 log-adjacency-changes
 network 172.16.0.0 0.0.0.3 area 0
network 172.16.0.4 0.0.0.3 area 0
 network 209.165.200.128 0.0.0.31 area 0
ip classless
ip http server
!
control-plane
banner motd ^CUnauthorized access strictly prohibited and prosecuted to the
full extent of the law^C
line con 0
exec-timeout 0 0
password cisco
logging synchronous
login
line aux 0
line vty 0 4
password cisco
login
!
end
```

R3

```
enable
configure terminal
hostname R3
1
enable secret class
no ip domain lookup
username R1 password 0 cisco
username R3 password 0 cisco
!
interface FastEthernet0/0
no ip address
shutdown
duplex auto
 speed auto
interface FastEthernet0/1
 ip address 10.0.0.129 255.255.255.0
duplex auto
 speed auto
interface Serial0/0/0
 ip address 172.16.0.10 255.255.255.252
no fair-queue
 clockrate 64000
interface Serial0/0/1
   encapsulation ppp
  ppp authentication pap
router ospf 1
log-adjacency-changes
network 10.0.0.128 0.0.0.127 area 0
network 192.16.0.4 0.0.0.3 area 0
 network 192.16.0.8 0.0.0.3 area 0
ip classless
ip http server
control-plane
banner motd ^CUnauthorized access strictly prohibited and prosecuted to the
full extent of the law^C
line con 0
 exec-timeout 0 0
```

```
password cisco
logging synchronous
login
line aux 0
line vty 0 4
password cisco
login
!
end
```

Tâche 2 : recherche et correction des erreurs sur le réseau

Tâche 3 : documentation du réseau corrigé

Une fois que vous avez corrigé toutes les erreurs et testé la connectivité du réseau, documentez la configuration finale de chaque périphérique.

Tâche 4 : remise en état

Supprimez les configurations et rechargez les routeurs. Déconnectez le câblage et stockez-le dans un endroit sécurisé. Reconnectez le câblage souhaité et restaurez les paramètres TCP/IP pour les hôtes PC connectés habituellement aux autres réseaux (réseau local de votre site ou Internet).