
FUN Drum Pad

USER MANUAL

Drop a sound. Trigger a beat. Shape every hit. A streamlined VST3 drum instrument with 64 independent pads across four banks.




64 PADS | **4 BANKS A–D** | **WAV / AIFF / FLAC**

The interface shown uses the Original Sage theme. Control names in this guide match the English labels in the plug-in.

© 2026 FUNtasia Audio

Quick start

Your first drum hit in four steps.



THE INTERFACE Top: selected waveform / Lower left: pads & banks / Lower right: pad controls

01 Open the plug-in

Insert FUN Drum Pad on an instrument track in your DAW.

02 Select a pad

Choose BANK A–D, then select a destination in the 4×4 pad grid.

03 Load a sample

Drop a WAV / AIFF / FLAC file onto the pad, or use LOAD SAMPLE.

04 Play and shape

Click a pad to audition, trigger it via MIDI, and use the right-side controls.

TIP Clicking a pad selects and auditions it. Double-click does not open a file chooser.

Shape each pad

Eight knobs and four switches, independently stored for every pad.

SELECT / EDIT

The right-hand inspector edits only the selected pad. Drag a knob to adjust it, hold Shift while dragging for fine control, or type a value in its numeric field.

At ±100%, POGO starts at up to ±24 semitones and returns to normal pitch in about 180 ms. 0% disables the sweep.



CONTROL	RANGE / DEFAULT	FUNCTION
TUNE	-24 … +24 st DEF: 0.00	Transposes the sample in semitones.
POGO	-100 … +100 % DEF: 0.0	Short pitch sweep at the beginning of each hit.
GAIN	-60 … +12 dB DEF: 0.00	Individual pad output level.
PAN	-1 … +1 DEF: 0.00	Left/right level balance; 0 is center.
ATTACK	0 … 2 s DEF: 0.000	Time for the sound to fade in.
DECAY	0 … 5 s DEF: 0.100	Time to fall from attack to sustain.
SUSTAIN	0 … 1 DEF: 1.00	Held amplitude level (0–1).
RELEASE	0 … 10 s DEF: 0.100	Fade-out time after MIDI Note Off.

Switches

REVERSE
Play the sample backward.

GATE
OFF = one-shot; ON = release on Note Off.

MUTE
Silence this pad.

SOLO
Hear only pads with SOLO enabled.

MIDI & banks

Four banks of 16 pads. All 64 MIDI notes work regardless of the visible bank.

Bank	Pads / bank	MIDI notes	Displayed notes
A	01–16	36–51	C1 – D#2
B	01–16	52–67	E2 – G3
C	01–16	68–83	G#3 – B4
D	01–16	84–99	C5 – D#6

BANK A: 4×4 pad layout



The lowest note (C1) is at bottom left. Notes rise by semitone across rows, bottom to top.

Click-to-audition is always one-shot, even when GATE is ON.

1. The 64 pads map consecutively to MIDI notes 36–99. Switching BANK changes which pads you view and edit, not MIDI routing.
2. The plug-in labels MIDI note 60 as C3. Some DAWs display it as C4; use MIDI note numbers if octave names differ.
3. With GATE OFF (default), Note Off is ignored and the sample plays to its end. With GATE ON, Note Off begins RELEASE.

Sessions, themes & help

Save your kit with the DAW project and keep creating.

Saving and restoring a project

The audio for all 64 pads and their settings are embedded in the DAW project's VST3 plug-in state. The kit can be restored even if source files were moved. Large kits may take longer to save or reload.

Seven color themes

Use THEME at the lower right. Themes change appearance only—not sound, MIDI mapping, or sample data. The selected theme is recalled with the project.

- Original Sage
- Charcoal
- Deep Brown
- Lapis Lazuli
- Lavender
- Coral Red
- Mikan Orange

Troubleshooting

No sound

Check the pad has a sample, MIDI note 36–99, MUTE/SOLO, GAIN and DAW output routing.

Drag and drop fails

Some DAW browsers use proprietary drag data. Select the pad and use LOAD SAMPLE instead.

File will not load

Use a mono or stereo WAV / AIFF / FLAC file no longer than five minutes.

Remove a sample

Select the pad, press CLEAR PAD, and confirm in the menu that appears.

At a glance

VST3 / 64 pads / WAV, AIFF, FLAC / Mono & stereo / Up to 300 seconds per sample / 512 MiB total decoded kit PCM.