
FUN MonoFilter

Shape the stereo image of your low end.



Keep the low frequencies anchored while preserving the width above them. Two essential controls make it easy to shape the stereo foundation of your mix.

USER MANUAL

Version 1.0.0

20-500 Hz

Crossover

0-100%

Low-band width

VST3 / 24 dB/oct / LR4

01 Interface and controls

The interface provides two knobs, a stereo-width guide, a colour menu and a resizable window.

01 CROSSOVER

20-500 Hz; default 200 Hz. Sets the split between the low and high bands. Turn the knob or drag the yellow horizontal marker in the graph. Double-click either control to reset it to 200 Hz.

02 LOW WIDTH

0-100%; default 0%. At 0%, the low band is mono. At 100%, the original left and right low-band signals are retained. Intermediate values blend smoothly. Double-click the knob to reset to 0%.

03 STEREO WIDTH

The L/R curves illustrate the intended stereo-width behaviour across frequency. The yellow dashed line shows CROSSOVER. This is an explanatory display, not a live spectrum analyzer.

04 COLOUR / SIZE

Select from seven colour themes using COLOUR. Drag the bottom-right corner to resize the GUI from 50% to 250%; the initial size is 75%. Theme and size are saved with the DAW state.



GUI example: Original Sage (v1.0.0)


7 COLOUR THEMES

Original Sage / Charcoal / Deep Brown / Lapis Lazuli / Lavender / Coral Red / Mikan Orange

The SIZE FIX label in this image identifies the tested build.

02 Signal flow and workflow

Signal path



LOW WIDTH changes only the low band. The high band retains its original stereo relationship. At 0%, Low Mono = (Low L + Low R) / 2 is sent to both channels; at 100%, each original low-band channel is retained.

Quick start

1. Insert FUN MonoFilter on a stereo track or bus.
2. Start with CROSSOVER at 200 Hz and locate the low range you want to control.
3. Set LOW WIDTH to 0% to audition a centered low end.
4. Increase LOW WIDTH if needed; compare in the mix and in mono.

Suggested starting points

Kick / bass	Try 80-150 Hz with LOW WIDTH at 0%.
Mix bus	Start around 150-250 Hz; evaluate low-end placement.
Gentle narrowing	Try LOW WIDTH at 20-50% to retain some original width.

Phase and mono compatibility
Low-frequency content that is nearly out of phase between left and right can become quieter when summed to mono. Always listen for tonal and level changes.

03 Technical reference

At a glance

Format	VST3 effect
I/O	Mono / stereo
Crossover	4th-order Linkwitz-Riley, minimum phase
Slope	24 dB/oct
CROSSOVER	20-500 Hz (default 200 Hz)
LOW WIDTH	0-100% (default 0%)
Reported latency	0 samples
Smoothing	CROSSOVER 20 ms / WIDTH 10 ms
GUI	50-250%; starts at 75%; 7 themes
Host support	Parameter automation / state recall

Frequently asked questions

Q. Why can the low end sound different?

A. A minimum-phase crossover produces phase rotation around the split frequency. The audible result depends on the source.

Q. Does the plug-in add latency?

A. The plug-in reports zero samples of latency to the host.

Q. Do colour and size affect the audio?

A. No. Appearance settings do not change DSP processing parameters.

Validation note: the 2026-11-06 build passed pluginval at strictness 10 and the VST3 Validator (537 passed, 0 failed). This does not guarantee operation in every DAW configuration.