## Descargar archivo a un directorio de PC Local en ABAP

Utilice los siguientes pasos para descargar los datos de la tabla interna ABAP a un archivo en el servidor de aplicaciones SAP.


- 1. Declare una tabla interna de ABAP.
- 2. Complete la tabla interna con los datos requeridos.
- 3. Utilice el módulo de función GUI\_DOWNLOAD 'o el método 'GUI\_DOWNLOAD' de la clase 'CL\_GUI\_FRONTEND\_SERVICES' para descargar los datos, las clases se puede ver en la Trx. SE24.

El siguiente ejemplo de un programa se usa el módulo de función GUI\_DOWNLOAD para descargar el archivo.

```
REPORT zinterface download.
    Data Declaration
DATA: gt spfli TYPE TABLE OF spfli,
     gs_spfli TYPE spfli.
DATA: gv filename TYPE string.
     START-OF-SELECTION
START-OF-SELECTION.
  PERFORM get data.
END-OF-SELECTION.
IF NOT gt spfli IS INITIAL.
 PERFORM save file.
 MESSAGE 'No se encontraron datos' TYPE 'I'.
ENDIF.
*& Form get data
FORM get data.
*Get data from table SPFLI
 SELECT * FROM spfli
        INTO TABLE gt spfli.
                            " get data
ENDFORM.
```

```
Form save file
*&-----
FORM save file.
*Move complete file path to file name
 gv filename = 'C:\test\data.txt'.
*Download the internal table data into a file in PC Local
 CALL FUNCTION 'GUI DOWNLOAD'
   EXPORTING
     filename
                          = gv filename
     filetype
                          = 'ASC'
     write field separator = 'X'
   TABLES
     data tab
                          = gt spfli.
                           " save file
ENDFORM.
```

Cuando ejecutas el programa anterior, el archivo 'data.txt' se descargará en la siguiente ruta 'C:\ test'.



También podemos usar el método GUI\_DOWNLOAD de la clase CL\_GUI\_FRONTEND\_SERVICES para descargar el archivo. En lugar de llamar al módulo de función GUI\_DOWNLOAD en la subrutina save\_file del programa anterior, llame al método GUI\_DOWNLOAD de la clase CL\_GUI\_FRONTEND\_SERVICES.

## Descargar archivo a un directorio de PC Local en ABAP separados por un delimitador.

REPORT zinterface download.

```
* Data Declaration
TYPE-POOLS: truxs.
DATA: gt spfli TYPE TABLE OF spfli,
    gs spfli TYPE spfli.
DATA: gv filename TYPE string.
* START-OF-SELECTION
PERFORM get data.
IF NOT gt spfli IS INITIAL.
 PERFORM save file.
ELSE.
 MESSAGE 'No se encontraron datos' TYPE 'I'.
ENDIF.
*c-----
*& Form get_data
*&-----
FORM get data.
*Get data from table SPFLI
 SELECT * FROM spfli
      INTO TABLE gt spfli.
                      " get data
ENDFORM.
*& Form save file
FORM save file.
 DATA: lv fltime TYPE char10,
      lv distance TYPE char14,
      lv period TYPE char3.
*Move complete file path to file name
 gv filename = 'C:\test\data.txt'.
 LOOP AT gt spfli INTO gs spfli.
   WRITE: gs_spfli-fltime TO lv_fltime,
        gs spfli-distance TO lv distance,
        gs spfli-period TO lv period.
```

```
CONCATENATE gs spfli-carrid
                qs spfli-connid
                gs spfli-countryfr
                gs spfli-cityfrom
                gs spfli-airpfrom
                gs spfli-countryto
                gs spfli-cityto
                qs spfli-airpto
                lv fltime
                                    "gs spfli-fltime
                gs spfli-deptime
                gs spfli-arrtime
                                    "gs spfli-distance
                lv distance
                gs spfli-distid
                gs spfli-fltype
                lv period
                                    "gs spfli-period
           INTO gs text
           SEPARATED BY ';'.
    APPEND gs text TO gt text.
 ENDLOOP.
*Download the internal table data into a file in PC Local
 CALL FUNCTION 'GUI DOWNLOAD'
    EXPORTING
      filename
                            = gv filename
      filetype
                            = 'ASC'
      write field separator = 'X'
    TABLES
                            = gt text. "gt spfli.
      data tab
                             " save file
ENDFORM.
```

## Salida del Archivo

## data: Bloc de notas Archivo Edición Formato Ver Ayuda

LH;0400;DE;FRANKFURT;FRA;US;NEW YORK;JFK; 7:24;101000;113400; 6.162,0000;KM;; 0
AA;0017;US;NEW YORK;JFK;US;SAN FRANCISCO;SFO; 6:01;110000;140100; 2.572,0000;MI;; 0
AZ;0555;IT;ROME;FCO;DE;FRANKFURT;FRA; 2:05;190000;210500; 845,0000;MI;; 0
LH;2402;DE;FRANKFURT;FRA;DE;BERLIN;SXF; 1:05;103000;113500; 555,0000;KM;; 0
UA;0941;DE;FRANKFURT;FRA;US;SAN FRANCISCO;SFO; 11:36;143000;170600; 5.685,0000;MI;; 0
AZ;0789;JP;TOKYO;TYO;IT;ROME;FCO; 15:40;114500;192500; 6.130,0000;MI;; 0
LH;0402;DE;FRANKFURT;FRA;US;NEW YORK;JFK; 7:35;133000;150500; 6.162,0000;KM;X; 0
QF;0005;SG;SINGAPORE;SIN;DE;FRANKFURT;FRA; 13:45;225000;053500; 10.000,0000;KM;; 1
SQ;0015;US;SAN FRANCISCO;SFO;SG;SINGAPORE;SIN; 18:45;160000;024500; 8.452,0000;MI;; 2
SQ;0002;SG;SINGAPORE;SIN;US;SAN FRANCISCO;SFO; 18:25;170000;192500; 8.452,0000;MI;; 0
LH;0401;US;NEW YORK;JFK;DE;FRANKFURT;FRA; 7:15;183000;074500; 6.162,0000;KM;; 1
DL;0106;US;NEW YORK;JFK;DE;FRANKFURT;FRA; 7:55;193500;093000; 3.851,0000;MI;; 1
JL;0407;JP;TOKYO;NRT;DE;FRANKFURT;FRA; 12:05;133000;173500; 9.100,0000;KM;; 0
JL;0408;DE;FRANKFURT;FRA;JP;TOKYO;NRT; 11:15;202500;154000; 9.100,0000;KM;X; 1

AA;0064;US;SAN FRANCISCO;SFO;US;NEW YORK;JFK; 5:21;090000;172100; 2.572,0000;MI;; 0