SHEEHAN INC.

Device setup manual

Set up a PC or phone for Sheehan QMS: the certificate, the app, and the ticket printer's 5.5 × 8.5 in paper. Step by step, with pictures.

Every PC and phone

- **Install the certificate**, so the queue opens securely, with no warning.
- **Install the app**, so Sheehan QMS has its own icon and window.

The PC that prints tickets

- **Set the ticket paper** to 5.5 × 8.5 in, once, so tickets aren't cut in half or printed on Letter.

CONTENTS

1 **Open Settings** where every set-up tool is, in the menu

2 **Install the certificate** once per device, for the secure address

3 **Install the app** an icon on the desktop and Start menu

4 **Set the ticket paper to 5.5 × 8.5 in** on the PC with the ticket printer

5 **If something goes wrong** the usual problems and their fixes


Before you start

Steps marked **NEEDS ADMINISTRATOR** need a Windows administrator account. The app's own steps don't. Windows and your printer's windows may look a little different from the drawings here; the names of the settings are the same.

1 Open Settings

Every set-up tool for this device is on one page.

Sign in to the queue as usual. In the menu on the left, under **Account**, click **Settings**. Every role has it.



Settings in the menu (outlined in amber). The page has three parts: Install app, Install certificate and Ticket paper.

Green box
This device is ready. Nothing to do.

Amber box
Something is still to do. The box says what, and the button under it starts it.

On a phone the menu is folded away: tap the menu button at the top left to open it.

2 Install the certificate

Once per device, so the secure address opens with no warning.

The queue server makes its own certificate, so each device has to be told once to trust it. Until then the browser shows a warning instead of the queue.

BEFORE

Not secure https://sheehanqms.local/staff

Your connection isn't private


AFTER

https://sheehanqms.local/staff

The queue opens, and Install app works

On a Windows PC NEEDS ADMINISTRATOR

1. In **Settings**, under **Install certificate**, click **Set up this device**. The setup page opens and the installer, `install-certificate.cmd`, starts downloading by itself.
2. If the browser warns about the file, choose **Keep**.
3. Open the file from your downloads. If Windows says *Windows protected your PC*, click **More info**, then **Run anyway**.
4. Click **Yes** on the administrator prompt and wait until it says **Done**.
5. Restart the browser: type `edge://restart` in Edge or `chrome://restart` in Chrome, and press `Enter`.
6. Open **Settings** again on the secure address (`https://`). The box turns green.



Not set up yet: the amber box, and **Set up this device** under it. The two buttons at the bottom are the files themselves, for setting up another device.

On a phone or tablet

Android	In Settings, tap **Certificate for a phone** to download it. Open the phone's **Settings**, search for **CA certificate**, tap **Install anyway** and pick `sheehan-ca.crt`. Close Chrome completely and open the queue again.
iPhone / iPad	In **Safari**, tap **Certificate for a phone**, then **Allow**. Open **Settings** → **Profile Downloaded** → **Install**. Then **Settings** → **General** → **About** → **Certificate Trust Settings** and turn on **Sheehan QMS local certificate authority**.

Is this safe?

It only makes the device trust the shop's own queue server. Nothing else on the device changes.


3 Install the app

Sheehan QMS gets its own icon and window, like any program.


Installed, the staff pages open from a **Sheehan QMS** icon on the desktop and in the Start menu, in their own window with no address bar or tabs. It stays up to date by itself: it's the same site, on the same server.

On a Windows PC

1. Install the certificate first (part 2). Edge and Chrome only offer Install app on the secure address.
2. Open the queue in **Edge** or **Chrome** and sign in.
3. In **Settings**, under **Install app**, click **Install app**. The same button is also at the bottom of the menu.
4. In the browser's window, click **Install**.
5. To keep it in the taskbar: right-click its icon there and choose **Pin to taskbar**.



When the browser can install it, the **Install app** button shows here.



Installed: the icon on the desktop and in the taskbar, and the app in its own window.

No Install app button?
It only shows in Edge or Chrome, on the secure address, while the app isn't installed yet. Already installed: open Sheehan QMS from the Start menu.

No certificate yet?
In Settings, **download install-app.cmd**, open it, and choose *More info* → *Run anyway*. It makes the same icon, over the plain address.


On a phone: in Chrome, open the menu (⋮) and tap **Add to home screen**. In Safari on an iPhone, tap **Share** → **Add to Home Screen**.

4 Set the ticket paper to 5.5 × 8.5 in

Once, on the PC with the ticket printer.


Tickets print on half letter paper, **5.5 × 8.5 in**, fed in standing up. The app asks the browser for that size, but the browser can only use sizes the printer has in Windows. If it isn't there, the browser falls back to **Letter (8.5 × 11 in)** and the ticket comes out cut in half or in the wrong place.

How the paper goes in



Slide the printer's paper guides to 5.5 in. The ticket prints turned a quarter turn, its top (the dashed line) along the left edge, so it reads across when you turn the paper.

Which PC to set up





To tell which: open **Settings** → **Bluetooth & devices** → **Printers & scanners** on a PC. "*Printer on PC1*" means shared (A). Just the printer's name means direct (B).

Step 1 · Create the paper size, if the printer has none NEEDS ADMINISTRATOR

Most printers already have it: Statement (5.5 × 8.5 in)
Look in the printer's **Printing preferences** (Step 2) first. If **Statement** is in its Paper size list, pick it and skip this step.

1. Press `Win` + `R`, type `printui /s /t0` and press `Enter`. **Print Server Properties** opens on the **Forms** tab.
2. Tick **Create a new form**. If it's greyed out, click **Change form settings** at the bottom first.
3. Name it `Ticket 5.5x8.5`.
4. Choose **English**, then type Width `5.50in` and Height `8.50in`. Set all four margins to `0.00in`.
5. Click **Save Form**, then **Close**.






DRAWING · the Forms tab, filled in

Step 2 · Make it the printer's paper

1. Open **Settings → Bluetooth & devices → Printers & scanners** and click the ticket printer.
2. Click **Printing preferences**. On a shared printer (A), set it on the PC with the printer under **Printer properties → Advanced → Printing Defaults** instead, so every PC gets it.
3. Set **Paper size** to **Statement**, or **Ticket 5.5x8.5** if you made it. It may be on a *Paper*, *Paper/Quality* or *Advanced* page.
4. Set **Orientation** to **Portrait**: the paper goes in standing up. Click **OK**.



DRAWING · names differ by printer; look for Paper size and Orientation


Epson and some other printers

Their own window may not list Windows' sizes. Look for **User Defined** or **Custom** paper and type 5.5 in wide and 8.5 in long there.

Step 3 · Restart the browser

Close **every** Edge or Chrome window, then open the queue again. The browser only reads the printer's paper sizes when it starts.

Step 4 · Print a ticket




DRAWING · the browser's print window, with the real ticket in the preview

1. On **Customer order**, press **Serve**, then **Print ticket**. The print window opens.
2. Open **More settings**. **Paper size** should already say **Statement** (or **Ticket 5.5x8.5**). If it says Letter, pick it once; the browser remembers it for this printer.
3. **Margins**: **None**.
4. **Scale**: **Default** (100%), never *Fit to page*.


Check the preview

It should say **1 sheet of paper**, standing up, with the whole ticket on it, turned on its side.

What comes out



As it comes out of the printer



Turned a quarter turn, to read

The whole ticket on one half letter sheet: the ticket's boxes and the invoice table, nothing cut off.

5 If something goes wrong

The usual problems and what fixes them.

WHAT YOU SEE	WHAT TO DO
The ticket is cut in half	The browser printed on **Letter**, because the printer doesn't have the 5.5 × 8.5 in size, or the paper went in lying across. Feed it standing up, the short side first, and set the paper size to **Statement** (or **Ticket 5.5x8.5**), **Portrait** (part 4).
The print window still says Letter (8.5 × 11)	The paper size isn't on this printer yet, or the browser was open while you added it. Do Step 1 and 2 on the right PC (shared or direct), close every browser window, and try again.
Neither *Statement* nor *Ticket 5.5x8.5* is in the printer's list	Some printers keep their own list. Use their **User Defined** or **Custom** size, 5.5 in wide and 8.5 in long.
The ticket prints small, or in a corner	In the print window set **Scale** to **Default** and **Margins** to **None**.
A blank sheet comes out after the ticket	The printer still thinks the paper is Letter. Check its **Printing preferences** (Step 2).
Your connection isn't private	This device doesn't have the certificate yet. Open `http://sheehanqms.local/install` and do part 2.
No Install app button	Use Edge or Chrome, on the `https://` address, after the certificate. If it's already installed, open Sheehan QMS from the Start menu instead.
A download link in Settings doesn't open	HTTPS isn't set up on the server yet. Message the developers from SheeChat.

Still stuck?

Open **SheeChat** → **Message developer** and say which PC, which printer, and what the print window shows. A photo of the printed ticket helps.