Webex Incoming Calls Not Appearing on iPhone

Follow these steps in order. After each step, ask someone to place a test call to your Webex number.

1. Update Webex and restart your iPhone

- Open the **App Store**.
- Tap your **profile picture** in the top-right corner.
- Scroll down to available updates.
- Find **Webex** and tap **Update** if available.
- Restart your iPhone.

2. Check iPhone permissions and notifications

The easiest route on current iOS versions is:

1. Open **Settings**.
2. Scroll down and tap **Apps > Webex**.
3. Make sure **Microphone** is turned on.
4. Turn on **Camera** if you use video calling.
5. Tap **Notifications**.
6. Turn on **Allow Notifications**.
7. Under **Alerts**, enable:
    - **Lock Screen**
    - **Notification Centre**
    - **Banners**
8. Make sure **Sounds** is turned on.
9. If **Banner Style** is shown, select **Persistent** if you want incoming Webex notifications to remain visible until dismissed.

Notifications are managed separately from app permissions on current iOS versions.

3. Check the notification settings inside Webex

1. Open **Webex**.
2. Tap your **profile picture**.
3. Go to **Settings > Notifications > Calling**.
4. Make sure **Incoming Calls on This Device** is turned on.
5. If your version displays a **Direct calls** setting, select **Don’t mute**.
6. Open **Sounds and vibration > Calls** and make sure:
    - **Silence rings** is turned off.
    - A **ringtone** is selected.
    - **Vibrate** is turned on if required.

Webex may display slightly different options depending on your organisation’s calling service and the app version.

4. Allow Webex to run in the background

iOS manages background activity differently from Android, so there is no **Unrestricted battery** setting for individual apps.

1. Open **Settings**.
2. Go to **General > Background App Refresh**.
3. Make sure **Background App Refresh** is turned on.
4. Make sure **Webex** is enabled in the list.

Also check **Low Power Mode**:

1. Go to **Settings > Battery**.
2. Temporarily turn off **Low Power Mode**.
3. Test an incoming Webex call.

Low Power Mode reduces some background activity and may affect how apps operate when they are not open.

5. Allow Webex through Focus / Do Not Disturb

On current iOS versions:

1. Go to **Settings > Focus**.
2. Select the Focus mode that is currently active, such as **Do Not Disturb**, **Personal**, **Work** or **Sleep**.
3. Tap **Apps**.
4. Under allowed notifications, add **Webex**.
5. Repeat this for any other Focus modes you regularly use.

Alternatively, temporarily turn off the active Focus mode from **Control Centre** and place a test call.

Also check whether your iPhone's **Silent Mode** is enabled if calls appear on screen but do not ring.

6. Restart Webex

iOS does not provide an individual **Clear cache** option for Webex like Android does.

Instead:

1. Swipe up from the bottom of the screen and pause to open the **App Switcher**.
    - On iPhones with a Home button, double-press the **Home button**.
2. Find **Webex**.
3. Swipe up on Webex to close it.
4. Reopen **Webex**.
5. Test an incoming call.

If the issue continues, restart the iPhone again before proceeding to the final step.

7. Reinstall Webex only if the problem continues

Use this as a final troubleshooting step:

1. Press and hold the **Webex** app icon.
2. Tap **Remove App**.
3. Tap **Delete App** and confirm.
4. Restart your iPhone.
5. Open the **App Store** and reinstall **Webex**.
6. Open Webex and sign in again.
7. Allow **Microphone**, **Camera** and **Notifications** when prompted.

8. Recheck the Webex notification settings in **Step 3**.
9. Test an incoming call.

Deleting and reinstalling Webex signs you out and removes the app's locally stored data and settings from the iPhone. It does **not** delete your Webex account.