A quantum computer can be simulated by applying rotations to a unit vector  $u \in \mathbb{C}^{2^n}$  where n is the number of qubits. The dimension is  $2^n$  because a register with n qubits has  $2^n$  eigenstates. Quantum operations are "rotations" because they preserve |u| = 1. Mathematically, a rotation of u is equivalent to the product Ru where R is a  $2^n \times 2^n$  matrix.

The Eigenmath function rotate(u, s, k, ...) rotates vector u and returns the result. Vector u is required to have  $2^n$  elements where n is an integer from 1 to 15. Arguments s, k, ... are a sequence of rotation codes where s is an upper case letter and k is a qubit number from 0 to n-1. Rotations are evaluated from left to right. The available rotation codes are

C, kControl prefix H, kHadamard  $P, k, \phi$ Phase modifier Q, kQuantum Fourier transform V, kInverse quantum Fourier transform W, k, jSwap bits X, kPauli X Y, kPauli Y Z, kPauli Z

Control prefix C, k modifies the next rotation code so that it is a controlled rotation with k as the control qubit. Fourier rotations Q, k and V, k are applied to qubits 0 through k. (Q and V ignore any control prefix.)

## Error codes

- 1 Argument u is not a vector or does not have  $2^n$  elements where n = 1, 2, ..., 15.
- 2 Unexpected end of argument list (i.e., missing argument).
- 3 Bit number format error or range error.
- 4 Unknown rotation code.

Eigenstates  $|j\rangle$  are represented by the following vectors. (Each vector has  $2^n$  elements.)

$$|0\rangle = (1, 0, 0, \dots, 0)$$

$$|1\rangle = (0, 1, 0, \dots, 0)$$

$$|2\rangle = (0, 0, 1, \dots, 0)$$

$$\vdots$$

$$|2^{n} - 1\rangle = (0, 0, 0, \dots, 1)$$

A quantum computer algorithm is a sequence of rotations applied to the initial state  $|0\rangle$ . (The sequence could be combined into a single rotation by associativity of matrix multiplication.) Let  $\psi_f$  be the final state of the quantum computer after all the rotations have been applied. Like any other state,  $\psi_f$  is a linear combination of eigenstates.

$$\psi_f = \sum_{j=0}^{2^n - 1} c_j |j\rangle, \quad |\psi_f| = 1$$

The last step is to measure  $\psi_f$  and get a result. Measurement rotates  $\psi_f$  to an eigenstate  $|j\rangle$ . The measurement result is  $|j\rangle$ . The probability  $P_j$  of getting a specific result  $|j\rangle$  is

$$P_j = |c_j|^2 = c_j c_j^*$$

Note that if  $\psi_f$  is already an eigenstate then no rotation occurs. (The probability of rotating to a different eigenstate is zero.) Since the measurement result is always an eigenstate, the coefficients  $c_j$  cannot be observed. However, the same calculation can be run multiple times to obtain a probability distribution of results. The probability distribution is an estimate of  $|c_j|^2$  for each  $|j\rangle$  in  $\psi_f$ .

Eigenmath code snippets for before and after rotate:

```
Initialize \psi = |0\rangle.

n = 4 -- number of qubits (example)

N = 2^n -- number of eigenstates

psi = zero(N)

psi[1] = 1

Compute the probability distribution for state \psi.

P = psi \ conj(psi)

Hence

P[1] = probability \ that \ |0\rangle \ will \ be \ the \ result

P[2] = probability \ that \ |1\rangle \ will \ be \ the \ result

P[3] = probability \ that \ |2\rangle \ will \ be \ the \ result

P[N] = probability \ that \ |N-1\rangle \ will \ be \ the \ result
```

Draw a probability distribution.

```
xrange = (0,N)
yrange = (0,1)
draw(P[ceiling(x)],x)

Compute an expectation value.
sum(k,1,N, (k - 1) P[k])

Make the high order qubit "don't care."
for(k,1,N/2, P[k] = P[k] + P[k + N/2])

Hence for N = 16

P[1] = \text{probability that the result will be } |0\rangle \text{ or } |8\rangle
P[2] = \text{probability that the result will be } |1\rangle \text{ or } |9\rangle
P[3] = \text{probability that the result will be } |2\rangle \text{ or } |10\rangle
\vdots
P[8] = \text{probability that the result will be } |7\rangle \text{ or } |15\rangle
```

## Example.

```
-- Verify the following truth table for cnot
      Input Output
      00
            00
      01
            11
     10
            10
      11
            01
U(psi) = rotate(psi,C,0,X,1) -- cnot
M(psi) = psi conj(psi) -- measure
ket00 = (1,0,0,0)
ket01 = (0,1,0,0)
ket10 = (0,0,1,0)
ket11 = (0,0,0,1)
M(U(ket00)) == M(ket00)
M(U(ket01)) == M(ket11)
M(U(ket10)) == M(ket10)
M(U(ket11)) == M(ket01)
```