



Portable Inspector

User's Guide

Version 1.0.1098

April, 2026

Contents

Chapter 1. Copyright.....	6
Chapter 2. Introduction.....	7
Management Program (MP).....	7
Scanning Tool (USB Device).....	8
Management Program Mode.....	9
Standalone Scanning Tool.....	13
Chapter 3. Setting Up.....	14
Installing the Management Program.....	14
Changing the Activation Code.....	19
Silent installation.....	21
CLI Parameters.....	21
Example.....	22
Activation.....	22
Activation Code format.....	23
Activating a Managed Scanning Tool.....	24
Procedure: Activating a Managed Scanning Tool.....	24
Activating a Standalone Scanning Tool.....	24
Procedure: Activating a Standalone Scanning Tool.....	25
Upgrades.....	26
Upgrading the Management Program.....	26
Procedure: Upgrading the Management Program.....	26
Upgrading the Scanning Tool.....	26
Procedure: Upgrading the Scanning Tool.....	26
Scan Action.....	27
Asset Information.....	27
Conditions.....	28
Chapter 4. Using the Management Program.....	34

Understanding the Management Program Console.....	34
Overview Tab.....	35
Checking the Latest Components.....	36
Portable Inspector (Pro) Components.....	37
Scheduled Update.....	38
Registered Scanning Tools.....	39
Scan Settings (Basic).....	40
Scan Type.....	41
Scan Option.....	41
Scan Settings (Advanced).....	42
Scan Settings (Rescue Disk).....	43
Scan Settings (Others).....	43
Plugged-in Scanning Tools.....	43
Updating Components through a Scanning Tool.....	44
Procedure: Updating Components through a Scanning Tool.....	44
Logs and Reports Tab.....	44
Management Program Settings.....	46
General Settings.....	46
Update Settings.....	47
Backing Up and Restoring Management Program Settings.....	47
Exporting and Importing Management Program Settings.....	48
Scan Settings.....	48
Chapter 5. Using the Scanning Tool Console.....	49
Scanning a Windows Endpoint.....	49
Procedure: Scanning a Windows Endpoint.....	49
Procedure: Enable or Disable Asset Info Collection During Scanning.....	50
Procedure: Manually Start Asset Collection.....	51
Procedure: Enable or Disable Auto Start for Scanning or Asset Info Collection.....	51
Procedure: Manually Stop Auto Start for Scan or Asset Info Collection.....	52

ST Scan Settings.....	53
Security Threats Found.....	57
Restore Tab.....	59
Logs Tab.....	59
Status & Update Tab.....	61
Component Updates.....	62
Changing the Scanning Tool Settings.....	63
Renaming an Asset.....	64
Chapter 6. Scanning Linux Endpoints.....	66
Linux System Requirements.....	66
Linux Command Line Reference.....	66
Scanning a Linux Endpoint for Security Risks.....	67
Restoring Files on a Linux Endpoint.....	68
Performing Debug Logging on Linux Systems.....	69
Viewing Linux Scan Logs.....	69
Chapter 7. Using the Secure Storage Console.....	70
User Data Mode.....	70
Transfer Files.....	70
Block History.....	71
Distributed Mode.....	72
Sync Distributed Files.....	72
Switch Back to User Data Mode.....	73
Change Password.....	74
Reset Secure Storage.....	74
Lost Password.....	75
Maximum Number of Password Attempts Exceeded.....	75
Secure Storage Controller for Linux.....	75
Chapter 8. Additional Tools.....	77
Portable Inspector Diagnostic Toolkit.....	77

Debug.....	77
Reset Device.....	78
Support Updates.....	79
Applying Hot Fixes.....	80
Rescue Disk.....	80
Procedure: Rescue Disk.....	81
Scanning Tool Agent.....	82
Install or Update the Scanning Tool Agent.....	83
Uninstall the Scanning Tool Agent.....	84
Scanning Tool Agent Console.....	84
Customize the Configuration Before Installation.....	86
Activate the Scanning Tool via Scanning Tool Agent.....	88
Diagnostic Tool Tab.....	90
Chapter 9. Contact Us.....	91

Chapter 1. Copyright

TXOne Networks Incorporated reserves the right to make changes to this document and to the product described herein without notice. Before installing and using the product, review the readme files, release notes, and/or the latest version of the applicable documentation, which are available at <https://help.txone.com/> and <https://my.txone.com/>.

TXOne Networks, TXOne Portable Inspector, TXOne ElementOne, and TXOne Safe Port are registered trademarks of TXOne Networks Incorporated. All other product names may be trademarks or registered trademarks of their owners.

Copyright ©2026 TXOne Networks Incorporated. All rights reserved. No part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted without the express prior written consent of TXOne Networks Incorporated.

Chapter 2. Introduction

This chapter introduces the Portable Inspector (Pro) product and features.

Portable Inspector (Pro) delivers high-performance, cost-effective security services, helping protect companies by finding and removing security threats from computers or devices that do not have security software or an Internet connection.

The Scanning Tool is an antivirus security program in a portable USB device that you can easily use to find and remove security threats from computers or devices without having to install an antivirus program. You can also use the Management Program to manage all the updates, scan settings, and logs generated by the Scanning Tool.

Most antivirus programs are installed on each device and need an Internet connection to be able to download the latest components. With Portable Inspector (Pro), the antivirus software is already in the portable USB device, and you can just plug the USB device into the computer or device and scan it.

Meanwhile, PI (Pro) offers a more secure way to transfer files. It monitors data put into secure storage in real time, and only files identified as clean can be placed in secure storage.

Portable Inspector™ (Pro) has two main components, both with a console:

- **Management Program:** This program can manage several Scanning Tool devices.
- **Scanning Tool:** You can register the Scanning Tool device to the Management Program, or you can also use the Scanning Tool as a standalone tool. This means you will not have to install anything on any device.

Management Program (MP)

The Management Program can perform various actions, including configuring scan settings and importing log data from multiple Scanning Tools.

You can use the Management Program to perform these tasks:

- Update and deploy security pattern files and scan engine components to registered Scanning Tools.
- Change the scan settings and synchronize them with registered Scanning Tools.
- Exclude files, folders, and extensions from scanning.

- Import and manage log data generated by scans.
- Specify an administrator account and password so that endpoints will try to execute Portable Inspector with these credentials when the user has no administrator's privileges.

Scanning Tool (USB Device)

The Scanning Tool can check the endpoint for security threats after you plug it in. The Scanning Tool can also fix, quarantine, or just log the threats found. The results of each scan are saved on the Scanning Tool.



Note:

- If the Scanning Tool does not start, you can open Windows Explorer and double-click Launcher.exe from the PI SYS partition.
- The Scanning Tool console is only available for Windows computers.

Each Scanning Tool launches its own console. However, the features you can see on the console depend on the mode you choose. You can choose either Standalone Scanning Tool mode or Management Program mode.

Refer to the [Management Program Mode \(on page 9\)](#) page.



Note:

Make sure you select the correct mode because after activation, you can only change the mode by resetting the device.

For more information, see [Reset Device \(on page 78\)](#).

Table 1. Scanning Tool Modes

	Management Program	Standalone Scanning Tool
Updates	In addition to downloading specified components from the TXOne ActiveUpdate server or a specified source, components can be updated from the Management Program.	Downloads all components from the TXOne ActiveUpdate server, from any endpoint with an Internet connection, or from a specified source.

Table 1. Scanning Tool Modes (continued)

	Management Program	Standalone Scanning Tool
Scan settings	Same as the Management Program or configured from the Scanning Tool.	Change the scan settings directly from the Scanning Tool console.
Logs	• Exported to the Management Program • Imported from another Scanning Tool	Imported from or exported to an endpoint.

**Note:**

- TXOne Networks recommends installing OfficeScan™ on the endpoints with the Management Program installed.
- While scanning for security threats, TXOne Networks may create temporary files on the endpoint. These files will be deleted after the Scanning Tool stops any running processes. You can also choose to scan endpoints without saving the temporary files.

Management Program Mode

The Management Program Control mode registers the Scanning Tool to the Management Program, which manages all the registered Scanning Tools. All the Scanning Tool devices can get the updates and scan settings from the Management Program, and you can also upload all the logs from each device.



In this mode, there are two ways you can connect the Scanning Tool: a) by connecting the Scanning Tool directly to the computer that has the Management Program on it or b) by connecting the Scanning Tool to a computer with Internet connection, and then remotely connecting it to the Management Program computer.

- **Direct connection**


You can plug the Scanning Tool device directly into the Management Program computer to get the updates, settings, or to transfer logs.



This setting is applicable for environments wherein all the computers are in one location and the Management Program computer is accessible. Here are some sample scenarios.

- **Remote connection**

You can plug the device into any computer with an Internet connection and then connect to the Management Program online to get the updates, settings, or to transfer logs.




Note:

There might be communication issues if a firewall is between the Management Program and the Scanning Tool. If this is the case, accept and give permission to the C:\Program Files\TXOne \Portable Inspector\PISfSrvCom.exe process.



This setting is applicable if you have several locations. In each location, you can have just one computer with an Internet or network connection and use that to regularly connect to the Management Program. Here are some sample scenarios.



Standalone Scanning Tool

The Standalone Scanning Tool mode uses the Scanning Tool as a standalone device, wherein you can use any endpoint that has Internet connection to update the components, change scan settings, or check the logs.

This setting is for those who want to use the Scanning Tool without having to go to the Management Program for updates or changes to the settings. With this mode, you can make any changes to the Scanning Tool settings directly from the Scanning Tool console.



Note:

TXOne recommends regularly updating the components before scanning any device to make sure that the latest threats can be fixed and quarantined as needed.

Chapter 3. Setting Up

Before you can use the Portable Inspector (Pro) Scanning Tool, remember the following.



Note:

You must activate the Scanning Tool before using it. Refer to [Activating a Managed Scanning Tool \(on page 24\)](#) page for more information.

- If the user account has administrator privileges, you can use Portable Inspector (Pro) to scan the computer.
- If the user account does not have administrator privileges, you can enable the **Scan as administrator** option then open Windows Explorer and double-click Launcher.exe from the PI SYS partition.
- Portable Inspector saves the scan result logs in the Scanning Tool after scanning a device.


Installing the Management Program

The Management Program is the central console for the components, settings, and logs of all the Scanning Tool devices. Each managed Scanning Tool can be used in a separate location but can upload to and sync with the Management Program locally or remotely.

• System Requirements

<https://help.txone.com/docs/portable-inspector-system-requirements>

1. Plug in the Scanning Tool to the target computer.
2. Open Windows Explorer and double-click MP_Install.exe from the PI SYS\MP directory to start the program.
3. When the **Installation Destination** screen appears, type or browse for a folder and click **Next**.



The screenshot shows the 'Portable Inspector' window with the 'Proxy Server Settings' tab selected. The window has a title bar with standard Windows controls and the txOne networks logo in the top right corner. The main content area contains a checkbox for 'Use a proxy server'. Below it are two radio buttons: 'Import the Internet Explorer proxy setting' (which is selected) and 'Enter the necessary proxy server settings in the following fields'. Under the second radio button, there are input fields for 'Address:', 'Port:', 'Authentication (optional):', 'Username:', and 'Password:'. At the bottom of the dialog are three buttons: '< Back', 'Next >' (which is highlighted with a blue border), and 'Cancel'.

Portable Inspector

Proxy Server Settings

txOne networks

☐ Use a proxy server

☒ Import the Internet Explorer proxy setting

☐ Enter the necessary proxy server settings in the following fields

Address:

Port:


Authentication (optional):

Username:

Password:

< Back Next > Cancel

4. When the **Proxy Server Setting** screen appears, fill in the proxy information if necessary and click **Next**.



The screenshot shows a window titled "Portable Inspector" with a standard Windows title bar (minimize, maximize, close buttons). The window has a header area with the text "Activation Code" on the left and the "txOne networks" logo on the right. The main area is a light gray rectangle. In the lower-left of this area, the text "Activation Code:" is followed by a long, empty text input field. Below the input field, the format "(XX-XXXX-XXXXX-XXXXX-XXXXX-XXXXX-XXXXX or XXXX-XXXX-XXXX-XXXX)" is displayed in a smaller font. At the bottom of the window, there are three buttons: "< Back", "Next >" (which is highlighted with a blue border), and "Cancel".

5. When the **Activation Code** screen appears, specify your Activation Code, and click **Next**.



6. When the **End User License Agreement** screen appears, read the agreement, and click **Agree and Install**.

**Note:**

You're able to manage a license for **Portable Inspector** and a license for **Portable Inspector Pro** here. You can add another license later in the **Overview** tab after installation.

Portable Inspector

Communication Port and Password

txOne networks

Specify the port number and password that the Management Program uses to establish a connection with the Scanning Tool.

Listening IP address:

Listening port:

Password:

Confirm password:


< Back **Next >** Cancel

- When the **Communication Port and Password** screen appears, specify the IP address, port number of the endpoint, and create a password.



Note:

If there is a firewall between the Management Program and the Scanning Tool, accept and give permission to the C:\Program Files\TXOne\Portable Inspector\PISfSrvCom.exe process to continue. Port 10240 (default port) must open on the Management Program server.




8. When the **Installation Done** screen appears, click **Close**.

Changing the Activation Code


The date next to Expires appears when you need to get another Activation Code. If you recently provided a new Activation Code, click **Refresh** to get the latest expiration date or click **Edit** to change the Activation Code.

For more information, refer to [Activation \(on page 22\)](#) page.

1. Access the correct screen for the Scanning Tool type.
 - a. For a managed Scanning Tool device, open the Management Program.



- b. For a standalone Scanning Tool, open the Scanning Tool console and click the **Status & Update** tab.



2. Click **Edit**.
3. Type the new Activation Code.
4. Click **OK**.

Silent installation

Users can use CLI mode to install/upgrade/uninstall MP without any interactive input.

MP provides two types of silent modes. One is silent with a simple UI, which may help to disclose status and progress information to the user, while the other is in full silent mode, and the user can only retrieve the exit code value of the final results.

CLI Parameters

- Mode
 - **-silent**: silent mode

- Action
 - **-install**: fresh install or upgrade MP. (If the target machine matches fresh install conditions, parameters are required)
 - **-upgrade** : upgrade existed MP
 - **-uninstall**: uninstall MP
- (Parameters required for fresh install)
 - **-address**: address of MP (with parameter)
 - **-port**: port of MP (with parameter)
 - **-password**: password of MP (with parameter)
 - **-AC_std**: PI AC (with parameter)
 - **-AC_pro**: PI-Pro AC (with parameter)
- (If the network environment requires proxy)
 - **-useproxy_ie** : use IE proxy setting when activating AC
 - **-proxy_host** : proxy host (with parameter)
 - **-proxy_port** : proxy port (with parameter)
 - **-proxy_username** : username for proxy, if available (with parameter)
 - **-proxy_password**: password for proxy, if available (with parameter)

Example

- Fresh install

```
E:\1135\MP>MP_Install.exe -silent -install "C:\Program Files\TXOne\Portable Inspector" -AC_pro "TE-AAAA-BBBBBB-CCCCC-XXXXX-YYYYY-ZZZZZ" -address "txone-someone" -port 10240 -password PASSWORD
```

- Upgrade

```
E:\1135\MP>MP_Install.exe -silent -upgrade_
```

Activation

After plugging in the Scanning Tool, you must select the operating mode and Activate the device before you can begin scanning endpoints. If you later decide to change operating modes (for example, from **Standalone Scanning Tool** to **Management Program Tool**), you must reset the device to factory default settings.

For more information, see [Reset Device \(on page 78\)](#) page.



Note:

This function is only available on Windows endpoints.

You can view the current activation status of your Scanning Tool by opening the console and going to the **Status and Update** tab.

You can view the current activation status of your Management Program by opening the console and going to the **Overview** tab.

Table 2. Icons and messages regarding Activation Codes

Icon	Message
	This Activation Code is already active, and no action is needed.
	This Activation Code is going to expire soon, and you need to renew your subscription.
	• This Activation Code has not yet been activated and you need to activate it to be able to use the product. • This Activation Code has already expired. You need to get a new Activation Code or renew your subscription to continue using the product.



Note:

TXOne recommends getting a new Activation Code before your current license expires to ensure that the Scanning Tool always has the most recent updates.

Activation Code format

TXOne activation code format is xxxx-xxxx-xxxx-xxxx.

**Note:**

In situations where there is a firewall, ports 80 and 443 need to be open, as both Portable Inspector activation and pattern/engine updates use these ports to function.

Activating a Managed Scanning Tool

Managed Scanning Tool devices are registered to the Management Program. Each Scanning Tool can synchronize device settings and download the latest updates from the Management Program. Each Scanning Tool device can also upload files to the Management Program.

Procedure: Activating a Managed Scanning Tool

1. Option 1: Simple Activation
 - a. Install the Management Program.
 - b. Plug in the new Scanning Tool or any Scanning Tool that has not yet been activated to the same computer. The Scanning Tool should automatically activate and register to the Management Program.
2. Option 2: Alternative Activation Procedure
 - a. Plug the new Scanning Tool or any Scanning Tool that has not yet been activated into a running computer.
 - i. Open Windows Explorer and double-click Launcher.exe in the PI SYS partition to start the program.
 - ii. The **Scanning Tool Mode** screen will open.
 - iii. Select **Management Program Control** and click **Next**.
The **Management Program and Proxy Settings** screen will open.
 - b. Specify the following:
 - i. Scanning Tool name
 - ii. Management Program address, port, and password
 - iii. (Optional) Proxy settings
 - c. Click Activate.
 - d. (Optional) Go to the Status & Update tab and click Update Now to get the latest components.

Activating a Standalone Scanning Tool


Standalone Scanning Tools are independent of the Management Program, and you can update the components directly from the Internet.

**Note:**

This function is only available on Windows endpoints.

Procedure: Activating a Standalone Scanning Tool

1. Plug in the new Scanning Tool or any Scanning Tool that has not yet been activated to a computer.
2. Open Windows Explorer and double-click Launcher.exe or SecureStorage.exe from the PI SYS partition to start the program.
3. Select Standalone Scanning Tool and click **Next**.



4. When the **End User License Agreement** screen appears, read the agreement, and click **Agree and Next**.
5. Specify your Activation Code and click **Activate**. The Scanning Tool console will open.

**Note:**

TXOne recommends immediately updating all components after activating the license or upgrading the program. Go to the **Status & Update** tab and click **Update Now**.

Upgrades

TXOne occasionally releases updates to Portable Inspector to provide more features and improve performance.

To upgrade the program, go to the **Status & Update** tab and click **Update Now**.

Upgrading the Management Program

TXOne occasionally releases updates to Portable Inspector to provide more features and improve performance.



Note:

Make sure you have at least 2.3GB of free space on the Management Program endpoint available for temporary usage during the upgrade.

Procedure: Upgrading the Management Program

1. Download and double-click the setup package. The **End User License Agreement** page will appear.
2. Read the TXOne License Agreement and select **Agree and Install**.
3. Click **Close** when the upgrade is complete.

Upgrading the Scanning Tool

TXOne occasionally releases updates to Portable Inspector to provide more features and improve performance.

TXOne recommends immediately updating all components after activating the license or upgrading the program. Go to the **Status & Update** tab and click **Update Now**.

Procedure: Upgrading the Scanning Tool

• Upgrade by Synchronizing with the Management Program

1. Upgrade the Management Program.
2. Plug in the Scanning Tool to the Management Program endpoint or connect it remotely through the Internet.
3. Select the Scanning Tool from the list shown in the Management Program and click **Sync Components and Settings**.

- **Upgrade Using the Support Tool**

1. Close the Scanning Tool console if it is open.
2. Log on to the endpoint using an account with administrator privileges and connect to the Scanning Tool.
3. Download the Portable Inspector (Pro) service pack.
4. Extract the contents of the service pack to a local folder on the endpoint where you have connected the Scanning Tool.
5. From the PI SYS drive, copy the SupportTool folder from the USB device onto your local drive.
6. In the appropriate Win32 or x64 folder, double-click the PISuprt.exe file.
7. Go to the **More Tools** tab.
8. Click the **Use for Updates** button.
9. Select **Apply Hot fix** and click **Next**. The **Apply New Component** screen will open.
10. Click **Browse** and select the .bin file from the service pack provided by TXOne.
11. Click **Apply**. A confirmation window will open.

Scan Action

The scan action setting determines what the scan will do.

- **Confirm:** The scan will identify security threats and then ask what action to perform.
- **Log only:** The scan will only identify security threats, without taking any action against them.
- **Take the recommended action:** The scan will automatically respond to security threats according to the recommendations of TXOne experts.

**Note:**

Depending on the type of threat, the scan will remove the security threat, place the file in quarantine, or skip over it. TXOne periodically reviews and revises the scanning tool's automatic responses, so they are subject to change after an update.

Asset Information

Assets can be acquired on both Windows and Linux systems following a scan conducted by the Scanning Tool.

Additionally, asset collection is possible after scanning. But the execution of the restore command is only possible on Linux systems.

Refer to the [Scanning Linux Endpoints \(on page 66\)](#) for details on all Linux systems-related commands.

It is essential to note that there may be slight variations in the assets obtained between these two operating systems.

Conditions

1. Asset information is collected only when the Scanning Tool is managed by ElementOne or the Management Program.

**Note:**

Refer to **Collect asset info during scanning** under **Scan Option** in [ST Scan Settings \(Basic\) \(on page 53\)](#) and **Auto Start** in [ST Scan Settings \(Others\) \(on page 55\)](#).

2. For Windows systems:

With the Management Program already installed on the machine, asset collection will not be possible. During Asset Collection the following Windows info data will be generated and may viewed and be saved as *.db or *.csv format using the Windows UI.

- Asset Details:

It serves as a repository for general host details in the system. See the table below.

- Application info:

Stores details about applications on hosts, including host id, application name, publisher, installed date, size, version, and install path.

- Update info:

Records updates for hosts or applications, including host id, name, program, version, publisher and installed date.

3. For Linux systems:

If you want the " OS Installed Date and Time " data of the asset shown, it is necessary to install "tune2fs" tool before collecting the asset.

It is not applicable if you have a "ZFS" file system with "tune2fs" already installed. During asset collection the following Linux info data will be generated and may viewed and be saved as *.db or *.csv format using the Windows UI.

- Asset Details:

It serves as a repository for general host details in the system. See the table below.

Item	Description
Host Name	The hostname of the asset.
Domain Name	Windows: The domain name of the logged-in user during the scan. Linux: This information will not be collected.
MAC Address	Windows: This column represents the MAC address of the asset. Linux: This column represents the MAC address of the default router interface.
IP Address	Windows: This column represents the first IPv4 address on the first adapter of the asset. Linux: This column represents the IPv4 address of the default router interface.
OS Desc	OS Description. The detailed operation system description of the asset.
OS Type	The operation system type of the asset.
Vendor Name	The name of the asset hardware vendor.
HW Model	The hardware model of the asset.
HW Serial Number	The hardware serial number of the asset.
BIOS Version and Date	The BIOS version and date of the asset.

Item	Description
BIOS Type	The BIOS type of the asset.
Secure Boot	The secure boot configuration of the asset. In the Linux system, to accurately determine whether Secure Boot is enabled, you need to install the “mokutil” tool.
CPU	The CPU name of the asset.
CPU Architecture	The architecture of the CPU on the asset.
Processors AND Core	The total number of processors and core of the CPU on the asset.
Physical Memory	The total amount of visible physical memory of the asset.
Available Memory	The total amount of available physical memory during the scanning of the asset.
OS Version and Build	The operating system’s version or build (kernel) number of the asset.
OS Service Pack	Windows: The installed operating system’s service pack of the asset. Linux: This information is not collected.
OS Product ID	The operating system’s product ID of the asset. Linux: This information is not collected.

Item	Description
OS Language	The operating system's language of the asset.
OS Installed Date and Time	The operating system's installed date and time of the asset.
IE Version and Build	Windows: The installed Internet Explorer version number or build number of the asset. Linux: This information is not collected.
IE Service Pack	Windows: The installed Internet Explorer service pack of the asset. Linux: This information is not collected.
IE Update Version	Windows: The updated version of Internet Explorer of the asset. Linux: This information is not collected.
Windows Directory	The directory where Windows is installed on the asset. Linux: This information is not collected.
System Directory	The directory where Windows system is located on the asset.
System Drive Size	The size of the drive where the Windows system is located on the asset the displayed units are in gigabytes (GB).
System Available Size	The amount of available space on the drive where the Windows system is located on the

Item	Description
	asset. The displayed units are in gigabytes (GB).
Boot Drive	Windows: The drive that contains the operating system on the asset. Linux: This information is not collected.
Time Zone	The time zone of the asset.
System Date and Time	The system date and time of the asset.
Logged-in Account	The name of the logged-in user during the scanning of the asset.
Logged-in Domain	Windows: The domain name of the logged-in user during the scanning of the asset. Linux: This information is not collected.
Meta data	◦ Bios uuid: The BIOS UUID of the asset. ◦ Mainboard sn: The serial number of mainboard on the asset. ◦ Machine id: A unique identifier assigned to the asset. ◦ IP addresses: All the IP address on the asset. ◦ MAC addresses: All the MAC address on the asset. ◦ USB: Includes USB information such as desc, instance_id, and manufacturer. ◦ CDROM: Includes CDROM information such as desc, instance_id, and manufacturer. ◦ Windows info: Includes Windows information such as osmajorversion, osmi-

Item	Description
	norversion, osbuildnumber,osubr, os-servicep ackmajor, osproducttype, sys-ProcessorArchitecture and smServerR2. ◦ Linux: USB, CDROM and Winodws_info are not collected.

- Application/Package info:

Stores details about applications and packages on hosts, including host id, application and package name, publisher, installed date, size, version, and install path.

Chapter 4. Using the Management Program

This chapter describes how to use and configure the Portable Inspector Management Program.

Understanding the Management Program Console

The Management Program console consists of tabbed screens and links to configure Scanning Tools, collect and view logs, and administer the console.

Table 3. Console Controls

Control	Description
Overview	Check the status of the components and perform an update, if needed. For more information, see the Overview Tab (on page 35) page.
Registered Scanning Tools	Configure the scan settings of all registered Scanning Tools managed by this Management Program. For more information, see Registered Scanning Tools (on page 39) page.
Plugged-in Scanning Tools	Check the status of the Scanning Tool devices currently plugged into the Management Program computer. For more information, see Plugged-in Scanning Tools (on page 43) page.
Logs and Reports	Check the results of earlier scans performed by the Scanning Tool. For more information, see Logs and Reports Tab (on page 44) page.

Table 3. Console Controls (continued)

Control	Description
Settings	Check or change the Management Program settings. For more information, see Management Program Settings (on page 46) page.
Help	Open the Help page and find more information about how to use the console.

Overview Tab


The Overview tab shows the Management Program status and enables changes to program settings.

Item	Description
Version	The build number of the Portable Inspector (Pro) Management Program. Click the Component versions link to see the component details and the date of the last update. For more information, see Checking the Latest Components (on page 36) page.
Last Update	The date of the last component update. • Scheduled Update: Enable to automatically update the Management Program components on the configured schedule. ◦ For more information, see the Scheduled Update (on page 38) page. • Update Now: Click to manually update the Management Program components.
Activation Code	The Activation Code currently used by the Management Program and Scanning Tools.

Item	Description
	• Edit: Click to change or update the Activation Code. • Refresh: Click this button when you have changed the Activation Code and it still says expired. • Do you need to manage another PI Pro license?: Click here to add a license for managing different versions of the Scanning Tool.
Expiration Date	The last day that the current Activation Code permits you to receive

Checking the Latest Components

To check the component version currently used and the date of the last update, click the **Component Version** link on the **Overview** tab.



Portable Inspector (Pro) Components

Portable Inspector uses the following components. To select the components to download, see [Scan Settings \(Others\)](#). *(on page 43)*

Table 4. Portable Inspector (Pro) Components

Component	Description
Virus Scan Engine (32-bit/64-bit)	The scan engine today is exceptionally sophisticated and capable of detecting different types of viruses and malware. The scan engine also detects controlled viruses that are developed and used for research. Rather than scanning every bit of every file, the engine and pattern file work together to identify the following: • Tell-tale characteristics of the virus code • The precise location within a file where the virus resides
Advanced Threat Scan Engine (32-bit/64-bit)	The Advanced Threat Scan Engine uses a combination of signature file-based scanning and heuristic rule-based scanning to detect document exploits and other threats used in targeted attacks. Major features include the following: 1. Detection of zero-day threats 2. Detection of embedded exploit code 3. Detection rules for known vulnerabilities 4. Enhanced parsers for handling file deformities
Behavior Monitoring Core Driver (32-bit/64-bit)	This prevents Portable Inspector from being affected by rootkits which hide drivers, processes, and

Table 4. Portable Inspector (Pro) Components (continued)

Component	Description
	registry entries from tools that use common system application programming interfaces (APIs).
Scanner (32-bit/64-bit)	This engine scans, cleans, and restores tasks.
Damage Cleanup Engine (32-bit/64-bit)	Scans for and removes Trojans and Trojan processes.
Virus Pattern	Contains information that helps Security Agents identify the latest virus/malware and mixed threat attacks.
Damage Cleanup Template	Used by the Virus Cleanup Engine to identify Trojan files and processes so the engine can eliminate them.
Spyware/Grayware Pattern	Identifies spyware/grayware in files and programs, modules in memory, Windows registry, and URL shortcuts.
Digital Signature Pattern	A list of approved programs that are regarded safe and will be excluded from scans.
Program Inspection Pattern	The pattern was designed to have the rule set for program inspection. The rule types include CLSID, file path, product name, company name, shortcut, and related registry. It also contains the fake AV detection rules. Currently it is used for fake AV detection for most cases, so it would also be the fake AV pattern.

Scheduled Update

Enable Scheduled Update to automatically download the most recent components at the scheduled times.

1. From the **Overview** tab, click the link beside **Scheduled Update**.

**Note:**

The link may show ON or OFF, depending on the current status of the update setting. If the link shows as **ON**, you have enabled scheduled updates. If the link shows as **OFF**, you have not enabled scheduled updates and will only get updates if you manually click the **Update Now** button.

2. Enable the **Use Scheduled Update** option.
3. Select the update frequency and the start time.
4. Click **Save**.
5. After making changes, the link in the **Overview** tab should reflect the change, showing whether the Scheduled Update option has been enabled or disabled.

Registered Scanning Tools

The **Registered Scanning Tools** tab displays a list of all registered Scanning Tools managed by this Management Program and provides the ability to change scan settings.

Section	Description
Standard Scanning Tool Setting	Displays a limited selection of settings currently applied to "Standard" Scanning Tools. Edit: Click to view or modify the scan settings for "Standard" Scanning Tool devices registered to the Management Program.
Scanning Tools List	Displays information about all the Scanning Tools registered to the Management Program. • Scanning Tool: Click the Scanning Tool name to view logs on the scans, synchronizations, and updates that the Scanning Tool has performed. • Scanning Tool ID: The unique ID of the Scanning Tool device. • Last Sync: The last time that the Scanning Tool synchronized data and settings with the Management Program. • Last Update: The last time that the Scanning Tool updated components.

Section	Description
	• Device Settings: Click to change between Standard (if the Scanning Tool uses the Standard Scanning Tool Setting) or Custom (to modify existing settings). • Lock: Click to lock or unlock the Scanning Tool user's ability to change settings directly from the Scanning Tool console.

Scan Settings (Basic)

Change the scan type, scan option, and scan action settings of the Scanning Tool device. You can change the following:

- **Scan Type:** Specify the folder locations to be scanned, whether to scan only file types vulnerable to malware.
 - **All local folders:** Scan all folders on the target endpoint.
 - **Default folders (Quick Scan):** Scan only the folders most vulnerable to system threats (such as the Windows System folder).
 - **Specific folders:** Limit the scan to the drives and folders you select.
- **Scan Option**
 - **Scan removable drives:** Select to scan any removable drives connected to the endpoint.
 - **Set to the lowest priority:** Select to reduce any performance impact on the endpoint but extend scanning times.
 - **Enable Suspend scan:** Select to display the Suspend button during scanning.
 - **Enable exploit detection:** Select to detect files exploiting known vulnerabilities in commercially available products based on the Common Vulnerabilities and Exposures (CVE) system.
- **Scan Action:** Specify what action the Scanning Tool should take after detecting a threat.
 - **Confirm:** Prompts user to confirm the action to perform.
 - **Log only:** Logs detected threats but takes no further action on them.
 - **Take the recommended action:** Automatically takes the TXOne recommended action per threat type.

**Note:**

Restart the Scanning Tool program for the changes to take effect.

Scan Type

Use the following settings to identify which drives and folders you want to scan.

**Note:**

Synchronize the settings to your device after making the changes in the Management Program.

- **All local folders:** Scan all folders on the target endpoint.
- **Default folders (Quick Scan):** Scan only the folders most vulnerable to system threats (such as the Windows System folder).
- **Specific folders:** Limit the scan to the drives and folders you select.

Scan Option

You can select additional options regarding scan priority and whether to scan removable drives.

- **Scan removable drives:** The Scanning Tool scans any removable storage connected to the endpoint.
- **Set to lowest priority:** The scanning process is set to the lowest priority to reduce system resource usage.

**Note:**

This may increase the scanning time.

- **Enable Suspend scan:** Displays the **Suspend** button during a scan, which allows users to pause the endpoint scan and resume the scan at a later time.

**Note:**

This affects the scanning time and stores temporary files on the endpoint.

- **Enable exploit detection:** Select to detect files exploiting known vulnerabilities in commercially available products based on the Common Vulnerabilities and Exposures (CVE) system.

Scan Settings (Advanced)

To access advanced scan settings of the Scanning Tool device, go to the **Advanced** tab.

- **Exclusion List:** Add files, folders, or file extensions to exclude from scans. Refer to [Changing the Exclusion List Settings \(on page 54\)](#) page.
- **Scan without saving temporary files:** Scans without saving files to the target computer. Enabling this option will prevent firmware upgrades for the Portable Inspector Scanning Tool. However, pattern and engine upgrades will not be affected.



Note:

This function is not applicable for scanning a Management Program computer.

- **Scan as Administrator:** Allows you to specify an administrator user name and password for users without administrative privileges.



Note:

You can use a backslash (\) or the at sign (@) to separate the user's name from the domain.

- **Compressed Layer:** Choose the number of compression layers and skip scanning any excess layers.



Note:

You can exclude up to 100 files and folders and use commas to exclude different extensions.

Additionally, you can do the following:

- Add a drive or folder to the list.
- Delete selected drives or folders from the list.
- Edit list items.



Note:

Synchronize the settings to your device after saving the changes you made to the configuration.

Scan Settings (Rescue Disk)

Changes the Rescue Disk settings for scan actions. You can change the following.

- **Scan and quarantine objects:** Select this option to quarantine detected threats in the local hard drive while scanning using the Rescue Disk. To be prompted before quarantine starts, select **Confirm before quarantine starts**.
- **Scan only:** Select this option to scan only, without quarantining any detected threats.

For more information, see [Rescue Disk \(on page 80\)](#) page.

Scan Settings (Others)

Change other settings for the Management Program. You can change the following:

- **Use Proxy Server:** Enable this option if your computer is required to use a proxy server to connect to the Management Program. Then choose one of the following options:
- **Import the Internet Explorer proxy settings:** Choose this option if you wish to use the same settings as those set for Microsoft™ Internet Explorer™ on the Management Program computer.
- **Enter the necessary proxy server settings in the following fields:** Choose this option to enter the proxy server settings yourself.
- **Program Components:** Click the **Settings** button to specify which components to download. For more information, see [Checking the Latest Components \(on page 36\)](#) page.
- **Log Deletion Lock:** If log deletion is locked, Scanning Tool is not allowed to delete logs before they have been synced with the Management Program.

Plugged-in Scanning Tools

The **Plugged-in Scanning Tools** tab allows you to view and manage any Scanning Tools currently plugged into the Management Program endpoint.

Item	Description
Change Name	Changes the name of the Scanning Tool.
Transfer Logs	Transfers logs from the Scanning Tool device to the Management Program.

Item	Description
	TXOne recommends selecting the confirmation dialog option, After transferring, delete the log file from the Scanning Tool , to keep the Scanning Tool disk space available.
Sync Components and Settings	Downloads components and settings from the Management Program to the Scanning Tool.
Scanning Tool list	Select a Scanning Tool to view synchronization and component update information.

Updating Components through a Scanning Tool

You can update the Management Program by importing components from a Scanning Tool which contains the latest components. This update method is suitable for scenarios that satisfy the following conditions:

- The Management Program is established in a closed network and does not have connectivity to the TXOne Active Update Server.
- The Scanning Tool has access to and contains the latest components.

Procedure: Updating Components through a Scanning Tool

1. Plug in the Scanning Tool device to the Management Program computer. The Management Program console opens automatically.
2. Click the **Plugged-in Scanning Tools** tab.
3. Select a Scanning Tool. When there are newer components on this device, these components will be indicated as 'newer', and the **Update Now** button will be accessible.
4. Click the **Update Now** button to start the update.

Logs and Reports Tab

The **Logs and Reports** tab allows you to import, export, and manage log data.

Item	Description
Import Logs	Imports database format logs that you exported from another Management Program.

Item	Description
Export Logs	Exports all scan logs to a database or CSV format.  Note: You must select Back up all scan data and logs (DB) if you want to import scan logs to another Management Program.
Delete Logs	Deletes specified scan logs.  Note: TXOne recommends exporting logs before performing the delete action.
Export Asset Info	Exports any asset information collected by the Scanning Tools in CSV format. • System and hardware information. • Update information (Microsoft applications only). • Installed application list.
Filter list results	• Computers: Lists scan logs based on computer name. • Scanning Tools: Lists scan logs based on Scanning Tool name. • Calendar: Filters scan log entries based on specified time frame.
View scan logs by Computer name	• Click the Computer name to view a list of all scan logs performed on that endpoint. • Click Last Scan time to view the scan results for the latest available scan data on the endpoint.

Item	Description
View scan logs by Scanning Tools name	• Click the Scanning Tool name to open a summary screen about the Scanning Tool device. ◦ Overview: Displays general information about Scan, Sync, and Update actions performed by the Scanning Tool. ◦ Scan: Lists all scan logs performed by the Scanning Tool. ◦ Sync: Lists information about log transfers and component updates on the Scanning Tool. ◦ Update: Lists information about the components updated on the Scanning Tool. ◦ Device Info: Displays the current component versions on the Scanning Tool. • Click Last Scan time to view the scan results for the latest available scan data transferred by the Scanning Tool.

Management Program Settings

- Click **Settings** > **Management Program Settings...** to make changes to how the Management Console connects to the Internet and Scanning Tools, and the source of component updates.
- Click **Settings** > **Import / Export Settings** to restore or back up Management Program settings.

General Settings

The **General** tab allows you to control Management Program settings including proxy, external communication authentication, and console language.



Note:

You must **Save** all changes before navigating to another screen or tab.



- **Use Proxy Server:** Enable this option if your computer is required to use a proxy server to connect to the Management Program. Then choose one of the following options:
 - **Import the Internet Explorer proxy settings:** Choose this option if you wish to use the same settings as those set for Microsoft™ Internet Explorer™ on the Management Program computer.
 - **Enter the necessary proxy server settings in the following fields:** Choose this option to enter the proxy server settings yourself.
- **Listening Settings:** Specify the Password and Port that the Management Program uses for communication with Scanning Tools attempting to connect remotely.

Update Settings

The **Update** tab allows you to change the source from which the Management Program receives component updates.



Note:

You must **Save** all changes before navigating to another screen or tab.

- **TXOne Active Update Server:** Obtain updates from the TXOne Active Update Server. Internet access is required.
- **Other update source:** Obtain updates from a specified source which can be located in a closed network.

Backing Up and Restoring Management Program Settings

TXOne recommends backing up your Management Program settings in case you need to migrate or restore the Management Program environment.

An export will include the following Management Program settings:

- Basic configurations
- A list of registered Scanning Tools
- Scanning Tools settings



Note:

The following settings are not included for export:

- Activation Code
- Security patterns and components
- Diagnostic Toolkit settings
- Management Program password and connection port

Exporting and Importing Management Program Settings

To access the settings, click **Settings** from the Management Program console, and click **Export Settings** or **Import Settings**.

Scan Settings

To change scan settings, click the **Scan** tab and click **Edit** from the Scanning Tool console.

Chapter 5. Using the Scanning Tool Console

This chapter outlines the features available on the various tabs of the Scanning Tool console.



Note:

This function is only available on Windows endpoints.

Scanning a Windows Endpoint

Use the **Scan** tab to manually start scanning an endpoint, monitor scan progress or change scan settings.

Procedure: Scanning a Windows Endpoint

1. Open the Scanning Tool console.
2. Click the **Scan** tab.
3. Click **Scan Now** to begin scanning the endpoint using the current scan settings.



Note:

To change scan settings before starting a scan, click the **Edit**. For more information, see [Scan Settings \(on page 48\)](#) page.

4. Refer to the LED lights on the Scanning Tool device to determine the scan status.

Table 5. Scanning Tool indicator lights

Indicator Light	Description
Blue (Blinking)	Information is being written to or retrieved from the Scanning Tool.
Blue	The scan is complete and Portable Inspector did not detect any threats.
Yellow	The scan is complete and Portable Inspector cleaned all detected threats.
Red	The scan is complete with detected threats that require further action.
Blue, Yellow, and Red (Continuous)	The Scanning Tool is currently scanning the endpoint.

5. Monitor the scan progress on the **Fix Problems** screen.

- Click **Stop** if you want to stop scanning the endpoint.
- Click **Suspend** if you want to suspend the current scan. Use the **Resume** button to resume the suspended scanning immediately after the Scanning Tool is relaunched.



Note:

The **Suspend** permission is only available if previously configured by the scan administrator.

For more information, see [Scan Settings \(Basic\) \(on page 40\)](#) page.

- **Apply Now** (threats detected): Click to apply actions on detected threats. For more information, see [Security Threats Found \(on page 57\)](#) page.
- **Comment**: Type a comment to add to the log entry for the scan.



Note:

TXOne does not recommend unplugging the Scanning Tool while the LED is flashing or while the Scanning Tool console is open.

6. The **Review Results** screen will display the following options after the scan is completed.

- **Scan again**: Click to return to the **Get Started** screen and begin a new scan of the endpoint.
- **Comment**: Type a comment to add to the log entry for the scan.
- **Close**: Exit the Scanning Tool console.

Procedure: Enable or Disable Asset Info Collection During Scanning

Enable Asset Info Collection During Scanning

1. From the **Scan** tab on the Scanning Tool console, click **Edit** in the **Scan Settings** column.
2. On the **Basic** tab, go to the **Scan Option** section and ensure **Collect asset info during scanning** is selected.
3. Click **Save** to apply the settings.



Note:

This option is enabled by default.

Disable Asset Info Collection During Scanning

1. From the **Scan** tab on the Scanning Tool console, click **Edit** in the **Scan Settings** column.
2. On the **Basic** tab, go to the **Scan Option** section and clear **Collect asset info during scanning**.

**Note:**

This option is enabled by default. Clear the checkbox to disable the function.

3. Click **Save** to apply the settings.

Procedure: Manually Start Asset Collection

1. From the **Scan** tab on the Scanning Tool console, click **Collect Asset Info** at the bottom of the page.
2. Wait for the asset collection to complete.
3. When completed, a message box displays the result and the asset name.

**Note:**

- You can edit the asset name in the text box if needed.
- If the process fails, the message **Asset Collection Failed** is displayed. Try again.

4. Click **OK**.

Procedure: Enable or Disable Auto Start for Scanning or Asset Info Collection

Enable Auto Start for Scanning or Asset Info Collection

1. From the **Scan** tab on the Scanning Tool console, click **Edit** in the **Scan Settings** column.
2. On the **Others** tab, go to the **Auto Start** section and ensure **When Portable Inspector is launched, it automatically starts scanning or collecting asset information** is selected.

**Note:**

This option is enabled by default.

3. Select one of the following options:
 - **Start scanning automatically**
 - **Start collecting asset information automatically**

**Note:**

If the auto start option is not selected, the two start options are hidden.

4. Enter a value between **1 and 30** in **Countdown before start**.

**Note:**

The countdown is in seconds and defaults to 30. Set a value between 1 and 30 as needed.

5. Click **Save** to apply the settings.

Disable Auto Start for Scanning or Asset Info Collection

1. From the **Scan** tab on the Scanning Tool console, click **Edit** in the **Scan Settings** column.
2. On the **Others** tab, go to the **Auto Start** section and clear **When Portable Inspector is launched, it automatically starts scanning or collecting asset information**.

**Note:**

This option is enabled by default. Clear the checkbox to disable the function.

3. Click **Save** to apply the settings.

Procedure: Manually Stop Auto Start for Scan or Asset Info Collection

After auto start for scanning or asset info collection is enabled, a countdown is displayed on the **Scan** tab when the Scanning Tool launches. The selected action starts when the countdown ends.

**Note:**

Refer to *Procedure: Enable or Disable Auto Start for Scanning or Asset Info Collection* for details.

To stop the auto start process, follow the steps below:

1. On the **Scan** tab, click the corresponding button displayed with the countdown:
 - If auto start scanning is enabled, click **Stop Auto Scan**.
 - If auto start asset info collection is enabled, click **Stop Auto Collection**.
2. In the confirmation message, click **OK**.
3. When stopped, one of the following messages is displayed on the **Scan** tab:

- Auto Scan stopped
- Auto Collection stopped

**Note:**

Click *Scan Now* or *Collect Asset Info* to start the action manually if needed.

ST Scan Settings

To change scan settings, click the Scan tab and click Edit from the Scanning Tool console.

ST Scan Settings (Basic)

Change the scan type, scan option, and scan action settings of the Scanning Tool device. You can change the following:

- **Scan Type:** Specify the folder locations to scan.
 - **All local folders:** Scan all folders on the target endpoint.
 - **Default folders (Quick Scan):** Scan only the folders most vulnerable to system threats (such as the Windows System folder).
 - **Specific folders:** Limit the scan to the drives and folders you select.
- **Scan Option**
 - **Collect asset info during scanning:** Select to collect asset information during the scan.

**Note:**

- This function is available when managed by ElementOne and can be configured through ElementOne or the Scanning Tool. In Management Program mode, it can only be configured on the Scanning Tool and is not available in the Management Program. It is also not available on the Standalone Scanning Tool.
- For detailed instructions, refer to *Procedure: Enable or Disable Asset Info Collection During Scanning* in the *Portable Inspector User's Guide* and the *ElementOne User's Guide*.

- **Scan removable drives:** Select to scan any removable drives connected to the endpoint.
- **Set to the lowest priority:** Select to reduce any performance impact on the endpoint but extend scanning times.

- **Enable Suspend scan:** Select to display the **Suspend** button during scanning.
- **Enable exploit detection:** Select to detect files exploiting known vulnerabilities in commercially available products based on the Common Vulnerabilities and Exposures (CVE) system.
- **Scan Action:** Specify what action the Scanning Tool takes after detecting a threat.
 - **Confirm:** Prompts user to confirm the action that is to be taken.
 - **Log only:** Logs detected threats but takes no further action on them.
 - **Take the recommended action:** Automatically takes the TXOne recommended action per threat type.

ST Scan Settings (Advanced)

To access advanced scan settings of the Scanning Tool device, go to the **Advanced** tab.

- **Exclusion List:** Add files, folders, or file extensions to exclude from scans. Refer to [Changing the Exclusion List Settings \(on page 54\)](#) page.
- **Scan without saving temporary files:** Scans without saving files to the target computer.



Note:

Using this option reduces scanning capability for certain types of malware.

- **Scan as Administrator:** Allows you to specify an administrator user name and password for users without administrative privilege.



Note:

You can use a backslash (\) or the at sign (@) to separate the user's name from the domain.

- **Number of Compressed Layers to Scan:** Choose the number of compression layers and skip scanning any excess layers.

Changing the Exclusion List Settings

Use this setting to exclude files, folders, or extensions from being scanned.



Note:

You can exclude up to 100 files and folders and use commas to exclude different extensions.

Additionally, you can do the following:

- Add a drive or folder to the list.
- Delete selected drives or folders from the list.
- Edit list items.

**Note:**

Synchronize the settings to your device after saving the changes you made to the configuration.

ST Scan Settings (Rescue Disk)

Changes the Rescue Disk settings for scan actions. You can change the following:

- **Scan and quarantine objects:** Select this option to quarantine detected threats in the local hard drive while scanning using the Rescue Disk. To be prompted before quarantine starts, select **Confirm before quarantine starts**.
- **Scan only:** Select this option to scan only, without quarantining any detected threats.

For details on Rescue Disk, refer to [Rescue Disk \(on page 80\)](#) page.

ST Scan Settings (Others)

Change other settings for the Scanning Tool device. You can change the following:

- **Proxy Server:** Enable this option if your computer is required to use a proxy server to connect to the Internet. Then choose one of the following options:
 - **Import the Internet Explorer proxy settings:** Choose this option if you wish to use the same settings as those set for Microsoft™ Internet Explorer™.
 - **Enter the necessary proxy server settings in the following fields:** Choose this option to enter the proxy server settings yourself.
- **Device Name Controlled By: Portable Inspector or ElementOne.**

If the Portable Inspector is managed by ElementOne, you can name a Portable Inspector using either the Scanning Tool or the ElementOne console.

If you are using the Scanning Tool, follow the steps below to select a console for naming a Portable Inspector.

1. From the Scanning Tool, go to the **Scan** Tab, click on **Edit** from the **Scan Settings** section.
2. From the **Scan Settings**, go to the **Others** tab.
3. Under the **Others** tab, go to the section **Device Name Controlled By**, select either **Portable Inspector** or **ElementOne** as the console to update the name of Portable Inspector.

For the details about naming a Portable Inspector using the Scanning Tool, go to Section [Status & Update Tab \(on page 61\)](#).

- **Pattern Outdate Alert:**

When enabled, an alert will be displayed when launching the Scanning Tool console if the antivirus pattern is outdated beyond the configured time period. The time units **Hour(s)**, **Day(s)**, and **Week(s)** are supported for configuration.

Pattern Outdate Alert can be configured through either the Scanning Tool console or the ElementOne Policy page.

- **Scan Restriction:**

When enabled, the Portable Inspector device will prevent scanning from starting if the antivirus pattern is outdated beyond the configured time period. The time units **Hour(s)**, **Day(s)**, and **Week(s)** are supported for configuration.

Scan Restriction can be configured through either the Scanning Tool console or the ElementOne Policy page.

- **Auto Start:**

Automatically start scanning or asset information collection when Portable Inspector is launched, with a configurable countdown of 1 to 30 seconds.

- **When Portable Inspector is launched, it automatically starts scanning or collecting asset information:** Select to enable auto start.
 - **Start scanning automatically:** Select to automatically start scanning after launch.
 - **Start collecting asset information automatically:** Select to automatically start asset information collection after launch.
 - **Countdown before start:** Specify the delay before the selected action starts. The value must be between **1 and 30 seconds**.

**Note:**

- This function is available when managed by ElementOne and can be configured through ElementOne or the Scanning Tool. In Management Program mode, it can only be configured on the Scanning Tool and is not available in the Management Program.
- For detailed instructions, refer to *Procedure: Enable or Disable Auto Start for Scanning or Asset Info Collection* in the *Portable Inspector User's Guide* and the *ElementOne User's Guide*.

Security Threats Found

If the scan finds a threat, review the results before selecting an option.

Procedure: Security Threats Found

1. Check the name of the file and the risk, then select a response from the Action column, or just keep the default response.
 - **Ignore:** Portable Inspector will not take any action against the threat.
 - **Fix:** Portable Inspector will respond to the threat by trying to clean or quarantine the file involved.

**Note:**

The exact response depends on the type of threat detected. TXOne periodically reviews and revises the automatic responses to different threats, so they may change after a pattern file or scan engine update.

2. Click **Apply Now**.

**Note:**

You can click **Scan Again** to check for security threats once more.

3. After confirming that no more security threats were found, you can add some notes about the scan in the **Comment** field, and then click **Close**.

**Note:**

You can type up to 63 characters in the **Comment** field. This information will appear along with the log data in the scan results. The name of the computer is the default value of this field.

Restoring Quarantined Files

You can restore files if Portable Inspector fixed and quarantined files that you need.

**Note:**

Restoring these files may put your security at risk. You have to be very sure that the files are NOT infected before restoring the files because TXOne does not guarantee the safety of your devices if you restore infected files.

1. Open the Scanning Tool console.
2. Go to the **Restore** tab.
3. Select the date and time of the scan from the drop-down list next to **Last scan started** and the files that were quarantined during that scan will appear.
4. Select the file and click **Restore**.

**Note:**

Restoring files can be only performed on a computer after Portable Inspector has quarantined a file and the files can only be restored on the same computer.

5. Click **OK** to confirm.

**Note:**

You must be absolutely sure that the file is essential and that the file is not infected.

6. Click **Close**.

Restore Tab

**Note:**

You can store quarantined files on the USB device instead of on the target computer, but you cannot use the Scanning Tool to store other files.

- **Last scan started:** Select the time that the scan was performed to view the logs and actions done at that time.
- **Scan:** This function is enabled for files that are tagged "Ignored" or "Unable to fix".

Selecting **Scan** opens a confirmation message box for users to choose the appropriate scan action to apply to the selected file(s).


- **Restore:** Select a file or files and click this button to put the file back and leave it in its original location. Refer to [Restoring Quarantined Files \(on page 58\)](#) page.

**Note:**

Restore files only if you are sure that the file is not infected.

Logs Tab

To view results for each scan, select **Scan logs** and click an item from the Time column.




- **Import Logs:** Click this button to import database format logs.
- **Export All:** Click this button to export all the logs into the database or CSV format.
- **Delete All:** Click this button to delete all log entries.
- **Equipment Security Inspection Report:** Click **Export** under each scan log to save it as a PDF file.




Note:

- After clicking **Export**, a message box will appear asking whether you want to include asset information in the report. Select the **Include Asset Information** checkbox if needed, then click **Export** to generate a PDF report.
- A report that includes asset information contains asset details and a list of installed applications, including the application name, version, and more. For example, if your asset runs on Windows, the report will include three additional sections



Status & Update Tab

The **Status & Update** tab shows the device component status. For more information on the device activation status, refer to [Activation \(on page 22\)](#) page.



- **Device Name:** This is the name of the Scanning Tool.
- **Rename:** If you selected Portable Inspector's Scanning Tool console to control the device name (refer to Section [ST Scan Settings \(Others\) \(on page 55\)](#)), you can click the **Rename** button to update the device name.

**Note:**

- When ElementOne is set to control the device name, the **Rename** button is hidden in the Scanning Tool.
- The device name can contain up to 64 characters. The characters \ / | " , . ? [] < > * + = ; : are not allowed.

- **Scanning Tool ID:** The Scanning Tool ID is a unique identification number given to every Scanning Tool device.
- **Version:** The build number of the Portable Inspector Scanning Tool appears next to **Version**. Click the **Component versions** link to see the component details and the date of the last update.
- **Last Update:** Shows the update status. Click **Update Now** to manually update the Scanning Tool for the latest components and hotfix.
- **Activation Code:** Click **Edit** to change or update the activation code. For more information, see [Changing the Activation Code \(on page 19\)](#) page.
- **Expires:** Shows the expiration date of the activation code. Click **Refresh** to check for a new expiration date.

Component Updates

Make sure to update your Scanning Tool for the most recent security pattern file or scan engine from TXOne. Click the **Components versions** to check the current version and the date of the last update.

**Note:**


Update the Scanning Tool whenever required.

1. Plug in the Scanning Tool on a computer with access to the updated source.

**Note:**

For details on update source settings, refer to [Changing the Scanning Tool Settings \(on page 63\)](#) page.

2. From the Scanning Tool console, go to the **Status & Update** tab.
3. Click **Update Now**.



Changing the Scanning Tool Settings

Configure the update source and language settings of your Scanning Tool.

1. Open the Scanning Tool console.
2. Click **Settings**.




Note:

The Management Program settings are automatically disabled for the Standalone Scanning Tool.

3. Specify an update source.
 - **TXOne ActiveUpdate Server:** Obtain updates from the TXOne ActiveUpdate Server. Internet access is required.
 - **Other update source:** Obtain updates from a specified source which can be located in a closed network.

4. (Optional) Select a language from the drop-down menu to change the Scanning Tool language.
5. Click **Save**.



The image shows a 'Scanning Tool Settings' dialog box. At the top, it says 'Specify the Management Program IP address, password, and port to sync the Scanning Tool settings with your Management Program or to another Management Program.' Below this, there are fields for 'Management Program: Address' (containing 'DESKTOP-8BS7K2L'), 'Port' (containing '10240'), and 'Password' (masked with dots). A 'Register' button is next to the password field. Under 'Update Source:', there are three radio button options: 'Management Program' (selected), 'TXOne ActiveUpdate Server (Internet required)' (with URL 'https://ttau.cs.txone.com/pi'), and 'Other update source' (with a text input field containing 'https://'). A note below the radio buttons states: 'Update source is used to check and download the latest scan engine and components.' At the bottom left, there is a 'Language:' dropdown menu set to 'English' and a 'Log Visibility:' button set to 'Password Protect'. At the bottom right, there are 'Save' and 'Cancel' buttons.


Renaming an Asset

By default, an asset is named after its hostname. The hostname can be replaced with a custom alias (up to 64 chars) to rename the asset.

The alias is included in the sync procedure with ElementOne, and any asset name changes will be reflected on ElementOne.

1. Perform a scan.
2. Scan result will be shown on Review Results tab, along with Asset Name text field.

3. Type the new name in the **Asset Name** field.



The screenshot shows the 'Portable Inspector' application window. The title bar reads 'Portable Inspector'. The main header is 'Scanning Tool' with the 'txOne networks' logo on the right. Below the header is a navigation bar with tabs: 'Scan', 'Restore', 'Logs', and 'Status & Update'. A 'Settings' link is visible on the right. The main content area has three steps: '1. Get Started', '2. Fix Problems', and '3. Review Results'. The '3. Review Results' step is active. It contains an 'Asset Name' field with the value 'LAB-A'. Below this is a 'Summary' section with a green checkmark icon and the text 'No threats found'. At the bottom, there is a 'Comment:' field with the text 'No threats found', and two buttons: 'Scan Again' and 'Close'.

Portable Inspector

Scanning Tool

txOne networks

Scan Restore Logs Status & Update [Settings](#)

1. Get Started 2. Fix Problems 3. Review Results

Asset Name

Summary

✓ No threats found

Comment:

Chapter 6. Scanning Linux Endpoints

This chapter outlines how to use the Scanning Tool device to scan Linux endpoints.



Note:

Before you can use a Scanning Tool on a Linux endpoint, you must activate the Scanning Tool device on a Windows endpoint, in either standalone mode or through the Management Program.

For more information, see [Activation \(on page 22\)](#) page.

Linux System Requirements

<https://help.txone.com/docs/portable-inspector-system-requirements>

Linux Command Line Reference

After mounting the Scanning Tool folders, you must perform all actions using the Linux command line.

Usage:

- **sudo sh ./LauncherLinux.sh -c scan [<scan options>] <scan targets>**
- **sudo sh ./LauncherLinux.sh -c scan_all**
- **sudo sh ./LauncherLinux.sh -c restore**

Command Structure	Description
Command	• -c --command < scan <scan targets> scan_all restore> • -h --help Displays the Help screen
<scan options>	• -a --action <action> Scan action that overrides default configuration settings: log confirm recommended

Command Structure	Description
<scan targets>	Specify folder location or full file path. Separate multiple targets using the white-space character.

Scanning a Linux Endpoint for Security Risks

This task assumes that your Linux environment supports the auto-mounting of USB drives. If your Linux environment does not support auto-mounting, refer to your Linux documentation to learn how to manually mount a USB device.



Note:

Before you can use a Scanning Tool on a Linux endpoint, you must activate the Scanning Tool device on a Windows endpoint, in either standalone mode or through the Management Program.

For more information, see [Activation \(on page 22\)](#) page.

1. Plug the Scanning Tool device into the target Linux endpoint on which you have “root” or “sudo” privilege.

The endpoint auto-mounts the device and the PI DAT and PI SYS drives appear on the screen.

2. Open the PI SYS drive.
3. Right-click anywhere within the folder (but not on a file or folder icon) and click **Open in Terminal**.
The terminal opens pointing to the PI SYS directory.
4. Scan the endpoint through use of the following command structure:

sudo sh ./LauncherLinux.sh -c scan [<scan options>] <scan targets>

- a. To scan the entire endpoint using the Management Program settings, type the following:

sudo sh ./LauncherLinux.sh -c scan_all

- b. To scan all files in the /tmp folder and perform the “recommended” action, type the following:

sudo sh ./LauncherLinux.sh -c scan -a recommended /tmp

**Note:**

- For more information about the available options, see [Linux Command Line Reference \(on page 66\)](#) page.
- When managed by ElementOne, **Pattern Outdate Alert** and **Scan Restriction** apply to Linux endpoints. Alerts may be displayed, or scanning may be restricted, if the antivirus pattern is outdated beyond the configured time period. For more information, refer to **Pattern Outdate Alert** and **Scan Restriction** in [ST Scan Settings \(Others\) \(on page 55\)](#).

5. The Scanning Tool begins scanning the endpoint.
6. Allow some time to allow the scan to complete or press CTRL-C to cancel an on-going scan.
7. If the configured scan action is **Confirm**, Portable Inspector prompts you for an action after detecting a threat.
 - **f**: Portable Inspector attempts to clean or quarantine the detected threat.
 - **I**: Portable Inspector takes no action on the detected threat.
 - **F**: Portable Inspector attempts to clean or quarantine all detected threats
 - **I**: Portable Inspector takes no action on any detected threat.
8. Portable Inspector displays the scan results and action results, and saves the scan logs to the Scanning Tool device.

Restoring Files on a Linux Endpoint

This task assumes that your Linux environment supports the auto-mounting of USB drives. If your Linux environment does not support auto-mounting, refer to your Linux documentation to learn how to manually mount a USB device.

1. Plug the Scanning Tool device into the target Linux endpoint on which you have “root” or “sudo” privilege. The endpoint will auto-mount the device and the PI DAT and PI SYS drives will appear on the screen.
2. Open the PI SYS drive.
3. Right-click anywhere within the folder (but not on a file or folder icon) and click **Open in Terminal**. The terminal will open, pointing to the PI SYS directory.
4. Restore files on the endpoint through use of the following command structure:

```
sudo sh ./LauncherLinux.sh -c restore
```

The Scanning Tool will display a list of previous scan logs for the endpoint.

5. Type the scan log **Index** that you want to restore files from. The Scanning Tool will display a list of quarantined files.
6. Type the quarantined file **Index** that you want to restore. The Scanning Tool will restore the quarantined file to the endpoint.
7. Portable Inspector will display the action result and will save the logs to the Scanning Tool device.

Performing Debug Logging on Linux Systems

If you encounter errors while scanning a Linux endpoint, you can enable debug logging and send the logs to your TXOne representative for troubleshooting.

1. Plug the Scanning Tool device into the target Linux endpoint on which you have “root” or “sudo” privilege. The endpoint will auto-mount the device and the PI DAT and PI SYS drives will appear on the screen.
2. Open the PI SYS drive.
3. Right-click anywhere within the folder (but not on a file or folder icon) and click **Open in Terminal**. The terminal will open pointing to the PI SYS directory.
4. Scan the endpoint using the following command:

```
[root@localhost]# sudo sh ./LauncherLinux.sh --debug -c scan <scan targets> > /tmp/pi.log 2>&1
```

5. The Scanning Tool will begin scanning the endpoint, recording all log data to the /tmp/pi.log file, and displaying status messages on the console.
6. After scanning completes, execute the following command to collect additional log information:

```
[root@localhost]# sudo dmesg > /tmp/dmesg.log
```

7. Copy the following log files and send the files to your TXOne representative:
 - /tmp/pi.log
 - /tmp/dmesg.log
 - /var/log/syslog

Viewing Linux Scan Logs

You cannot directly view the entire scan logs using a Linux endpoint. To view complete scan logs, plug the Scanning Tool into a Windows endpoint or an endpoint with the Management Program installed.

Chapter 7. Using the Secure Storage Console

This chapter describes the features available in the **Secure Storage console** on Portable Inspector Pro.



Note:

The Secure Storage console is available only on **Windows endpoints**.

The Secure Storage console supports two storage modes:

- User Data mode
- Distributed mode

User Data Mode

User Data mode allows users to manually transfer files and folders into Secure Storage. Files transferred in this mode are scanned by Portable Inspector before being saved.

Transfer Files

Secure Storage is a unique type of storage because when users drag and drop files/folders to the window, PI Pro will scan them. It will then allow only clean data to be saved in storage.

- **Last Update:** Shows the last time that the pattern was updated.



Note:

The pattern and update settings are shared between the Scanning Tool console and Secure Storage console, which means any pattern update or setting changes made in one console will affect the other.

- **Block History:** Check the history of malware discovered during file transfers.
- **Working Area:** Use the working area to transfer your files in or out of Secure Storage.



Note:

When you launch Secure Storage for the first time, you will be asked to set up a password for Secure Storage.

Procedure: Transfer files

1. Open the Secure Storage console by double-clicking **SecureStorage.exe** in the **PI SYS** folder.

**Note:**

When launching Secure Storage for the first time, set a password. A maximum of **16 characters** is allowed.

2. Drag files or folders from your system into the Secure Storage working area.
3. Portable Inspector scans the files before transferring them into Secure Storage. Refer to the indicator lights on the Portable Inspector device to determine the scan status.

Table 6. Portable Inspector Indicator Lights

Indicator Light	Description
Blue (Blinking)	Secure Storage is launching or closing.
Blue (Continuous)	Files were transferred and no threats were found.
Red (Continuous)	Threats were detected and blocked.
Blue, Yellow, and Red (Continuous)	File transfer is in progress.

Block History

The **Block History** section records malware events detected during file transfers.

- **Export all:** Exports all malware event logs to a database or CSV format.

**Note:**

You must select **Backup all scan data and logs (DB)** if you want to import scan logs to another Management Program.

- **Delete all:** Deletes all event logs.

**Note:**

TXOne recommends exporting logs to back them up before deleting them.

Distributed Mode

Distributed mode displays files that are securely distributed from ElementOne to the Portable Inspector device through the **Secure Distribute** feature. Files are uploaded, scanned, and distributed through ElementOne, and are synchronized to the Portable Inspector device when users perform a **sync** operation in the Secure Storage console. Distributed files cannot be modified manually on the Portable Inspector device.

**Note:**

For more information about Secure Distribute configuration and behavior, refer to the **Secure Distribute** section in the **ElementOne User's Guide**.

Sync Distributed Files

1. In the Secure Storage console in **Distributed** mode, click the **Sync** button in the upper-right corner.
2. Wait for the synchronization process to complete.

**Note:**

- While syncing is in progress, you can click **Stop** in the message box to cancel the synchronization. A **Sync Canceled** message will be displayed.
- If Secure Storage does not have enough capacity to store the distributed files, an error message will be displayed.

3. If all files are synchronized successfully, click **OK** to close the message box.

**Note:**

If an error occurs during synchronization, an error message will be displayed. Click **More Details** to view the file paths and the reasons for synchronization failures.

4. After synchronization with ElementOne is complete, the distributed items will appear in the **Secure Storage** console. Users can navigate to **PI SEC > Distributed** to view and access the distributed files.

**Note:**

Any updates, removals, or redistribution of distributed files are controlled by **ElementOne**.

Status Information

- The lower-left corner of the Secure Storage console displays the **device name** and **Portable Inspector version**.
- The **Last File Sync Time** with ElementOne is also shown.
- If a synchronization error occurs, a **warning icon** will appear next to the Last File Sync Time.

Switch Back to User Data Mode

There are two scenarios in which users may access or switch from **Distributed** storage to **User Data** storage, depending on how the storage mode is configured.

Scenario 1: Switching Modes from ElementOne Policy Settings

This scenario applies when the storage mode is changed through **ElementOne**.

1. Go to the ElementOne Device Policy page.
2. Navigate to the **Storage Allocation** section and change the mode from **Distributed** to **User Data**.
3. Restart the Secure Storage console.

After the Secure Storage console restarts, it synchronizes the latest storage mode setting from ElementOne. Portable Inspector then switches to **User Data** mode, automatically cleans up the **Distributed** storage, and restores access to **User Data** storage.

Scenario 2: Accessing User Data Storage from the Secure Storage Console

This scenario applies when **data already exists in User Data storage** and the storage mode has previously been set to **Distributed** through ElementOne.

When you open the Secure Storage console, the **Distributed** page is displayed because the storage mode is set to **Distributed** in ElementOne.

To access User Data storage:


In the Secure Storage console, click the **Distributed** button in the upper-left corner to switch to the **User Data** page.

This action only switches between pages in the Secure Storage console. It does **not** change the storage mode, and no data is cleaned up.

You can view, copy, delete, and manage existing data stored in **User Data** storage, and the data continues to consume Secure Storage capacity.

Change Password

Please find this function under the password authentication field.



Reset Secure Storage

Reset Device affects both the **Scanning Tool** and **Secure Storage**. Before resetting the device, make sure that any data you want to keep is backed up.

When a **program reset** or **factory reset** is performed, all data in **PI SEC** is cleared, regardless of whether the device is in **User Data** mode or **Distributed** mode.

After the reset, when you open the **Secure Storage** console, you will be prompted to reset the Secure Storage password.

For detailed instructions, refer to the [Reset Device \(on page 78\)](#) page.

Lost Password

If you lose your password, Secure Storage will be locked until Portable Inspector has been reset. See [Reset Device \(on page 78\)](#) page for more details.

Maximum Number of Password Attempts Exceeded

If you exceed the maximum number of password attempts permitted, Secure Storage will be locked until Portable Inspector has been reset. Please refer to [Reset Device \(on page 78\)](#) page for more details.

Secure Storage Controller for Linux

This task assumes that your Linux environment supports the auto-mounting of USB drives. If your Linux environment does not support auto-mounting, refer to your Linux documentation to learn how to manually mount a USB device.

1. Plug the Scanning Tool device into the target Linux endpoint on which you have “root” or “sudo” privilege. The endpoint auto-mounts the device and the PI DAT and PI SYS drives appear on the screen.
2. Open the PI SYS drive.
3. Right-click anywhere within the folder (but not on a file or folder icon) and click **Open in Terminal**. The terminal opens pointing to the PI SYS directory.
4. Linux users can get access to Secure Storage through the Linux shell.



Note:

Secure Storage on Linux is mounted in read-only mode. Users cannot write, modify, or transfer files or folders to Secure Storage. Full functionality is supported only on Windows platforms.

Usage:

◦ **sudo sh ./SecureStorageLinux.sh**



Note:

A password must be set before use.

Portable Inspector Secure Storage Controller for Linux

0. Exit

1. Login SEC

```
2. Logout SEC
```

```
Please enter your selection:
```

Select Login SEC and input the password. After successful login, mount the Secure Storage (PI SEC) manually if it does not occur automatically. Please refer to your Linux documentation to learn how to manually mount a USB device.

```
Portable Inspector Secure Storage Controller for Linux
```

```
0. Exit
```

```
1. Login SEC
```

```
2. Logout SEC
```

```
Please enter your selection: 1
```

```
Please enter the password:
```

```
Login successful.
```

Select Logout SEC to unmount Secure Storage.

```
Portable Inspector Secure Storage Controller for Linux
```

```
0. Exit
```

```
1. Login SEC
```

```
2. Logout SEC
```

```
Please enter your selection: 2
```

```
Logout successful.
```

Chapter 8. Additional Tools

This chapter discusses how to use the additional tools provided with Portable Inspector (Pro).

Portable Inspector Diagnostic Toolkit

Use the Portable Inspector Diagnostic Toolkit to diagnose and troubleshoot problems. Portable Inspector (Pro) automatically includes the toolkit during installation, and you can access the toolkit from the Windows Start Menu.

Debug

Use the **Debug** tab to generate debug logs for troubleshooting issues with the product.

- Generate Debug Logs for Installation Issues

Follow the steps below to generate debug logs for installation issues with Scanning Tool Agent.

1. From the Start menu of the Portable Inspector (Pro) endpoint, click **TXOne Portable Inspector > Portable Inspector Diagnostic Toolkit**.
 - a. Plug in the Portable Inspector (Pro) Scanning Tool to the endpoint.
 - b. Copy the SupportTool folder from the USB device into your local drive.
 - c. Double-click the PISuprt.exe file.
2. In the **[A] Debug** tab, select **Diagnose installation issues** and click **Start**.
3. Click **Collect Data**.
4. Click **Finish**.
5. Click **Open Folder**.

- Generate Debug Logs for Portable Inspector Devices

1. Plug in the Portable Inspector (Pro) Scanning Tool to the endpoint.
2. On the PI SYS drive, navigate to the SmallDebugTool folder.
3. Launch SmallDebugTool.exe to collect logs.
 - a. Double-click the SmallDebugTool.exe file.
 - b. According to your situation, choose **Scanning Tool** or **Secure Storage** and click **Start**.
 - c. Reproduce the problem encountered by Portable Inspector (Pro).
 - d. After the problem has been reproduced, enable **Troubleshooting data has been collected**.
 - e. Click **Stop Debugging Mode**.

- f. Click **Transfer Data**. The program will start transferring the logs to the Scanning Tool. It may take a while for the process to complete.
 - g. Click **Close**.
4. Remove the Scanning Tool from the endpoint and plug it into an endpoint that has Portable Inspector (Pro) installed.
5. Launch the Portable Inspector Diagnostic Toolkit.
 - a. From the Start menu of the Portable Inspector (Pro) endpoint, click **TXOne Portable Inspector > Portable Inspector Diagnostic Toolkit**.
 - b. If you are using a different endpoint, you can do the following:
 - i. Plug in the Portable Inspector (Pro) Scanning Tool to the endpoint.
 - ii. Copy the SupportTool folder from the USB device into your local drive.
 - iii. Double-click the PISuprt.exe file.
6. Use the Portable Inspector Diagnostic Toolkit to export the logs.
 - a. In the **Debug** tab, select **Load logs from the Scanning Tool**, and click **Start**.
 - b. Connect the Scanning Tool to the endpoint and click **Next**. The Diagnostic Toolkit will display the storage path of the logs.
 - c. Click **Open Folder** to navigate to the path.
 - d. Locate and open the zip file to verify that the debug logs have been successfully generated.

Reset Device

You can use the Portable Inspector Diagnostic Toolkit to reset the device to either program or factory settings.

You also need to reset the device if you want to change the current Scanning Tool mode. For example, if the Scanning Tool is currently a Standalone tool, you need to reset the device to be able to change the mode and register to the Management Program.

There are two reset modes:

- **Program Reset:** Select this option if the Scanning Tool is not working because some components might be damaged. This mode retains the activation code and status.
 1. Plug in the Portable Inspector Scanning Tool to the endpoint.
 2. Copy the SupportTool folder from the USB device into your local drive.
 3. Double-click the PISuprt.exe file.
 4. Go to the **More Tools** tab.
 5. Click the **Reset Device** button.
 6. Select **Default Program Settings** and click **Next**.

7. Confirm the reset.



Note:

Do not unplug the Scanning Tool until the reset process has been completed and a pop stating "You have successfully reset the device" appears.

8. Unplug and then plug in the device again to verify that the Scanning Tool has been reset.

• **Factory Reset:** Select this option to reset to factory status.

1. Plug the Portable Inspector Scanning Tool into the endpoint.
2. From the PI SYS drive, copy the SupportTool folder from the USB device onto your local drive.
3. In the appropriate Win32 or x64 folder, double-click the PISuprt.exe file.
4. Go to the **More Tools** tab.
5. Click **Reset Device**.
6. Select **Default Factory Settings** and click **Next**.
7. Copy the Activation Code, and select the **Finished saving the Activation Code** option.
8. Click **Yes**.



Note:

Do not unplug the Scanning Tool until the reset process has been completed and a pop stating "You have successfully reset the device" appears.

9. Remove and reinsert the device, then execute Launcher.exe to verify that the Scanning Tool has been reset.

10. The Scanning Tool Mode will appear after the Scanning Tool has been successfully reset.



Note:

- You can only reset one device at a time.
- The Portable Inspector Diagnostic Toolkit does not support resetting any previous versions of Trend Micro Portable Security Scanning Tools.

Support Updates

Use the **Portable Inspector Diagnostic Toolkit** to apply hotfixes or bandage patterns to the Scanning Tool, if needed.

**Note:**

- These updates can only be applied to one device at a time.
- Bandage patterns are pre-released versions of a virus pattern, for emergency antivirus protection. These patterns are not publicly available because these have not been fully tested. Apply **ONLY** those provided by TXOne Premium Support and only to the devices specified.

Applying Hot Fixes

Hotfixes are workarounds or solutions to customer-reported issues. TXOne provides hotfixes to individual customers. Hotfix file names use the xxx.bin format.

**Note:**

Hotfixes are not publicly available because these not have been fully tested. Apply **ONLY** those provided by TXOne and only to the devices specified.

1. Copy the SupportTool folder from the USB device into your local drive.
2. Open the Portable Inspector Diagnostic Toolkit console.
3. Go to the **More Tools** tab.
4. Click **Use for Updates**. The **Updates** window will open.
5. Select **Apply Hot Fix**, and click **Next**. The **Apply New Components** window will open.
6. Select the hotfix file provided by TXOne.
7. Click **Apply**. A confirmation window will open.
8. To finish the update, select **No** and reinsert the device for the update to take effect.

**Note:**

To update another Scanning Tool, click **Yes**.

Rescue Disk

Use the Rescue Disk to examine your endpoint without launching your operating systems. It finds and removes persistent or difficult-to-clean security threats that can lurk deep within your operating system.

Rescue Disk can scan hidden files, system drivers, and the Master Boot Record (MBR) of your endpoint's hard drive without disturbing the operating system. Rescue Disk does not load potentially infected system files into memory before trying to remove them.



Note:

- By default, Rescue Disk quarantines any detected threats to the local hard drive. If you wish to scan without writing any information to your local hard drive, change the scan action settings to **Scan only**.
- For more information, see [Scan Settings \(Rescue Disk\) \(on page 43\)](#) page.
- Rescue Disk supports the following file systems:

<https://help.txone.com/docs/portable-inspector-system-requirements>

Procedure: Rescue Disk

1. Insert the USB device into the endpoint.
2. Restart the endpoint.
3. When the endpoint powers up again, open the BIOS or UEFI Setup Utility.
4. Look for Boot, Boot Order, or Boot Options in the menu and change the First Boot Device to the USB device.
5. Exit the menu.
6. Rescue Disk will automatically open after restarting.



Note:

After you have restarted the endpoint, the Rescue Disk console will open automatically.

7. Press ENTER, or wait for a while. The **Confirm Disk Log** window will appear.
8. Select **Yes**. The **Choose Action** window will appear.
9. Select **[1] Scan for Security Threats** and then select the type of scan.
 - **[1] Quick Scan:** Scan only the folders most vulnerable to system threats (such as the Windows System folder).
 - **[2] Full Scan:** Scan all folders.
10. The Rescue Disk will automatically start scanning. Wait for the scan to finish.
11. If any threats are detected, the message "Are you sure you want to resolve these objects?" appears. Select **Yes** to remove threats.

**Note:**

The confirmation message only appears if you have configured the Rescue Disk to:

- Scan and quarantine objects
- Inform users before the quarantine starts

12. After scan logs are saved to the Scanning Tool, confirm the removal of the Scanning Tool from the endpoint.

13. Press ENTER to restart the endpoint.

Scanning Tool Agent

The Scanning Tool Agent is a service by which the plugged-in Scanning Tool's actions can be initiated. This includes scanning computers, updating components, and configuring as well as synchronizing settings with the Management Program. Actions can be started when a Scanning Tool is plugged in or scheduled to start periodically from a plugged-in Scanning Tool. Scheduled actions will be conducted according to the configuration in the Scanning Tool Agent. If there is more than one Scanning Tool plugged into an endpoint with Scanning Tool Agent installed, the actions will be executed one by one. That is, there can't be more than one Scanning Tool active at the same time.

**Note:**

This function is only available on Windows endpoints.

Actions that Scanning Tool Agent initiates include:

- Automatically activating a Scanning Tool in Management Program mode
- Automatically updating components
- Auto scanning
- Automatically synchronizing logs and settings
- Periodically scanning
- Periodically updating components

The Scanning Tool Agent is recommended for environments that require minimal handling and for endpoints that do not have a screen during normal use.

With the configuration generator (STAgentConfigGen.exe), users can create a customized configuration that can be saved inside the installer before installation. When users need to auto-activate, they can use this configuration generator.

Install or Update the Scanning Tool Agent

The folder PI-Agent under PI SYS in the Scanning Tool USB is the installation package. If you want to customize the Scanning Tool Agent configuration before installation, please consult the later section "Customize the Configuration Before Installation".

Two modes of installation are available: with or without GUI.



Note:

- You must close the Scanning Tool console before continuing.
- Upgrading an existing Scanning Tool Agent won't change the existing configuration.

• Install the Scanning Tool Agent **with GUI**

1. Plug the Scanning Tool USB device into the endpoint that you want to install the Scanning Tool Agent on.
2. Open the PI-Agent folder in the PI SYS drive, and double-click the Setup.exe file.
3. The Setup program will check the system for Microsoft Visual C++ 2008 Redistributable and prompt you to install the package if necessary.
4. When the End-User License Agreement screen appears, read the agreement and click Agree and Continue.
5. When the Specify Destination screen opens, type or browse for a folder and click Install.
6. When the Installation Complete screen appears, click Exit.



Note:

By default, the Scanning Tool Agent console will open. To disable this function, clear the Open Scanning Tool Agent Console option.

• Install or update the Scanning Tool Agent **without GUI**

1. Open Windows Command Prompt.



Note:

You must have administrator privileges to do so.

2. Move the working directory to the PIAgent folder and then enter the command based on the operation you wish to perform:

- a. Fresh installation: **Setup.exe -silent -install [full-path]**



Note:

[full-path] is optional, and the default path is %ProgramFiles%\TXOne
\\Portable Inspector Scanning Tool Agent\.

- b. Upgrading the existing Scanning Tool Agent: **Setup.exe -silent -install**

Uninstall the Scanning Tool Agent



Note:

Make sure the Scanning Tool is not plugged into the endpoint before continuing.

There are also two ways to uninstall the Scanning Tool Agent:

- Uninstall the Scanning Tool Agent **with GUI**:

Uninstall the Scanning Tool Agent using your version of Windows Control Panel.


- Uninstall the Scanning Tool Agent **without GUI**:

1. Open Windows Command Prompt with using administrator privileges.
2. Go to the installation directory of the Scanning Tool Agent and enter the command:

Uninstall.exe -silent.

Scanning Tool Agent Console

The Scanning Tool Agent console allows you to perform some basic automated tasks after detecting a plugged-in Scanning Tool on the endpoint. You can also use the Scanning Tool Agent to perform diagnostic tasks.



The following table outlines the options available under the **Settings** tab.

	Options
Auto- matic Tasks	• Update security patterns and components: Select this to automatically update the Scanning Tool with the latest security patterns and components. • Start scanning the computer: Select this to automatically start scanning. To view the result of this scan immediately after it is complete, select Always keep the scanning program open after scanning. • Always keep the scanning program open after scanning: Select this to ensure that you can view scan logs immediately after a scan is completed. •  Note: This option interrupts all automatic tasks by the Scanning Tool Agent including synchronization and scheduled updates.

	Options
	• Sync logs and settings with the Management Program: Select this option to synchronize the Scanning Tool's logs and settings with the Management Program.  Note: Ensure that there is a working network connection between the Scanning Tool Agent and the Management Program.  Note: This feature is only functional for Scanning Tools operating in Management Program Control mode.
Scheduled Tasks	• Enable scheduled updates: Select to have the Scanning Tool updated at the defined frequency and start time. • Enable scheduled scans: Select to have the Scanning Tool scan the endpoint at the specified frequency and start time. After the scheduled scanning, the synchronization of the settings and logs will be executed as well.  Note: If both scheduled updates and scheduled scans are enabled, the Scanning Tool performs the update first. The Scanning Tool console automatically closes when both tasks are complete.

Customize the Configuration Before Installation

There are two executables in the Scanning Tool Agent installation package (PIAgent folder). Setup.exe is the installer, and STAgentConfigGen.exe is a wizard mode tool for customizing the configuration.

All settings are disabled by default. The following procedure helps you to get the customized configuration within your own installation package. You can then copy the whole package to endpoints where you would like to install the Scanning Tool Agent.

- Follow the steps below **if the scanning tool is not yet registered with MP/ElementOne**.
 1. Plug the Scanning Tool USB device into a Windows endpoint and copy the PIAgent folder from the USB device onto your local drive.
 2. Open the Command Prompt via the Windows menu, change the directory to your local PIAgent folder, and then execute STAgentConfigGen.exe.

```
C:\Users\tester\Desktop\1083\PrepareHA\PIAgent>STAgentConfigGen.exe
=====
Portable Inspector
(c) 2023 TXone Networks. All Rights Reserved.
=====
Welcome to the Scanning Tool Agent CLI Wizard! (v1.0.1083)
=====
1. Activating Scanning Tool by Management Program
=====
Do you want to activating Scanning Tool by Management Program? [Y/N]
```

**Note:**

The first part of the wizard is about "automatic activation" and for more information, you can please refer to the details in Section **Activate the Scanning Tool via Scanning Tool Agent**.

3. Follow the instructions given by the CLI Wizard to set your preferred configuration for the Scanning Tool Agent. The customized configuration file (pi_agent_config.xml) will be saved in your local installation package once it's complete.
 4. Now you can execute Setup.exe.
- Follow the steps below **if the scanning tool has been registered with another MP/ElementOne**.
 1. Plug the Scanning Tool USB device into a Windows endpoint and copy the PIAgent folder from the USB device onto your local drive.
 2. Open the Command Prompt via the Windows menu, change the directory to your local PIAgent folder, and then execute STAgentConfigGen.exe.
 3. Follow the instructions given by the CLI Wizard to set your preferred configuration for the Scanning Tool Agent.
 4. Enter **Y** to force register to another MP/ElementOne.

```

Do you want to force the activation of the Scanning Tool even though it has already been activated by
another Manangement Program? [Y/N]
Y

```


5. Now you can execute Setup.exe.

Activate the Scanning Tool via Scanning Tool Agent

When you plug in one or more non-activated Scanning Tools into the Windows endpoint with Scanning Tool Agent installed, Scanning Tool Agent can automatically trigger the Management Program's activation process according to the configuration of the Scanning Tool Agent.

The feature is disabled in the default configuration and cannot be changed after installation. For users that need this feature, they must customize the configuration.

Using the Scanning Tool Agent to activate the Scanning Tool with Management Program requires the IP/hostname, the listening port, and the password of your Management Program.



```

C:\Users\tester\Desktop\1083\PrepareHA\PIAgent>STAgentConfigGen.exe
=====
Portable Inspector
(c) 2023 TXone Networks. All Rights Reserved.
=====
Welcome to the Scanning Tool Agent CLI Wizard! (v1.0.1083)

=====
1. Activating Scanning Tool by Management Program
=====
Do you want to activating Scanning Tool by Management Program? [Y/N]
y
Enter IP address or hostname of your Management Program:
192.168.16.129
Enter the listening port [10240] of your Management Program:
10240
Enter the password of your Management Program:
*****
Re-enter your password:
*****
Activation Settings:
IP or Hostname = 192.168.16.129
Listening Port = 10240
Password = 1****6
Confirm? [Y/N]


```


**Note:**


- If you enable any of the Automatic Task Settings, these tasks will be started **immediately after the activation**.
- **During the activation, you will see the LED** of the Scanning Tool blinking in blue for a few seconds, though time may vary from one Windows endpoint to another. Please do not unplug the Scanning Tool while the activation process is running.

To check that the activation has been completed, you can use the Scanning Tool by opening its Launcher.exe under the PI SYS folder. Please make sure you close all consoles properly after this verification.

- An activated Scanning Tool will show a window like the one shown here.



- A non-activated Scanning Tool will show a window like the one shown here. Please make sure you have the correct configuration and an available network for the Management Program to use.



Note:

If the Scanning Tool Agent is still performing the operation when Launcher.exe is run, you will see a warning message.

Diagnostic Tool Tab

Use the Diagnostic Tool to help TXOne Technical Support collect useful troubleshooting information. Only use the tool when instructed to do so by TXOne Technical Support.

1. From the Scanning Tool Agent console, click the Diagnostic Tool tab.
2. Click Start Diagnostic Tool.
3. Click Start Diagnostic Logging to start collecting information.
4. Reproduce the issue you are investigating from the endpoint.
5. Click Stop Diagnostic Logging to stop recording system information. The Diagnostic Tool performs final system checks and saves the collected log data to a ZIP package.
6. Click Open Folder to open the folder containing the ZIP package.
7. Send the collected information to TXOne Technical Support for further analysis.

Chapter 9. Contact Us

TXOne Networks Contact Information

In the United States, TXOne Networks representatives are available by phone or email:

Address	TXOne Networks, Incorporated 225 E. John Carpenter Freeway, Suite 450, Irving, TX 75062, U.S.A.
Phone	+1 (214) 225-0198
Website	https://www.txone.com
Email address	Americas@txone.com

For further information, you can visit the following sites:

- Worldwide support offices: <https://www.txone.com/contact/>
- TXOne Networks product documentation: <https://help.txone.com/docs>
- MyTXOne: <https://my.txone.com>