

Fab Tool Scan Portable Inspector PRO

User Guide

Table of Contents


1. Deliverable.....	3
2. Terminology and Network Topology	3
3. Prerequisites	4
4. Working Flow of Remote Scan	5
5. Known Issues.....	8
6. Limitations.....	10
7. Collecting Debug Logs.....	13

1. Deliverable

- Builds later than 1062
 - Scanning Tool
 - Management Program(CMS)

2. Terminology and Network Topology

Term	Description
Local machine	A machine with a Portable Inspector (PI) device plugged in, also known as a Fab Tool Scan Server. The Fab Tool Scan Server program acts as a PI scanning tool, and is capable of scanning the local machine and collecting scanning status and results from the FTS Agent
Remote machine	Machines that connected to a local machine





Default port: 8081


3. Prerequisites

- Remote machines are able to be connected via RDP
- Use the same credentials(administrator/password) for Local/Remote machines
- IP addresses can be discovered by ARP
- For auto-discovery of IP addresses (via the "Discover Client" button):
Local and Remote machines are under the same Class C
- For manual input of IP addresses (via the 'Edit Client List' button): Local and Remote machines can belong to Class A, B, or C. IP addresses from all three classes (A, B, and C) can be input simultaneously
- Port 8081 needs to be allowed in the local machine

4. Working Flow of Remote Scan


Section	Steps
Steps for enabling Remote Scan   	1. Plugged-in Portable Security device and open folder PI SYS 2. Click Launcher.exe by Administrator 3. Click "Edit" 4. Go to Tab "Basic", make sure to select "Fab Tool Scan" for "Default Scan Mode" 5. Go to Tab "Advanced" and check "Scan as Administrator" 6. Under Tab "Advanced", type the account and password of the local & remote machines 7. Click "Save", and close the console

Steps for local/remote scan via “Discover Client”



1. Plugged-in Portable Inspector device and open folder **PI SYS**
2. Click **Launcher.exe** by Administrator
3. (Optional) Check “Scan Local Machine” if needed
4. Click “Scan Now”
5. Click “Discover Client”, select a network interface, and then click “Confirm”
6. Click “Copy FTSAgent folder”
7. Use the IP hyperlink to log in to the remote machine via RDP
8. Paste “FTSAgent” on the remote machine and then run **FTSLauncher.exe** in the folder
9. (Optional) Close the RDP console
10. Repeat steps 7~8 until all of the remote machines have been scanned
11. Wait until the local machine scan finishes
12. Click “Finish”


Section	Steps
Steps for local/remote scan via “Edit client List” 	1. Plugged-in Portable Inspector device and open folder PI SYS 2. Click Launcher.exe by Administrator 3. (Optional) Check “Scan Local Machine” if needed 4. Click “Scan Now” 5. Click “Edit Client List” to input IP addresses, and then click “Confirm” 6. Click “Copy FTSAgent folder” 7. Use the IP hyperlink to log in to the remote machine via RDP



8. Paste "FTSAgent" on the remote machine and then run **FTSLauncher.exe** in the folder
9. (Optional) Close the RDP console
10. Repeat steps 7~8 until all the remote machines have been scanned
11. Wait until the local machine scan finishes
12. Click "Finish"


5. Known Issues

1. On Windows 2000, Fab Tool Scan is not available. The system will automatically run an OS Scan instead.



2. Using our RDP flow, users cannot copy the FTSAgent and paste to Windows XP. However, users can use steps below to manually deploy


the FTSAgent or another method to Windows XP.




3. The Fab Tool Scan mode doesn't work with Management Program/Scanning Tool Agent.

6. Limitations

1. **Remote Desktop:** If the OS version of the **local machine** is below Windows Vista (eg. Windows XP, Windows Server 2003), users need to disable the network level authentication (NLA) on the **remote machines** if the OS version is higher than Windows Vista.




2. The firewall notifications should be allowed in the local machine:




3. **Maximum Limit and Format Requirements for IP Addresses:**

- a. A maximum of 50 IP addresses is allowed, whether using "Discover Clients" or "Edit Client List"



- b. When inputting IP addresses via "Edit Client List," they should follow the IPv4 format



7. Collecting Debug Logs

1. Select the RDP console of the remote machine.
2. Run “FTSDebugLancher.exe” to start scanning and reproduce issue.
3. Collect “FTS_LOG” folder.

