Dockerfile reference

Docker can build images automatically by reading the instructions from a <code>Dockerfile</code> . A <code>Dockerfile</code> is a text document that contains all the commands a user could call on the command line to assemble an image. Using <code>docker build</code> users can create an automated build that executes several command-line instructions in succession.

This page describes the commands you can use in a <code>Dockerfile</code> . When you are done reading this page, refer to the <code>Dockerfile</code> Best Practices (https://docs.docker.com/engine/userguide/eng-image/dockerfile_best-practices/) for a tip-oriented guide.

Usage

The docker build

(https://docs.docker.com/engine/reference/commandline/build/) command builds an image from a <code>Dockerfile</code> and a <code>context</code>. The build's context is the set of files at a specified location <code>PATH</code> or <code>URL</code>. The <code>PATH</code> is a directory on your local filesystem. The <code>URL</code> is a Git repository location.

A context is processed recursively. So, a PATH includes any subdirectories and the URL includes the repository and its submodules. This example shows a build command that uses the current directory as context:

```
$ docker build .
Sending build context to Docker daemon 6.51 MB
...
```

The build is run by the Docker daemon, not by the CLI. The first thing a build process does is send the entire context (recursively) to the daemon. In most cases, it's best to start with an empty directory as context and keep your Dockerfile in that directory. Add only the files needed for building the Dockerfile.

Warning: Do not use your root directory, /, as the PATH as it causes the build to transfer the entire contents of your hard drive to the Docker daemon.

To use a file in the build context, the <code>Dockerfile</code> refers to the file specified in an instruction, for example, a <code>COPY</code> instruction. To increase the build's performance, exclude files and directories by adding a <code>.dockerignore</code> file to the context directory. For information about how to create a <code>.dockerignore</code> file (/engine/reference/builder/#dockerignore-file) see the documentation on this page.

Traditionally, the <code>Dockerfile</code> is called <code>Dockerfile</code> and located in the root of the context. You use the <code>-f</code> flag with <code>docker build</code> to point to a Dockerfile anywhere in your file system.

```
$ docker build -f /path/to/a/Dockerfile .
```

You can specify a repository and tag at which to save the new image if the build succeeds:

```
$ docker build -t shykes/myapp .
```

To tag the image into multiple repositories after the build, add multiple -t parameters when you run the build command:

```
$ docker build -t shykes/myapp:1.0.2 -t shykes/myapp:latest .
```

Before the Docker daemon runs the instructions in the <code>Dockerfile</code> , it performs a preliminary validation of the <code>Dockerfile</code> and returns an error if the syntax is incorrect:

```
$ docker build -t test/myapp .
Sending build context to Docker daemon 2.048 kB
Error response from daemon: Unknown instruction: RUNCMD
```

The Docker daemon runs the instructions in the <code>Dockerfile</code> one-by-one, committing the result of each instruction to a new image if necessary, before finally outputting the ID of your new image. The Docker daemon will automatically clean up the context you sent.

Note that each instruction is run independently, and causes a new image to be created - so RUN cd /tmp will not have any effect on the next instructions.

Whenever possible, Docker will re-use the intermediate images (cache), to accelerate the docker build process significantly. This is indicated by the Using cache message in the console output. (For more information, see the Build cache section (https://docs.docker.com/engine/userguide/engimage/dockerfile_best-practices/#build-cache) in the Dockerfile best practices guide):

```
$ docker build -t svendowideit/ambassador .
Sending build context to Docker daemon 15.36 kB
Step 1/4 : FROM alpine:3.2
 ---> 31f630c65071
Step 2/4 : MAINTAINER SvenDowideit@home.org.au
 ---> Using cache
 ---> 2a1c91448f5f
Step 3/4 : RUN apk update && apk add socat && rm -r /var/
cache/
 ---> Using cache
 ---> 21ed6e7fbb73
Step 4/4 : CMD env | grep _TCP= | (sed 's/.*_PORT_\([0-9]*\)_TCP=tcp:
\/\\(.*\):\(.*\)/socat -t 100000000 TCP4-LISTEN:\1,fork,reuseaddr TC
P4:\2:\3 \&/' && echo wait) | sh
 ---> Using cache
 ---> 7ea8aef582cc
Successfully built 7ea8aef582cc
```

Build cache is only used from images that have a local parent chain. This means that these images were created by previous builds or the whole chain of images was loaded with <code>docker load</code> . If you wish to use build cache of a specific image you can specify it with <code>--cache-from</code> option. Images specified with <code>--cache-from</code> do not need to have a parent chain and may be pulled from other registries.

When you're done with your build, you're ready to look into *Pushing a repository* to its registry

(https://docs.docker.com/engine/tutorials/dockerrepos/#/contributing-to-docker-hub).

BuildKit

Starting with version 18.09, Docker supports a new backend for executing your builds that is provided by the moby/buildkit (https://github.com/moby/buildkit) project. The BuildKit backend provides many benefits compared to the old implementation. For example, BuildKit can:

- Detect and skip executing unused build stages
- Parallelize building independent build stages

- Incrementally transfer only the changed files in your build context between builds
- Detect and skip transferring unused files in your build context
- Use external Dockerfile implementations with many new features
- Avoid side-effects with rest of the API (intermediate images and containers)
- Prioritize your build cache for automatic pruning

To use the BuildKit backend, you need to set an environment variable DOCKER_BUILDKIT=1 on the CLI before invoking docker build .

To learn about the experimental Dockerfile syntax available to BuildKit-based builds refer to the documentation in the BuildKit repository (https://github.com/moby/buildkit/blob/master/frontend/dockerfile/docs/experimental.md).

Format

Here is the format of the <code>Dockerfile</code>:

```
# Comment
INSTRUCTION arguments
```

The instruction is not case-sensitive. However, convention is for them to be UPPERCASE to distinguish them from arguments more easily.

Docker runs instructions in a <code>Dockerfile</code> in order. A <code>Dockerfile</code> must start with a `FROM` instruction. The <code>FROM</code> instruction specifies the <code>Base Image</code> (https://docs.docker.com/engine/reference/glossary/#base-image) from which you are building. <code>FROM</code> may only be preceded by one or more <code>ARG</code> instructions, which declare arguments that are used in <code>FROM</code> lines in the <code>Dockerfile</code>.

Docker treats lines that *begin* with # as a comment, unless the line is a valid parser directive (/engine/reference/builder/#parser-directives). A # marker anywhere else in a line is treated as an argument. This allows statements like:

```
# Comment
RUN echo 'we are running some # of cool things'
```

Line continuation characters are not supported in comments.

Parser directives

Parser directives are optional, and affect the way in which subsequent lines in a <code>Dockerfile</code> are handled. Parser directives do not add layers to the build, and will not be shown as a build step. Parser directives are written as a special type of comment in the form <code># directive=value</code> . A single directive may only be used once.

Once a comment, empty line or builder instruction has been processed, Docker no longer looks for parser directives. Instead it treats anything formatted as a parser directive as a comment and does not attempt to validate if it might be a parser directive. Therefore, all parser directives must be at the very top of a Dockerfile.

Parser directives are not case-sensitive. However, convention is for them to be lowercase. Convention is also to include a blank line following any parser directives. Line continuation characters are not supported in parser directives.

Due to these rules, the following examples are all invalid:

Invalid due to line continuation:

```
# direc \
tive=value
```

Invalid due to appearing twice:

```
# directive=value1
# directive=value2
FROM ImageName
```

Treated as a comment due to appearing after a builder instruction:

```
FROM ImageName
# directive=value
```

Treated as a comment due to appearing after a comment which is not a parser directive:

```
# About my dockerfile
# directive=value
FROM ImageName
```

The unknown directive is treated as a comment due to not being recognized. In addition, the known directive is treated as a comment due to appearing after a comment which is not a parser directive.

```
# unknowndirective=value
# knowndirective=value
```

Non line-breaking whitespace is permitted in a parser directive. Hence, the following lines are all treated identically:

```
#directive=value
# directive = value
# directive = value
# directive = value
# dIrEcTiVe=value
```

The following parser directives are supported:

- syntax
- escape

syntax

```
# syntax=[remote image reference]
```

For example:

```
# syntax=docker/dockerfile
# syntax=docker/dockerfile:1.0
# syntax=docker.io/docker/dockerfile:1
# syntax=docker/dockerfile:1.0.0-experimental
# syntax=example.com/user/repo:tag@sha256:abcdef...
```

This feature is only enabled if the BuildKit (/engine/reference/builder/#buildkit) backend is used.

The syntax directive defines the location of the Dockerfile builder that is used for building the current Dockerfile. The BuildKit backend allows to seamlessly use external implementations of builders that are distributed as Docker images and execute inside a container sandbox environment.

Custom Dockerfile implementation allows you to:

Automatically get bugfixes without updating the daemon

- Make sure all users are using the same implementation to build your Dockerfile
- · Use the latest features without updating the daemon
- Try out new experimental or third-party features

Official releases

Docker distributes official versions of the images that can be used for building Dockerfiles under docker/dockerfile repository on Docker Hub. There are two channels where new images are released: stable and experimental.

Stable channel follows semantic versioning. For example:

- docker/dockerfile:1.0.0 only allow immutable version 1.0.0
- docker/dockerfile:1.0 allow versions 1.0.*
- docker/dockerfile:1 allow versions 1..
- docker/dockerfile:latest latest release on stable channel

The experimental channel uses incremental versioning with the major and minor component from the stable channel on the time of the release. For example:

- docker/dockerfile:1.0.1-experimental only allow immutable version 1.0.1-experimental
- docker/dockerfile:1.0-experimental latest experimental releases after 1.0
- docker/dockerfile:experimental latest release on experimental channel

You should choose a channel that best fits your needs. If you only want bugfixes, you should use <code>docker/dockerfile:1.0</code> . If you want to benefit from experimental features, you should use the experimental channel. If you are using the experimental channel, newer releases may not be backwards compatible, so it is recommended to use an immutable full version variant.

For master builds and nightly feature releases refer to the description in the source repository (https://github.com/moby/buildkit/blob/master/README.md).

escape

```
# escape=\ (backslash)
Or
# escape=` (backtick)
```

The escape directive sets the character used to escape characters in a Dockerfile . If not specified, the default escape character is \ .

The escape character is used both to escape characters in a line, and to escape a newline. This allows a <code>Dockerfile</code> instruction to span multiple lines. Note that regardless of whether the <code>escape</code> parser directive is included in a <code>Dockerfile</code>, <code>escaping</code> is not performed in a <code>RUN</code> command, except at the end of a line.

Setting the escape character to ` is especially useful on <code>Windows</code> , where \ is the directory path separator. ` is consistent with Windows PowerShell (https://technet.microsoft.com/en-us/library/hh847755.aspx).

Consider the following example which would fail in a non-obvious way on Windows . The second \ at the end of the second line would be interpreted as an escape for the newline, instead of a target of the escape from the first \ . Similarly, the \ at the end of the third line would, assuming it was actually handled as an instruction, cause it be treated as a line continuation. The result of this dockerfile is that second and third lines are considered a single instruction:

```
FROM microsoft/nanoserver
COPY testfile.txt c:\\
RUN dir c:\
```

Results in:

```
PS C:\John> docker build -t cmd .

Sending build context to Docker daemon 3.072 kB

Step 1/2 : FROM microsoft/nanoserver
---> 22738ff49c6d

Step 2/2 : COPY testfile.txt c:\RUN dir c:

GetFileAttributesEx c:RUN: The system cannot find the file specified.

PS C:\John>
```

One solution to the above would be to use / as the target of both the COPY instruction, and dir . However, this syntax is, at best, confusing as it is not natural for paths on Windows , and at worst, error prone as not all commands on Windows support / as the path separator.

By adding the escape parser directive, the following Dockerfile succeeds as expected with the use of natural platform semantics for file paths on Windows:

```
# escape=`
FROM microsoft/nanoserver
COPY testfile.txt c:\
RUN dir c:\
```

Results in:

```
PS C:\John> docker build -t succeeds --no-cache=true .
Sending build context to Docker daemon 3.072 kB
Step 1/3 : FROM microsoft/nanoserver
 ---> 22738ff49c6d
Step 2/3 : COPY testfile.txt c:\
 ---> 96655de338de
Removing intermediate container 4db9acbb1682
Step 3/3 : RUN dir c:\
 ---> Running in a2c157f842f5
 Volume in drive C has no label.
 Volume Serial Number is 7E6D-E0F7
 Directory of c:\
                          1,894 License.txt
10/05/2016 05:04 PM
10/05/2016 02:22 PM <DIR>
10/05/2016 02:14 PM <DIR>
                                  Program Files
                                     Program Files (x86)
10/28/2016 11:18 AM
                                  62 testfile.txt
10/28/2016 11:20 AM <DIR> Users 10/28/2016 11:20 AM <DIR> Window
                                     Windows
          2 File(s) 1,956 bytes
           4 Dir(s) 21,259,096,064 bytes free
 ---> 01c7f3bef04f
Removing intermediate container a2c157f842f5
Successfully built 01c7f3bef04f
PS C:\John>
```

Environment replacement

Environment variables (declared with the ENV statement (/engine/reference/builder/#env)) can also be used in certain instructions as variables to be interpreted by the <code>Dockerfile</code> . Escapes are also handled for including variable-like syntax into a statement literally.

Environment variables are notated in the <code>Dockerfile</code> either with <code>\$variable_name</code> or <code>\${variable_name}</code> . They are treated equivalently and the brace syntax is typically used to address issues with variable names with no whitespace, like <code>\${foo}_bar</code> .

The \${variable_name} syntax also supports a few of the standard bash modifiers as specified below:

- \${variable:-word} indicates that if variable is set then the result will be that value. If variable is not set then word will be the result.
- \${variable:+word} indicates that if variable is set then word will be the result, otherwise the result is the empty string.

In all cases, word can be any string, including additional environment variables.

Escaping is possible by adding a $\$ before the variable: \$foo or \$foo , for example, will translate to \$foo and \$foo} literals respectively.

Example (parsed representation is displayed after the #):

```
FROM busybox

ENV foo /bar

WORKDIR ${foo} # WORKDIR /bar

ADD . $foo # ADD . /bar

COPY \$foo /quux # COPY $foo /quux
```

Environment variables are supported by the following list of instructions in the Dockerfile:

- ADD
- COPY
- ENV
- EXPOSE
- FROM
- LABEL
- STOPSIGNAL
- USER
- VOLUME
- WORKDIR

as well as:

• ONBUILD (when combined with one of the supported instructions above)

Note: prior to 1.4, ONBUILD instructions did **NOT** support environment variable, even when combined with any of the instructions listed above.

Environment variable substitution will use the same value for each variable throughout the entire instruction. In other words, in this example:

```
ENV abc=hello
ENV abc=bye def=$abc
ENV ghi=$abc
```

will result in def having a value of hello , not bye . However, ghi will have a value of bye because it is not part of the same instruction that set abc to bye .

.dockerignore file

Before the docker CLI sends the context to the docker daemon, it looks for a file named .dockerignore in the root directory of the context. If this file exists, the CLI modifies the context to exclude files and directories that match patterns in it. This helps to avoid unnecessarily sending large or sensitive files and directories to the daemon and potentially adding them to images using ADD or COPY.

The CLI interprets the .dockerignore file as a newline-separated list of patterns similar to the file globs of Unix shells. For the purposes of matching, the root of the context is considered to be both the working and the root directory. For example, the patterns /foo/bar and foo/bar both exclude a file or directory named bar in the foo subdirectory of PATH or in the root of the git repository located at URL . Neither excludes anything else.

If a line in .dockerignore file starts with # in column 1, then this line is considered as a comment and is ignored before interpreted by the CLI.

Here is an example .dockerignore file:

```
# comment
*/temp*
*/*/temp*
temp?
```

This file causes the following build behavior:

Rule	Behavior
# comment	Ignored.
/temp	Exclude files and directories whose names start with temp in any immediate subdirectory of the root. For example, the plain file /somedir/temporary.txt is excluded, as is the directory /somedir/temp.
//temp*	Exclude files and directories starting with temp from any subdirectory that is two levels below the root. For example, /somedir/subdir/temporary.txt is excluded.
temp?	Exclude files and directories in the root directory whose names are a one-character extension of temp . For example, /tempa and /tempb are excluded.

Matching is done using Go's filepath.Match

(http://golang.org/pkg/path/filepath#Match) rules. A preprocessing step removes leading and trailing whitespace and eliminates . and .. elements using Go's filepath.Clean (http://golang.org/pkg/path/filepath/#Clean). Lines that are blank after preprocessing are ignored.

** that matches any number of directories (including zero). For example,

**/*.go will exclude all files that end with .go that are found in all directories, including the root of the build context.

Lines starting with ! (exclamation mark) can be used to make exceptions to exclusions. The following is an example .dockerignore file that uses this mechanism:

```
*.md
!README.md
```

All markdown files except README.md are excluded from the context.

The placement of ! exception rules influences the behavior: the last line of the .dockerignore that matches a particular file determines whether it is included or excluded. Consider the following example:

```
*.md
!README*.md
README-secret.md
```

No markdown files are included in the context except README files other than README-secret.md .

Now consider this example:

```
*.md
README-secret.md
!README*.md
```

All of the README files are included. The middle line has no effect because <code>!README*.md</code> matches <code>README-secret.md</code> and comes last.

You can even use the .dockerignore file to exclude the Dockerfile and .dockerignore files. These files are still sent to the daemon because it needs them to do its job. But the ADD and COPY instructions do not copy them to the image.

Finally, you may want to specify which files to include in the context, rather than which to exclude. To achieve this, specify * as the first pattern, followed by one or more ! exception patterns.

Note: For historical reasons, the pattern . is ignored.

FROM

```
FROM <image> [AS <name>]
Or
FROM <image>[:<tag>] [AS <name>]
Or
FROM <image>[@<digest>] [AS <name>]
```

The FROM instruction initializes a new build stage and sets the *Base Image* (https://docs.docker.com/engine/reference/glossary/#base-image) for subsequent instructions. As such, a valid <code>Dockerfile</code> must start with a <code>FROM</code> instruction. The image can be any valid image – it is especially easy to start by **pulling an image** from the *Public Repositories*

(https://docs.docker.com/engine/tutorials/dockerrepos/).

- ARG is the only instruction that may precede FROM in the Dockerfile.
 See Understand how ARG and FROM interact
 (/engine/reference/builder/#understand-how-arg-and-from-interact).
- FROM can appear multiple times within a single <code>Dockerfile</code> to create multiple images or use one build stage as a dependency for another. Simply make a note of the last image ID output by the commit before each new <code>FROM</code> instruction. Each <code>FROM</code> instruction clears any state created by previous instructions.

- Optionally a name can be given to a new build stage by adding AS name to the FROM instruction. The name can be used in subsequent FROM and COPY --from=<name|index> instructions to refer to the image built in this stage.
- The tag or digest values are optional. If you omit either of them, the builder assumes a latest tag by default. The builder returns an error if it cannot find the tag value.

Understand how ARG and FROM interact

FROM instructions support variables that are declared by any ARG instructions that occur before the first FROM .

```
ARG CODE_VERSION=latest
FROM base:${CODE_VERSION}
CMD /code/run-app

FROM extras:${CODE_VERSION}
CMD /code/run-extras
```

An ARG declared before a FROM is outside of a build stage, so it can't be used in any instruction after a FROM. To use the default value of an ARG declared before the first FROM use an ARG instruction without a value inside of a build stage:

```
ARG VERSION=latest
FROM busybox:$VERSION
ARG VERSION
RUN echo $VERSION > image_version
```

RUN

RUN has 2 forms:

- RUN <command> (shell form, the command is run in a shell, which by default is /bin/sh -c on Linux or cmd /S /C on Windows)
- RUN ["executable", "param1", "param2"] (exec form)

The RUN instruction will execute any commands in a new layer on top of the current image and commit the results. The resulting committed image will be used for the next step in the <code>Dockerfile</code> .

Layering RUN instructions and generating commits conforms to the core concepts of Docker where commits are cheap and containers can be created from any point in an image's history, much like source control.

The *exec* form makes it possible to avoid shell string munging, and to RUN commands using a base image that does not contain the specified shell executable.

The default shell for the *shell* form can be changed using the SHELL command.

In the *shell* form you can use a \ (backslash) to continue a single RUN instruction onto the next line. For example, consider these two lines:

```
RUN /bin/bash -c 'source $HOME/.bashrc; \
echo $HOME'
```

Together they are equivalent to this single line:

```
RUN /bin/bash -c 'source $HOME/.bashrc; echo $HOME'
```

Note: To use a different shell, other than '/bin/sh', use the *exec* form passing in the desired shell. For example,

```
RUN ["/bin/bash", "-c", "echo hello"]
```

Note: The *exec* form is parsed as a JSON array, which means that you must use double-quotes (") around words not single-quotes (').

Note: Unlike the *shell* form, the *exec* form does not invoke a command shell. This means that normal shell processing does not happen. For example, RUN ["echo", "\$HOME"] will not do variable substitution on \$HOME . If you want shell processing then either use the *shell* form or execute a shell directly, for example:

RUN ["sh", "-c", "echo \$HOME"] . When using the exec form and executing a shell directly, as in the case for the shell form, it is the shell that is doing the environment variable expansion, not docker.

Note: In the *JSON* form, it is necessary to escape backslashes. This is particularly relevant on Windows where the backslash is the path separator. The following line would otherwise be treated as *shell* form due to not being valid JSON, and fail in an unexpected way:

```
RUN ["c:\windows\system32\tasklist.exe"] The correct syntax for this
example is: RUN ["c:\\windows\\system32\\tasklist.exe"]
```

The cache for RUN instructions isn't invalidated automatically during the next build. The cache for an instruction like RUN apt-get dist-upgrade -y will be reused during the next build. The cache for RUN instructions can be invalidated by using the --no-cache flag, for example docker build --no-cache.

See the <code>Dockerfile</code> Best Practices guide (https://docs.docker.com/engine/userguide/eng-image/dockerfile_best-practices/#/build-cache) for more information.

The cache for RUN instructions can be invalidated by ADD instructions. See below (/engine/reference/builder/#add) for details.

Known issues (RUN)

Issue 783 (https://github.com/docker/docker/issues/783) is about file
permissions problems that can occur when using the AUFS file system. You
might notice it during an attempt to rm a file, for example.

For systems that have recent aufs version (i.e., dirperm1 mount option can be set), docker will attempt to fix the issue automatically by mounting the layers with dirperm1 option. More details on dirperm1 option can be found at aufs man page (https://github.com/sfjro/aufs3-linux/tree/aufs3.18/Documentation/filesystems/aufs)

If your system doesn't have support for <code>dirperm1</code> , the issue describes a workaround.

CMD

The CMD instruction has three forms:

- CMD ["executable", "param1", "param2"] (exec form, this is the preferred form)
- CMD ["param1","param2"] (as default parameters to ENTRYPOINT)
- CMD command param1 param2 (shellform)

There can only be one CMD instruction in a Dockerfile . If you list more than one CMD then only the last CMD will take effect.

The main purpose of a CMD is to provide defaults for an executing container.

These defaults can include an executable, or they can omit the executable, in which case you must specify an ENTRYPOINT instruction as well.

Note: If CMD is used to provide default arguments for the ENTRYPOINT instruction, both the CMD and ENTRYPOINT instructions should be specified with the JSON array format.

Note: The *exec* form is parsed as a JSON array, which means that you must use double-quotes (") around words not single-quotes (').

Note: Unlike the *shell* form, the *exec* form does not invoke a command shell. This means that normal shell processing does not happen. For example, CMD ["echo", "\$HOME"] will not do variable substitution on \$HOME . If you want shell processing then either use the *shell* form or execute a shell directly, for example: CMD ["sh", "-c", "echo \$HOME"] . When using the exec form and executing a shell directly, as in the case for the shell form, it is the shell that is doing the environment variable expansion, not docker.

When used in the shell or exec formats, the CMD instruction sets the command to be executed when running the image.

```
If you use the shell form of the CMD , then the <command> will execute in
/bin/sh -c :

FROM ubuntu
CMD echo "This is a test." | wc -
```

If you want to **run your** <command> **without a shell** then you must express the command as a JSON array and give the full path to the executable. **This array form is the preferred format of CMD** . Any additional parameters must be individually expressed as strings in the array:

```
FROM ubuntu
CMD ["/usr/bin/wc","--help"]
```

If you would like your container to run the same executable every time, then you should consider using <code>ENTRYPOINT</code> in combination with <code>CMD</code> . See <code>ENTRYPOINT</code> (/engine/reference/builder/#entrypoint).

If the user specifies arguments to docker run then they will override the default specified in CMD.

Note: Don't confuse RUN with CMD . RUN actually runs a command and commits the result; CMD does not execute anything at build time, but specifies the intended command for the image.

LABEL

```
LABEL <key>=<value> <key>=<value> ...
```

The LABEL instruction adds metadata to an image. A LABEL is a key-value pair. To include spaces within a LABEL value, use quotes and backslashes as you would in command-line parsing. A few usage examples:

```
LABEL "com.example.vendor"="ACME Incorporated"
LABEL com.example.label-with-value="foo"
LABEL version="1.0"
LABEL description="This text illustrates \
that label-values can span multiple lines."
```

An image can have more than one label. You can specify multiple labels on a single line. Prior to Docker 1.10, this decreased the size of the final image, but this is no longer the case. You may still choose to specify multiple labels in a single instruction, in one of the following two ways:

```
LABEL multi.label1="value1" multi.label2="value2" other="value3"

LABEL multi.label1="value1" \
    multi.label2="value2" \
    other="value3"
```

Labels included in base or parent images (images in the FROM line) are inherited by your image. If a label already exists but with a different value, the most-recently-applied value overrides any previously-set value.

To view an image's labels, use the docker inspect command.

```
"Labels": {
    "com.example.vendor": "ACME Incorporated"
    "com.example.label-with-value": "foo",
    "version": "1.0",
    "description": "This text illustrates that label-values can span
multiple lines.",
    "multi.label1": "value1",
    "multi.label2": "value2",
    "other": "value3"
},
```

MAINTAINER (deprecated)

MAINTAINER < name>

The MAINTAINER instruction sets the *Author* field of the generated images. The LABEL instruction is a much more flexible version of this and you should use it instead, as it enables setting any metadata you require, and can be viewed easily, for example with <code>docker inspect</code>. To set a label corresponding to the MAINTAINER field you could use:

```
LABEL maintainer="SvenDowideit@home.org.au"
```

This will then be visible from docker inspect with the other labels.

EXPOSE

```
EXPOSE <port> [<port>/<protocol>...]
```

The EXPOSE instruction informs Docker that the container listens on the specified network ports at runtime. You can specify whether the port listens on TCP or UDP, and the default is TCP if the protocol is not specified.

The EXPOSE instruction does not actually publish the port. It functions as a type of documentation between the person who builds the image and the person who runs the container, about which ports are intended to be published. To actually publish the port when running the container, use the -p flag on docker run to publish and map one or more ports, or the -P flag to publish all exposed ports and map them to high-order ports.

By default, EXPOSE assumes TCP. You can also specify UDP:

```
EXPOSE 80/udp
```

To expose on both TCP and UDP, include two lines:

```
EXPOSE 80/tcp
EXPOSE 80/udp
```

In this case, if you use -P with docker run, the port will be exposed once for TCP and once for UDP. Remember that -P uses an ephemeral high-ordered host port on the host, so the port will not be the same for TCP and UDP.

Regardless of the EXPOSE settings, you can override them at runtime by using the -p flag. For example

```
docker run -p 80:80/tcp -p 80:80/udp ...
```

To set up port redirection on the host system, see using the -P flag (https://docs.docker.com/engine/reference/run/#expose-incoming-ports). The docker network command supports creating networks for communication among containers without the need to expose or publish specific ports, because the containers connected to the network can communicate with each other over any port. For detailed information, see the overview of this feature (https://docs.docker.com/engine/userguide/networking/)).

ENV

```
ENV <key> <value>
ENV <key>=<value> ...
```

The ENV instruction sets the environment variable <key> to the value <value> . This value will be in the environment for all subsequent instructions in the build stage and can be replaced inline (/engine/reference/builder/#environment-replacement) in many as well.

The ENV instruction has two forms. The first form, ENV <key> <value> , will set a single variable to a value. The entire string after the first space will be treated as the <value> - including whitespace characters. The value will be interpreted for other environment variables, so quote characters will be removed if they are not escaped.

The second form, ENV <key>=<value> ... , allows for multiple variables to be set at one time. Notice that the second form uses the equals sign (=) in the syntax, while the first form does not. Like command line parsing, quotes and backslashes can be used to include spaces within values.

For example:

```
ENV myName="John Doe" myDog=Rex\ The\ Dog \
    myCat=fluffy
```

and

```
ENV myName John Doe
ENV myDog Rex The Dog
ENV myCat fluffy
```

will yield the same net results in the final image.

The environment variables set using ENV will persist when a container is run from the resulting image. You can view the values using docker inspect, and change them using docker run --env <key>=<value> .

Note: Environment persistence can cause unexpected side effects. For example, setting ENV DEBIAN_FRONTEND noninteractive may confuse aptget users on a Debian-based image. To set a value for a single command, use RUN <key>=<value> <command> .

ADD

ADD has two forms:

- ADD [--chown=<user>:<group>] <src>... <dest>
- ADD [--chown=<user>:<group>] ["<src>",... "<dest>"] (this form is required for paths containing whitespace)

Note: The --chown feature is only supported on Dockerfiles used to build Linux containers, and will not work on Windows containers. Since user and group ownership concepts do not translate between Linux and Windows, the use of /etc/passwd and /etc/group for translating user and group names to IDs restricts this feature to only be viable for Linux OS-based containers.

The ADD instruction copies new files, directories or remote file URLs from <src> and adds them to the filesystem of the image at the path <dest> .

Multiple <src> resources may be specified but if they are files or directories, their paths are interpreted as relative to the source of the context of the build.

Each <src> may contain wildcards and matching will be done using Go's filepath.Match (http://golang.org/pkg/path/filepath#Match) rules. For example:

```
ADD hom* /mydir/  # adds all files starting with "hom"

ADD hom?.txt /mydir/  # ? is replaced with any single character, e.
g., "home.txt"
```

The <dest> is an absolute path, or a path relative to WORKDIR, into which the source will be copied inside the destination container.

```
ADD test relativeDir/  # adds "test" to `WORKDIR`/relativeDir /
ADD test /absoluteDir/  # adds "test" to /absoluteDir/
```

When adding files or directories that contain special characters (such as [and]), you need to escape those paths following the Golang rules to prevent them from being treated as a matching pattern. For example, to add a file named arr[0].txt , use the following;

```
ADD arr[[]0].txt /mydir/ # copy a file named "arr[0].txt" to /mydi r/
```

All new files and directories are created with a UID and GID of 0, unless the optional --chown flag specifies a given username, groupname, or UID/GID combination to request specific ownership of the content added. The format of the --chown flag allows for either username and groupname strings or direct integer UID and GID in any combination. Providing a username without groupname or a UID without GID will use the same numeric UID as the GID. If a username or groupname is provided, the container's root filesystem /etc/passwd and /etc/group files will be used to perform the translation from name to integer UID or GID respectively. The following examples show valid definitions for the --chown flag:

```
ADD --chown=55:mygroup files* /somedir/
ADD --chown=bin files* /somedir/
ADD --chown=1 files* /somedir/
ADD --chown=10:11 files* /somedir/
```

If the container root filesystem does not contain either /etc/passwd or /etc/group files and either user or group names are used in the --chown flag, the build will fail on the ADD operation. Using numeric IDs requires no lookup and will not depend on container root filesystem content.

In the case where <code><src></code> is a remote file URL, the destination will have permissions of 600. If the remote file being retrieved has an HTTP <code>Last-Modified</code> header, the timestamp from that header will be used to set the <code>mtime</code> on the destination file. However, like any other file processed during an <code>ADD</code>, <code>mtime</code> will not be included in the determination of whether or not the file has changed and the cache should be updated.

Note: If you build by passing a Dockerfile through STDIN

(docker build - < somefile), there is no build context, so the

Dockerfile can only contain a URL based ADD instruction. You can also

pass a compressed archive through STDIN:

(docker build - < archive.tar.gz), the Dockerfile at the root of the archive and the rest of the archive will be used as the context of the build.

Note: If your URL files are protected using authentication, you will need to use RUN wget , RUN curl or use another tool from within the container as the ADD instruction does not support authentication.

Note: The first encountered ADD instruction will invalidate the cache for all following instructions from the Dockerfile if the contents of <src> have changed. This includes invalidating the cache for RUN instructions. See the Dockerfile Best Practices guide (https://docs.docker.com/engine/userguide/eng-image/dockerfile_best-practices/#/build-cache) for more information.

ADD obeys the following rules:

- The <src> path must be inside the context of the build; you cannot
 ADD ../something /something , because the first step of a docker build is to send the context directory (and subdirectories) to the docker daemon.
- If <src> is a URL and <dest> does not end with a trailing slash, then a file is downloaded from the URL and copied to <dest> .
- If <src> is a URL and <dest> does end with a trailing slash, then the filename is inferred from the URL and the file is downloaded to <dest>/<filename> . For instance, ADD http://example.com/foobar / would create the file /foobar . The URL must have a nontrivial path so that an appropriate filename can be discovered in this case (http://example.com will not work).

 If <src> is a directory, the entire contents of the directory are copied, including filesystem metadata.

Note: The directory itself is not copied, just its contents.

- If <src> is a *local* tar archive in a recognized compression format (identity, gzip, bzip2 or xz) then it is unpacked as a directory. Resources from *remote*URLs are **not** decompressed. When a directory is copied or unpacked, it has the same behavior as tar -x , the result is the union of:
 - 1. Whatever existed at the destination path and
 - 2. The contents of the source tree, with conflicts resolved in favor of "2." on a file-by-file basis.

Note: Whether a file is identified as a recognized compression format or not is done solely based on the contents of the file, not the name of the file. For example, if an empty file happens to end with .tar.gz this will not be recognized as a compressed file and will not generate any kind of decompression error message, rather the file will simply be copied to the destination.

- If <src> is any other kind of file, it is copied individually along with its metadata. In this case, if <dest> ends with a trailing slash / , it will be considered a directory and the contents of <src> will be written at <dest>/base(<src>) .
- If multiple <src> resources are specified, either directly or due to the use
 of a wildcard, then <dest> must be a directory, and it must end with a
 slash / .
- If <dest> does not end with a trailing slash, it will be considered a regular file and the contents of <src> will be written at <dest> .
- If <dest> doesn't exist, it is created along with all missing directories in its path.

COPY

COPY has two forms:

- COPY [--chown=<user>:<group>] <src>... <dest>
- COPY [--chown=<user>:<group>] ["<src>",... "<dest>"] (this form is required for paths containing whitespace)

Note: The --chown feature is only supported on Dockerfiles used to build Linux containers, and will not work on Windows containers. Since user and group ownership concepts do not translate between Linux and Windows, the use of /etc/passwd and /etc/group for translating user and group names to IDs restricts this feature to only be viable for Linux OS-based containers.

The COPY instruction copies new files or directories from <code><src></code> and adds them to the filesystem of the container at the path <code><dest></code>.

Multiple <src> resources may be specified but the paths of files and directories will be interpreted as relative to the source of the context of the build.

Each <src> may contain wildcards and matching will be done using Go's filepath.Match (http://golang.org/pkg/path/filepath#Match) rules. For example:

```
COPY hom* /mydir/  # adds all files starting with "hom"

COPY hom?.txt /mydir/  # ? is replaced with any single character, e
.g., "home.txt"
```

The <dest> is an absolute path, or a path relative to WORKDIR, into which the source will be copied inside the destination container.

```
COPY test relativeDir/  # adds "test" to `WORKDIR`/relativeDir/
COPY test /absoluteDir/  # adds "test" to /absoluteDir/
```

When copying files or directories that contain special characters (such as [and]), you need to escape those paths following the Golang rules to prevent them from being treated as a matching pattern. For example, to copy a file named arr[0].txt , use the following;

```
COPY arr[[]0].txt /mydir/  # copy a file named "arr[0].txt" to /myd
ir/
```

All new files and directories are created with a UID and GID of 0, unless the optional --chown flag specifies a given username, groupname, or UID/GID combination to request specific ownership of the copied content. The format of the --chown flag allows for either username and groupname strings or direct integer UID and GID in any combination. Providing a username without groupname or a UID without GID will use the same numeric UID as the GID. If a

username or groupname is provided, the container's root filesystem

/etc/passwd and /etc/group files will be used to perform the translation from

name to integer UID or GID respectively. The following examples show valid

definitions for the --chown flag:

```
COPY --chown=55:mygroup files* /somedir/
COPY --chown=bin files* /somedir/
COPY --chown=1 files* /somedir/
COPY --chown=10:11 files* /somedir/
```

If the container root filesystem does not contain either /etc/passwd or /etc/group files and either user or group names are used in the --chown flag, the build will fail on the COPY operation. Using numeric IDs requires no lookup and will not depend on container root filesystem content.

Note: If you build using STDIN (docker build - < somefile), there is no build context, so COPY can't be used.

Optionally COPY accepts a flag --from=<name|index> that can be used to set the source location to a previous build stage (created with FROM .. AS <name>) that will be used instead of a build context sent by the user. The flag also accepts a numeric index assigned for all previous build stages started with FROM instruction. In case a build stage with a specified name can't be found an image with the same name is attempted to be used instead.

COPY obeys the following rules:

- The <src> path must be inside the context of the build; you cannot
 COPY ../something /something , because the first step of a docker build is to send the context directory (and subdirectories) to the docker daemon.
- If <src> is a directory, the entire contents of the directory are copied, including filesystem metadata.

Note: The directory itself is not copied, just its contents.

If <src> is any other kind of file, it is copied individually along with its
metadata. In this case, if <dest> ends with a trailing slash / , it will be
considered a directory and the contents of <src> will be written at
<dest>/base(<src>) .

- If multiple <src> resources are specified, either directly or due to the use
 of a wildcard, then <dest> must be a directory, and it must end with a
 slash / .
- If <dest> does not end with a trailing slash, it will be considered a regular file and the contents of <src> will be written at <dest> .
- If <dest> doesn't exist, it is created along with all missing directories in its path.

ENTRYPOINT

ENTRYPOINT has two forms:

- ENTRYPOINT ["executable", "param1", "param2"] (exec form, preferred)
- ENTRYPOINT command param1 param2 (*shell* form)

An ENTRYPOINT allows you to configure a container that will run as an executable.

For example, the following will start nginx with its default content, listening on port 80:

```
docker run -i -t --rm -p 80:80 nginx
```

Command line arguments to docker run <image> will be appended after all elements in an exec form ENTRYPOINT, and will override all elements specified using CMD. This allows arguments to be passed to the entry point, i.e., docker run <image> -d will pass the -d argument to the entry point. You can override the ENTRYPOINT instruction using the docker run --entrypoint flag.

The *shell* form prevents any CMD or run command line arguments from being used, but has the disadvantage that your ENTRYPOINT will be started as a subcommand of <code>/bin/sh -c</code>, which does not pass signals. This means that the executable will not be the container's PID 1 - and will *not* receive Unix signals - so your executable will not receive a SIGTERM from docker stop <code><container></code>.

Only the last ENTRYPOINT instruction in the Dockerfile will have an effect.

Exec form ENTRYPOINT example

You can use the *exec* form of ENTRYPOINT to set fairly stable default commands and arguments and then use either form of CMD to set additional defaults that are more likely to be changed.

```
FROM ubuntu
ENTRYPOINT ["top", "-b"]
CMD ["-c"]
```

When you run the container, you can see that top is the only process:

```
$ docker run -it --rm --name test top -H
top - 08:25:00 up 7:27, 0 users, load average: 0.00, 0.01, 0.05
Threads: 1 total, 1 running, 0 sleeping, 0 stopped, 0 zombi
e
%Cpu(s): 0.1 us, 0.1 sy, 0.0 ni, 99.7 id, 0.0 wa, 0.0 hi, 0.0 s
i, 0.0 st
KiB Mem: 2056668 total, 1616832 used, 439836 free, 99352 buff
ers
KiB Swap: 1441840 total, 0 used, 1441840 free. 1324440 cach
ed Mem

PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ CO
MMAND
1 root 20 0 19744 2336 2080 R 0.0 0.1 0:00.04 to
p
```

To examine the result further, you can use docker exec:

And you can gracefully request top to shut down using docker stop test.

The following Dockerfile shows using the ENTRYPOINT to run Apache in the foreground (i.e., as PID 1):

```
FROM debian:stable
RUN apt-get update && apt-get install -y --force-yes apache2
EXPOSE 80 443

VOLUME ["/var/www", "/var/log/apache2", "/etc/apache2"]
ENTRYPOINT ["/usr/sbin/apache2ctl", "-D", "FOREGROUND"]
```

If you need to write a starter script for a single executable, you can ensure that the final executable receives the Unix signals by using exec and gosu commands:

Lastly, if you need to do some extra cleanup (or communicate with other containers) on shutdown, or are co-ordinating more than one executable, you may need to ensure that the ENTRYPOINT script receives the Unix signals, passes them on, and then does some more work:

```
#!/bin/sh
# Note: I've written this using sh so it works in the busybox contain
er too

# USE the trap if you need to also do manual cleanup after the servic
e is stopped,
# or need to start multiple services in the one container
trap "echo TRAPed signal" HUP INT QUIT TERM

# start service in background here
/usr/sbin/apachectl start

echo "[hit enter key to exit] or run 'docker stop <container>'"
read

# stop service and clean up here
echo "stopping apache"
/usr/sbin/apachectl stop
echo "exited $0"
```

If you run this image with docker run -it --rm -p 80:80 --name test apache , you can then examine the container's processes with docker exec , or docker top , and then ask the script to stop Apache:

```
$ docker exec -it test ps aux
USER PID %CPU %MEM VSZ RSS TTY START TIME COMM
AND
         1 0.1 0.0 4448 692 ? Ss+ 00:42 0:00 /bin
root
/sh /run.sh 123 cmd cmd2
root 19 0.0 0.2 71304 4440 ? Ss 00:42
                                                 0:00 /usr
/sbin/apache2 -k start
www-data 20 0.2 0.2 360468 6004 ? S1 00:42 0:00 /usr
/sbin/apache2 -k start
www-data 21 0.2 0.2 360468 6000 ? S1 00:42 0:00 /usr
/sbin/apache2 -k start
root 81 0.0 0.1 15572 2140 ? R+ 00:44 0:00 ps a
ПX
$ docker top test
PID
               USER
                                COMMAND
10035
                                {run.sh} /bin/sh /run.sh 123
                root
cmd cmd2
10054
               root
                                /usr/sbin/apache2 -k start
10055
                33
                                /usr/sbin/apache2 -k start
10056
                33
                                /usr/sbin/apache2 -k start
$ /usr/bin/time docker stop test
test
      0m 0.27s
real
user 0m 0.03s
sys 0m 0.03s
```

Note: you can override the ENTRYPOINT setting using --entrypoint , but this can only set the binary to *exec* (no sh -c will be used).

Note: The *exec* form is parsed as a JSON array, which means that you must use double-quotes (") around words not single-quotes (').

Note: Unlike the *shell* form, the *exec* form does not invoke a command shell. This means that normal shell processing does not happen. For example, <code>ENTRYPOINT</code> ["echo", "\$HOME"] will not do variable substitution on \$HOME . If you want shell processing then either use the *shell* form or execute a shell directly, for example:

ENTRYPOINT ["sh", "-c", "echo \$HOME"] . When using the exec form and executing a shell directly, as in the case for the shell form, it is the shell that is doing the environment variable expansion, not docker.

Shell form ENTRYPOINT example

You can specify a plain string for the ENTRYPOINT and it will execute in /bin/sh -c . This form will use shell processing to substitute shell environment variables, and will ignore any CMD or docker run command line arguments. To ensure that docker stop will signal any long running ENTRYPOINT executable correctly, you need to remember to start it with exec:

```
FROM ubuntu
ENTRYPOINT exec top -b
```

When you run this image, you'll see the single PID 1 process:

Which will exit cleanly on docker stop:

```
$ /usr/bin/time docker stop test
test
real     0m 0.20s
user     0m 0.02s
sys     0m 0.04s
```

If you forget to add exec to the beginning of your ENTRYPOINT:

```
FROM ubuntu
ENTRYPOINT top -b
CMD --ignored-param1
```

You can then run it (giving it a name for the next step):

You can see from the output of top that the specified ENTRYPOINT is not PID 1.

If you then run docker stop test, the container will not exit cleanly - the stop command will be forced to send a SIGKILL after the timeout:

Understand how CMD and ENTRYPOINT interact

Both CMD and ENTRYPOINT instructions define what command gets executed when running a container. There are few rules that describe their co-operation.

- 1. Dockerfile should specify at least one of CMD or ENTRYPOINT commands.
- 2. ENTRYPOINT should be defined when using the container as an executable.
- 3. CMD should be used as a way of defining default arguments for an ENTRYPOINT command or for executing an ad-hoc command in a container.
- 4. CMD will be overridden when running the container with alternative arguments.

The table below shows what command is executed for different ENTRYPOINT / CMD combinations:

No ENTRYPOINT	ENTRYPOINT exec_entry p1_entry	ENTRYPOINT ["exec_entry", "p1_entry"]
------------------	--------------------------------	---------------------------------------

	No ENTRYPOINT	ENTRYPOINT exec_entry p1_entry	ENTRYPOINT ["exec_entry", "p1_entry"]
No CMD	error, not allowed	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry
CMD ["exec_cmd", "p1_cmd"]	exec_cmd p1_cmd	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry exec_cmd p1_cmd
CMD ["p1_cmd", "p2_cmd"]	p1_cmd p2_cmd	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry p1_cmd p2_cmd
CMD exec_cmd p1_cmd	/bin/sh -c exec_cmd p1_cmd	/bin/sh -c exec_entry p1_entry	exec_entry p1_entry /bin/sh -c exec_cmd p1_cmd

Note: If CMD is defined from the base image, setting ENTRYPOINT will reset CMD to an empty value. In this scenario, CMD must be defined in the current image to have a value.

VOLUME

VOLUME ["/data"]

The VOLUME instruction creates a mount point with the specified name and marks it as holding externally mounted volumes from native host or other containers. The value can be a JSON array, VOLUME ["/var/log/"], or a plain string with multiple arguments, such as VOLUME /var/log or

VOLUME /var/log /var/db . For more information/examples and mounting instructions via the Docker client, refer to *Share Directories via Volumes* (https://docs.docker.com/engine/tutorials/dockervolumes/#/mount-a-host-directory-as-a-data-volume) documentation.

The docker run command initializes the newly created volume with any data that exists at the specified location within the base image. For example, consider the following Dockerfile snippet:

```
FROM ubuntu
RUN mkdir /myvol
RUN echo "hello world" > /myvol/greeting
VOLUME /myvol
```

This Dockerfile results in an image that causes docker run to create a new mount point at /myvol and copy the greeting file into the newly created volume.

Notes about specifying volumes

Keep the following things in mind about volumes in the <code>Dockerfile</code> .

- Volumes on Windows-based containers: When using Windows-based containers, the destination of a volume inside the container must be one of:
 - a non-existing or empty directory
 - a drive other than c:
- Changing the volume from within the Dockerfile: If any build steps change the data within the volume after it has been declared, those changes will be discarded.
- JSON formatting: The list is parsed as a JSON array. You must enclose words with double quotes (") rather than single quotes (').
- The host directory is declared at container run-time: The host directory (the mountpoint) is, by its nature, host-dependent. This is to preserve image portability, since a given host directory can't be guaranteed to be available on all hosts. For this reason, you can't mount a host directory from within the Dockerfile. The VOLUME instruction does not support specifying a host-dir parameter. You must specify the mountpoint when you create or run the container.

USER

```
USER <user>[:<group>] or
USER <UID>[:<GID>]
```

The USER instruction sets the user name (or UID) and optionally the user group (or GID) to use when running the image and for any RUN, CMD and ENTRYPOINT instructions that follow it in the Dockerfile.

Warning: When the user doesn't have a primary group then the image (or the next instructions) will be run with the root group.

On Windows, the user must be created first if it's not a built-in account. This can be done with the net user command called as part of a Dockerfile.

```
FROM microsoft/windowsservercore
# Create Windows user in the container
RUN net user /add patrick
# Set it for subsequent commands
USER patrick
```

WORKDIR

```
WORKDIR /path/to/workdir
```

The WORKDIR instruction sets the working directory for any RUN , CMD , ENTRYPOINT , COPY and ADD instructions that follow it in the Dockerfile . If the WORKDIR doesn't exist, it will be created even if it's not used in any subsequent Dockerfile instruction.

The WORKDIR instruction can be used multiple times in a Dockerfile . If a relative path is provided, it will be relative to the path of the previous WORKDIR instruction. For example:

```
WORKDIR /a
WORKDIR b
WORKDIR c
RUN pwd
```

The output of the final $\ pwd$ command in this $\ Dockerfile$ would be $\ /a/b/c$.

The WORKDIR instruction can resolve environment variables previously set using ENV . You can only use environment variables explicitly set in the <code>Dockerfile</code> . For example:

```
ENV DIRPATH /path
WORKDIR $DIRPATH/$DIRNAME
RUN pwd
```

The output of the final pwd command in this Dockerfile would be /path/\$DIRNAME

ARG

```
ARG <name>[=<default value>]
```

The ARG instruction defines a variable that users can pass at build-time to the builder with the docker build command using the

--build-arg <varname>=<value> flag. If a user specifies a build argument that was not defined in the Dockerfile, the build outputs a warning.

```
[Warning] One or more build-args [foo] were not consumed.
```

A Dockerfile may include one or more ARG instructions. For example, the following is a valid Dockerfile:

```
FROM busybox
ARG user1
ARG buildno
```

Warning: It is not recommended to use build-time variables for passing secrets like github keys, user credentials etc. Build-time variable values are visible to any user of the image with the docker history command.

Default values

An ARG instruction can optionally include a default value:

```
FROM busybox
ARG user1=someuser
ARG buildno=1
...
```

If an ARG instruction has a default value and if there is no value passed at buildtime, the builder uses the default.

Scope

An ARG variable definition comes into effect from the line on which it is defined in the <code>Dockerfile</code> not from the argument's use on the command-line or elsewhere. For example, consider this Dockerfile:

```
1 FROM busybox
2 USER ${user:-some_user}
3 ARG user
4 USER $user
...
```

A user builds this file by calling:

```
$ docker build --build-arg user=what_user .
```

The USER at line 2 evaluates to some_user as the user variable is defined on the subsequent line 3. The USER at line 4 evaluates to what_user as user is defined and the what_user value was passed on the command line. Prior to its definition by an ARG instruction, any use of a variable results in an empty string.

An ARG instruction goes out of scope at the end of the build stage where it was defined. To use an arg in multiple stages, each stage must include the ARG instruction.

```
FROM busybox
ARG SETTINGS
RUN ./run/setup $SETTINGS
FROM busybox
ARG SETTINGS
RUN ./run/other $SETTINGS
```

Using ARG variables

You can use an ARG or an ENV instruction to specify variables that are available to the RUN instruction. Environment variables defined using the ENV instruction always override an ARG instruction of the same name. Consider this Dockerfile with an ENV and ARG instruction.

```
1 FROM ubuntu
2 ARG CONT_IMG_VER
3 ENV CONT_IMG_VER v1.0.0
4 RUN echo $CONT_IMG_VER
```

Then, assume this image is built with this command:

```
$ docker build --build-arg CONT_IMG_VER=v2.0.1 .
```

In this case, the RUN instruction uses v1.0.0 instead of the ARG setting passed by the user: v2.0.1 This behavior is similar to a shell script where a locally scoped variable overrides the variables passed as arguments or inherited from environment, from its point of definition.

Using the example above but a different ENV specification you can create more useful interactions between ARG and ENV instructions:

```
1 FROM ubuntu
2 ARG CONT_IMG_VER
3 ENV CONT_IMG_VER ${CONT_IMG_VER:-v1.0.0}
4 RUN echo $CONT_IMG_VER
```

Unlike an ARG instruction, ENV values are always persisted in the built image. Consider a docker build without the --build-arg flag:

```
$ docker build .
```

Using this Dockerfile example, $CONT_IMG_VER$ is still persisted in the image but its value would be v1.0.0 as it is the default set in line 3 by the ENV instruction.

The variable expansion technique in this example allows you to pass arguments from the command line and persist them in the final image by leveraging the ENV instruction. Variable expansion is only supported for a limited set of Dockerfile instructions. (/engine/reference/builder/#environment-replacement)

Predefined ARGs

Docker has a set of predefined ARG variables that you can use without a corresponding ARG instruction in the Dockerfile.

- HTTP PROXY
- http_proxy

- HTTPS PROXY
- https_proxy
- FTP_PROXY
- ftp_proxy
- NO_PROXY
- no_proxy

To use these, simply pass them on the command line using the flag:

```
--build-arg <varname>=<value>
```

By default, these pre-defined variables are excluded from the output of docker history. Excluding them reduces the risk of accidentally leaking sensitive authentication information in an http_proxy variable.

For example, consider building the following Dockerfile using

```
--build-arg HTTP_PROXY=http://user:pass@proxy.lon.example.com

FROM ubuntu
RUN echo "Hello World"
```

In this case, the value of the <code>HTTP_PROXY</code> variable is not available in the docker history and is not cached. If you were to change location, and your proxy server changed to <code>http://user:pass@proxy.sfo.example.com</code>, a subsequent build does not result in a cache miss.

If you need to override this behaviour then you may do so by adding an ARG statement in the Dockerfile as follows:

```
FROM ubuntu

ARG HTTP_PROXY

RUN echo "Hello World"
```

When building this Dockerfile, the HTTP_PROXY is preserved in the docker history, and changing its value invalidates the build cache.

Automatic platform ARGs in the global scope

This feature is only available when using the BuildKit (/engine/reference/builder/#buildkit) backend.

Docker predefines a set of ARG variables with information on the platform of the node performing the build (build platform) and on the platform of the resulting image (target platform). The target platform can be specified with the

```
--platform flag on docker build .
```

The following ARG variables are set automatically:

- TARGETPLATFORM platform of the build result. Eg linux/amd64, linux/arm/v7, windows/amd64.
- TARGETOS OS component of TARGETPLATFORM
- TARGETARCH architecture component of TARGETPLATFORM
- TARGETVARIANT variant component of TARGETPLATFORM
- BUILDPLATFORM platform of the node performing the build.
- BUILDOS OS component of BUILDPLATFORM
- BUILDARCH OS component of BUILDPLATFORM
- BUILDVARIANT OS component of BUILDPLATFORM

These arguments are defined in the global scope so are not automatically available inside build stages or for your RUN commands. To expose one of these arguments inside the build stage redefine it without value.

For example:

```
FROM alpine
ARG TARGETPLATFORM
RUN echo "I'm building for $TARGETPLATFORM"
```

Impact on build caching

ARG variables are not persisted into the built image as ENV variables are. However, ARG variables do impact the build cache in similar ways. If a Dockerfile defines an ARG variable whose value is different from a previous build, then a "cache miss" occurs upon its first usage, not its definition. In particular, all RUN instructions following an ARG instruction use the ARG variable implicitly (as an environment variable), thus can cause a cache miss. All predefined ARG variables are exempt from caching unless there is a matching ARG statement in the Dockerfile.

For example, consider these two Dockerfile:

```
1 FROM ubuntu
2 ARG CONT_IMG_VER
3 RUN echo $CONT_IMG_VER

1 FROM ubuntu
2 ARG CONT_IMG_VER
3 RUN echo hello
```

If you specify --build-arg CONT_IMG_VER=<value> on the command line, in both cases, the specification on line 2 does not cause a cache miss; line 3 does cause a cache miss. ARG CONT_IMG_VER causes the RUN line to be identified as the same as running CONT_IMG_VER=<value> echo hello, so if the <value> changes, we get a cache miss.

Consider another example under the same command line:

```
1 FROM ubuntu
2 ARG CONT_IMG_VER
3 ENV CONT_IMG_VER $CONT_IMG_VER
4 RUN echo $CONT_IMG_VER
```

In this example, the cache miss occurs on line 3. The miss happens because the variable's value in the ENV references the ARG variable and that variable is changed through the command line. In this example, the ENV command causes the image to include the value.

If an ENV instruction overrides an ARG instruction of the same name, like this Dockerfile:

```
1 FROM ubuntu
2 ARG CONT_IMG_VER
3 ENV CONT_IMG_VER hello
4 RUN echo $CONT_IMG_VER
```

Line 3 does not cause a cache miss because the value of <code>CONT_IMG_VER</code> is a constant (<code>hello</code>). As a result, the environment variables and values used on the <code>RUN</code> (line 4) doesn't change between builds.

ONBUILD

```
ONBUILD [INSTRUCTION]
```

The <code>ONBUILD</code> instruction adds to the image a *trigger* instruction to be executed at a later time, when the image is used as the base for another build. The trigger will be executed in the context of the downstream build, as if it had been inserted immediately after the <code>FROM</code> instruction in the downstream <code>Dockerfile</code>.

Any build instruction can be registered as a trigger.

This is useful if you are building an image which will be used as a base to build other images, for example an application build environment or a daemon which may be customized with user-specific configuration.

For example, if your image is a reusable Python application builder, it will require application source code to be added in a particular directory, and it might require a build script to be called *after* that. You can't just call ADD and RUN now, because you don't yet have access to the application source code, and it will be different for each application build. You could simply provide application developers with a boilerplate <code>Dockerfile</code> to copy-paste into their application, but that is inefficient, error-prone and difficult to update because it mixes with application-specific code.

The solution is to use ONBUILD to register advance instructions to run later, during the next build stage.

Here's how it works:

- 1. When it encounters an <code>ONBUILD</code> instruction, the builder adds a trigger to the metadata of the image being built. The instruction does not otherwise affect the current build.
- 2. At the end of the build, a list of all triggers is stored in the image manifest, under the key <code>OnBuild</code> . They can be inspected with the <code>docker inspect command</code>.
- 3. Later the image may be used as a base for a new build, using the FROM instruction. As part of processing the FROM instruction, the downstream builder looks for ONBUILD triggers, and executes them in the same order they were registered. If any of the triggers fail, the FROM instruction is aborted which in turn causes the build to fail. If all triggers succeed, the FROM instruction completes and the build continues as usual.
- 4. Triggers are cleared from the final image after being executed. In other words they are not inherited by "grand-children" builds.

For example you might add something like this:

```
[...]
ONBUILD ADD . /app/src
ONBUILD RUN /usr/local/bin/python-build --dir /app/src
[...]
```

Warning: Chaining ONBUILD instructions using ONBUILD ONBUILD isn't allowed.

Warning: The ONBUILD instruction may not trigger FROM OR MAINTAINER instructions.

STOPSIGNAL

```
STOPSIGNAL signal
```

The STOPSIGNAL instruction sets the system call signal that will be sent to the container to exit. This signal can be a valid unsigned number that matches a position in the kernel's syscall table, for instance 9, or a signal name in the format SIGNAME, for instance SIGKILL.

HEALTHCHECK

The HEALTHCHECK instruction has two forms:

- HEALTHCHECK [OPTIONS] CMD command (check container health by running a command inside the container)
- HEALTHCHECK NONE (disable any healthcheck inherited from the base image)

The HEALTHCHECK instruction tells Docker how to test a container to check that it is still working. This can detect cases such as a web server that is stuck in an infinite loop and unable to handle new connections, even though the server process is still running.

When a container has a healthcheck specified, it has a *health status* in addition to its normal status. This status is initially starting. Whenever a health check passes, it becomes healthy (whatever state it was previously in). After a certain number of consecutive failures, it becomes unhealthy.

The options that can appear before CMD are:

```
    --interval=DURATION (default: 30s)
    --timeout=DURATION (default: 30s)
    --start-period=DURATION (default: 0s)
    --retries=N (default: 3)
```

The health check will first run **interval** seconds after the container is started, and then again **interval** seconds after each previous check completes.

If a single run of the check takes longer than **timeout** seconds then the check is considered to have failed.

It takes **retries** consecutive failures of the health check for the container to be considered unhealthy .

start period provides initialization time for containers that need time to bootstrap. Probe failure during that period will not be counted towards the maximum number of retries. However, if a health check succeeds during the start period, the container is considered started and all consecutive failures will be counted towards the maximum number of retries.

There can only be one HEALTHCHECK instruction in a Dockerfile. If you list more than one then only the last HEALTHCHECK will take effect.

The command after the CMD keyword can be either a shell command (e.g. HEALTHCHECK CMD /bin/check-running) or an *exec* array (as with other Dockerfile commands; see e.g. ENTRYPOINT for details).

The command's exit status indicates the health status of the container. The possible values are:

- 0: success the container is healthy and ready for use
- 1: unhealthy the container is not working correctly
- 2: reserved do not use this exit code

For example, to check every five minutes or so that a web-server is able to serve the site's main page within three seconds:

```
HEALTHCHECK --interval=5m --timeout=3s \
CMD curl -f http://localhost/ || exit 1
```

To help debug failing probes, any output text (UTF-8 encoded) that the command writes on stdout or stderr will be stored in the health status and can be queried with docker inspect. Such output should be kept short (only the first 4096 bytes are stored currently).

When the health status of a container changes, a health_status event is generated with the new status.

The HEALTHCHECK feature was added in Docker 1.12.

SHELL

```
SHELL ["executable", "parameters"]
```

The SHELL instruction allows the default shell used for the *shell* form of commands to be overridden. The default shell on Linux is ["/bin/sh", "-c"], and on Windows is ["cmd", "/S", "/C"]. The SHELL instruction *must* be written in JSON form in a Dockerfile.

The SHELL instruction is particularly useful on Windows where there are two commonly used and quite different native shells: cmd and powershell, as well as alternate shells available including sh.

The SHELL instruction can appear multiple times. Each SHELL instruction overrides all previous SHELL instructions, and affects all subsequent instructions. For example:

```
FROM microsoft/windowsservercore

# Executed as cmd /S /C echo default
RUN echo default

# Executed as cmd /S /C powershell -command Write-Host default
RUN powershell -command Write-Host default

# Executed as powershell -command Write-Host hello
SHELL ["powershell", "-command"]
RUN Write-Host hello

# Executed as cmd /S /C echo hello
SHELL ["cmd", "/S", "/C"]
RUN echo hello
```

The following instructions can be affected by the SHELL instruction when the *shell* form of them is used in a Dockerfile: RUN , CMD and ENTRYPOINT .

The following example is a common pattern found on Windows which can be streamlined by using the SHELL instruction:

```
RUN powershell -command Execute-MyCmdlet -param1 "c:\foo.txt"
...
```

The command invoked by docker will be:

```
cmd /S /C powershell -command Execute-MyCmdlet -param1 "c:\foo.txt"
```

This is inefficient for two reasons. First, there is an un-necessary cmd.exe command processor (aka shell) being invoked. Second, each RUN instruction in the *shell* form requires an extra powershell -command prefixing the command.

To make this more efficient, one of two mechanisms can be employed. One is to use the JSON form of the RUN command such as:

```
...
RUN ["powershell", "-command", "Execute-MyCmdlet", "-param1 \"c:\\foo
.txt\""]
...
```

While the JSON form is unambiguous and does not use the un-necessary cmd.exe, it does require more verbosity through double-quoting and escaping. The alternate mechanism is to use the SHELL instruction and the *shell* form, making a more natural syntax for Windows users, especially when combined with the escape parser directive:

```
# escape=`
FROM microsoft/nanoserver
SHELL ["powershell","-command"]
RUN New-Item -ItemType Directory C:\Example
ADD Execute-MyCmdlet.ps1 c:\example\
RUN c:\example\Execute-MyCmdlet -sample 'hello world'
```

Resulting in:

```
PS E:\docker\build\shell> docker build -t shell .
Sending build context to Docker daemon 4.096 kB
Step 1/5 : FROM microsoft/nanoserver
---> 22738ff49c6d
Step 2/5 : SHELL powershell -command
 ---> Running in 6fcdb6855ae2
 ---> 6331462d4300
Removing intermediate container 6fcdb6855ae2
Step 3/5 : RUN New-Item -ItemType Directory C:\Example
 ---> Running in d0eef8386e97
   Directory: C:\
Mode
                 LastWriteTime Length Name
----
                  -----
                                       -----
d---- 10/28/2016 11:26 AM
                                               Example
 ---> 3f2fbf1395d9
Removing intermediate container d0eef8386e97
Step 4/5 : ADD Execute-MyCmdlet.ps1 c:\example\
---> a955b2621c31
Removing intermediate container b825593d39fc
Step 5/5 : RUN c:\example\Execute-MyCmdlet 'hello world'
---> Running in be6d8e63fe75
hello world
---> 8e559e9bf424
Removing intermediate container be6d8e63fe75
Successfully built 8e559e9bf424
PS E:\docker\build\shell>
```

The SHELL instruction could also be used to modify the way in which a shell operates. For example, using SHELL cmd /S /C /V:ON|OFF on Windows, delayed environment variable expansion semantics could be modified.

The SHELL instruction can also be used on Linux should an alternate shell be required such as zsh, csh, tcsh and others.

The SHELL feature was added in Docker 1.12.

External implementation features

This feature is only available when using the BuildKit (/engine/reference/builder/#buildkit) backend.

Docker build supports experimental features like cache mounts, build secrets and ssh forwarding that are enabled by using an external implementation of the builder with a syntax directive. To learn about these features, refer to the documentation in BuildKit repository

(https://github.com/moby/buildkit/blob/master/frontend/dockerfile/docs/experimental.md).

Dockerfile examples

Below you can see some examples of Dockerfile syntax. If you're interested in something more realistic, take a look at the list of Dockerization examples (https://docs.docker.com/engine/examples/).

```
# Nginx
# VERSION
                      0.0.1
FROM
        ubuntu
LABEL Description="This image is used to start the foobar executable"
Vendor="ACME Products" Version="1.0"
RUN apt-get update && apt-get install -y inotify-tools nginx apache2
openssh-server
# Firefox over VNC
# VERSION
                      0.3
FROM ubuntu
# Install vnc, xvfb in order to create a 'fake' display and firefox
RUN apt-get update && apt-get install -y x11vnc xvfb firefox
RUN mkdir ~/.vnc
# Setup a password
RUN x11vnc -storepasswd 1234 ~/.vnc/passwd
# Autostart firefox (might not be the best way, but it does the trick
RUN bash -c 'echo "firefox" >> /.bashrc'
EXPOSE 5900
CMD ["x11vnc", "-forever", "-usepw", "-create"]
```

```
# Multiple images example
#
# VERSION      0.1

FROM ubuntu
RUN echo foo > bar
# Will output something like ===> 907ad6c2736f

FROM ubuntu
RUN echo moo > oink
# Will output something like ===> 695d7793cbe4

# You'll now have two images, 907ad6c2736f with /bar, and 695d7793cbe 4 with
# /oink.
```

builder (https://docs.docker.com/glossary/?term=builder), docker (https://docs.docker.com/glossary/?term=docker), Dockerfile (https://docs.docker.com/glossary/?term=Dockerfile), automation (https://docs.docker.com/glossary/?term=automation), image creation (https://docs.docker.com/glossary/?term=image creation)