

## **Docs**

**Getting Started** 

**Data Structure** 

**Object Mapping** 

Collections

**BsonDocument** 

Expressions

DbRef

**Connection String** 

FileStorage

Indexes

Encryption

Pragmas

Collation

## Pragmas

In LiteDB v5, pragmas are variables that can alter the behavior of a datafile. They are stored in the header of the datafile.

Name	Read- only	Data type	Description	Default value
USER_VERSION	no	int	Reserved for version control by the user. Does not affect the behavior of the datafile.	0
COLLATION	yes (can be changed with a rebuild)	string (internally stored as int)	Check <u>Collation</u> .	CurrentCulture and IgnoreCase



Name	Read- only	Data type	Description	Default value
TIMEOUT	no	int	Maximum amount of time (in seconds) that the engine waits for a shared resouce to be unlocked.	60
LIMIT_SIZE	no	long	Maximum size (in bytes) that the datafile can grow to. Cannot be smaller than the current datafile size. Cannot be smaller than 4 pages (32768 bytes).	long.MaxValue
UTC_DATE	no	bool	If false, dates are converted to local time on retrieval. Storage format is not affected (always in UTC).	false
CHECKPOINT	no	int	Maximum number of pages to be stored in the log before a soft checkpoint. If set to 0, auto-checkpoint and shutdown checkpoint are disabled.	1000

## **Examples**

- select pragmas from \$database; returns the pragmas in the current datafile
- pragma USER\_VERSION = 1; sets USER\_VERSION to 1
- pragma UTC\_DATE = true; sets UTC\_DATE to true

## Rebuild Options

Rebuild options are used to configure a rebuild.

Name	Data type	Description	Default value
collation	string	Check <u>Collation</u> .	null(will use CurrentCulture and IgnoreCase if null)
password	string	Defines the password for an encrypted datafile.	null (datafile will not be encrypted)

If the rebuild command is issued without options, both are assumed to be null.

Rebuilds are also useful to defragment a datafile, making it smaller and faster to access.

- rebuild; rebuilds the database with the default collation and no password
- rebuild {"collation": "en-GB/IgnoreCase"}; rebuilds the datafile with the en-GB culture and case-insensitive string comparison
- rebuild {"collation": "pt-BR/None", "password" : "1234"}; rebuilds the datafile with the pt-BR culture, case-sensitive string comparison and sets the password to "1234"

Made with ♥ by LiteDB team - @mbdavid - MIT License