

Red Hat Lightspeed 1-latest

Getting started with Red Hat Lightspeed with FedRAMP

How to start using Red Hat Lightspeed

Last Updated: 2026-09-02

Red Hat Lightspeed 1-latest Getting started with Red Hat Lightspeed with FedRAMP

How to start using Red Hat Lightspeed

Legal Notice

Copyright © Red Hat.

Except as otherwise noted below, the text of and illustrations in this documentation are licensed by Red Hat under the Creative Commons Attribution–Share Alike 3.0 Unported license . If you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, the Red Hat logo, JBoss, Hibernate, and RHCE are trademarks or registered trademarks of Red Hat, LLC. or its subsidiaries in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

XFS is a trademark or registered trademark of Hewlett Packard Enterprise Development LP or its subsidiaries in the United States and other countries.

The OpenStack ® Word Mark and OpenStack logo are trademarks or registered trademarks of the Linux Foundation, used under license.

All other trademarks are the property of their respective owners.

Abstract

This document provides starting points and resources for registering and installing Red Hat Lightspeed on Red Hat Enterprise Linux and OpenShift Container Platform with FedRAMP®.

Table of Contents

CHAPTER 1. ABOUT RED HAT LIGHTSPEED 3

CHAPTER 2. INSTALL RED HAT LIGHTSPEED ON RHEL SYSTEMS 4
2.1. INSTALLATION METHODS FOR RED HAT LIGHTSPEED ON RHEL 4
2.2. RED HAT SATELLITE INTEGRATION RESOURCES FOR RED HAT LIGHTSPEED 4
2.3. REGISTER AND CONFIGURE SATELLITE SERVER INTEGRATION WITH FEDRAMP 4
2.4. MANAGE TRUSTED IP ADDRESSES WITH AN IP ALLOWLIST 6
2.4.1. IP allowlist configuration methods 6
2.4.2. Add trusted IP addresses to an allowlist 6
2.4.3. Remove IP addresses from the allowlist 8
2.4.4. Additional resources 9

CHAPTER 3. MANAGE USER PERMISSIONS FOR RED HAT LIGHTSPEED SERVICES 10
3.1. USER ACCESS OVERVIEW 10
3.2. PREDEFINED GROUPS IN USER ACCESS 10
3.3. PREDEFINED ROLES ASSIGNED TO GROUPS 11
3.4. CHECK YOUR PERMISSIONS 11
3.5. CONFIGURE USER PERMISSIONS 12

CHAPTER 1. ABOUT RED HAT LIGHTSPEED

Red Hat Lightspeed can discover relevant insights, recommend tailored, proactive next actions, and automate tasks. Using Red Hat Lightspeed, customers benefit from the experience and technical knowledge of Red Hat Certified Engineers, to identify, prioritize, and resolve issues for business operations.

As a SaaS offering, Red Hat Lightspeed is regularly updated. Regular updates expand the Red Hat Lightspeed knowledge archive in real time to reflect new IT challenges that can impact the stability of mission-critical systems.

CHAPTER 2. INSTALL RED HAT LIGHTSPEED ON RHEL SYSTEMS

Install the insights-client and register your RHEL systems with Red Hat Lightspeed using various supported installation methods.

2.1. INSTALLATION METHODS FOR RED HAT LIGHTSPEED ON RHEL

Multiple installation methods are available for Red Hat Lightspeed on RHEL depending on your system configuration and management approach.

You can use other supported methods to register and install Red Hat Lightspeed, too. A registration assistant is also available to guide you through the process of registering and installing Red Hat Lightspeed. You can also use the remote host configuration (RHC) tool. The installation method you choose depends on several factors, including whether:

- You are connecting to Red Hat for the first time
- You use a certain version of RHEL
- You want to do an automated installation or a manual installation

2.2. RED HAT SATELLITE INTEGRATION RESOURCES FOR RED HAT LIGHTSPEED

Red Hat Satellite documentation resources provide guidance for installing and configuring Red Hat Lightspeed on RHEL hosts managed by Satellite Server.


- Creating a host in Red Hat Satellite
- Using Ansible roles to automate repetitive tasks on clients
- Managing hosts

2.3. REGISTER AND CONFIGURE SATELLITE SERVER INTEGRATION WITH FEDRAMP

Connect your servers to Satellite Server for communication with Red Hat Lightspeed in the FedRAMP environment.


Before you can use Red Hat Lightspeed with your server, you need to connect your servers to the Satellite Server. The Satellite Server enables your servers to communicate with Red Hat Lightspeed.

An IP address-based allow list restricts network access to the Red Hat Lightspeed service. This ensures that only the servers and ports that you specify can connect to the Satellite Server.



NOTE

Red Hat Lightspeed subscription services are currently not available in the FedRAMP environment. Red Hat continuously evaluates service offerings, and will announce any updates or expansions to the FedRAMP environment as they become available.



NOTE

The following requirements are in addition to existing Satellite Server connectivity requirements to the Red Hat Content Delivery Network and Red Hat Subscription Manager for software updates. For more information about connectivity requirements, refer to How to access Red Hat Subscription Manager through a firewall or proxy (Red Hat Knowledgebase).

Prerequisites

- The Satellite Server can connect to the domain **mtls.console.stage.openshiftusgov.com** by using the HTTPS protocol on port 443.
- A static public egress IP address (or address range) is configured for Satellite traffic to originate from. The public egress IP address is an additional IP address on the primary network interface of your server.



NOTE

Contact Red Hat Support to set up the public egress IP address.

- You are logged in to the Hybrid Cloud Console (https://console.openshiftusgov.com) as an Organization Administrator.
- You have administrator **ssh** access to the Satellite Server.
- You are logged in to the Satellite Server using **ssh**.

Procedure

1. From the main menu, navigate to **Inventory > Configure Satellites** The Configure Satellites page displays.
2. Click **Generate Token** to create the registration token for your organization.
3. Copy the token.
4. Open a terminal window on your Satellite Server and enter the following command:

```
# hammer organization list
```

   The system returns your organization ID. Make note of it for the next step.

5. Copy the command shown in Step 3 on the Configure Satellites page. Paste it into the terminal. Substitute the organization ID for **<organization_id>**.

```
# SATELLITE_RH_CLOUD_URL=https://mtls.console.openshiftusgov.com org_id=
<organization_id> foreman-rake rh_cloud:hybridcloud_register
```

   The system returns a prompt for the token that you generated.

6. Paste the generated token that you copied at the prompt and press **Enter**.
   The system returns a success message. You can now register the system with Satellite and run **insights-client**.

Additional resources

- *Hammer CLI Guide* (Red Hat Knowledgebase)
- Registering RHEL systems and configuring client tools with Red Hat Lightspeed
- *Installing the Satellite Server in a disconnected network*

2.4. MANAGE TRUSTED IP ADDRESSES WITH AN IP ALLOWLIST

Configure an IP allowlist with trusted addresses to connect Red Hat Lightspeed to your Satellite Servers.

2.4.1. IP allowlist configuration methods

Configure the IP allowlist with Red Hat Support during onboarding or manually through the Hybrid Cloud Console to allow network traffic from your Satellite-controlled environment into Red Hat Lightspeed.

You can configure the allowlist in the following ways:

- Provide the trusted IP address (or addresses) to Red Hat stateside support during onboarding. Support uses the IP addresses to configure an allowlist for Red Hat Lightspeed. This allowlist allows network traffic from your Satellite-controlled environment into Red Hat Lightspeed.
- If you have not created the allowlist during onboarding, use the IP allowlist in the **Manage Satellites** page in the Red Hat Hybrid Cloud Console to manually add trusted IP addresses.

2.4.2. Add trusted IP addresses to an allowlist

Add trusted IP addresses to an allowlist to enable FedRAMP users in your organization to access the Hybrid Cloud Console.

You can create a new allowlist or add an IP address (or range of IP addresses) to an existing allowlist.



NOTE

Manage Satellites allows only IPv4 addresses. It does not support IPv6 addresses.


To add a range of IP addresses, use CIDR notation (for example, 226.167.71.76/32).

Prerequisites


- You have Organization Administrator permissions.
- You are logged in to the Hybrid Cloud Console.

Procedure


1. Click **Manage Satellites**. The **Manage Satellites** page opens.
2. Scroll down the page to the IP Address Allowlist section at the bottom.



3. Click **Add IP Addresses**. The **Add IP Addresses to Allowlist** dialog box opens.



4. Type an IP address (or range of IP addresses) and click **Submit**. The IP addresses appear on the allowlist.



2.4.3. Remove IP addresses from the allowlist


Remove IP addresses from the allowlist to revoke access to the Hybrid Cloud Console for specific systems or users.

Prerequisites

- You have Organization Administrator permissions.
- You are logged in to the Hybrid Cloud Console.
- You have an IP allowlist configured.
- You have added at least one IP address (or range of IP addresses) to the allowlist.

Procedure

1. Click **Manage Satellites**. The **Manage Satellites** page displays.
2. Scroll down the page to the **IP Address Allowlist** section at the bottom.
3. Select the IP address you want to remove, and then click **Remove**. The **Remove IP Addresses from Allowlist** dialog box displays.



4. Click **Remove**, and then click **Submit**.

Additional resources

- Registering RHEL systems and configuring client tools with Red Hat Lightspeed

2.4.4. Additional resources

- Red Hat stateside support

CHAPTER 3. MANAGE USER PERMISSIONS FOR RED HAT LIGHTSPEED SERVICES

Manage user permissions to control access to Red Hat Lightspeed applications. Use the User Access feature to apply role-based access control (RBAC). Red Hat provides predefined groups and roles to help Organization Administrators manage user permissions.

3.1. USER ACCESS OVERVIEW

You can simplify access management in the Red Hat Hybrid Cloud Console by using role-based access control (RBAC). The User Access feature assigns specific permissions to roles instead of individual users, which are then inherited when roles are assigned to user groups.

You can also create custom groups and roles to provide more fine-tuned control over specific features of Red Hat Lightspeed to suit the needs of your organization.

If you are an Organization Administrator, you can use the User Access feature under **Identity & Access Management → User Access** in the Hybrid Cloud Console to:

- Control user permissions and organize roles.
- Create groups that include roles and their corresponding permissions.
- Assign users to these groups, allowing them to inherit the permissions associated with their group's roles.

All users on your account have access to most of the data in Red Hat Lightspeed.

Additional resources

- User Access in the Hybrid Cloud Console
- User Access Configuration Guide for Role-based Access Control (RBAC) with FedRAMP

3.2. PREDEFINED GROUPS IN USER ACCESS

The two predefined groups available in User Access, **Default access** and **Default admin access** provide different baseline privilege levels for users in your organization. You can also create custom groups to align permissions with specific personas, job functions, or teams in your organization.

The Default access group

By default, the **Default access** group is assigned many granular predefined roles, so that group members have basic visibility. Because all users in your organization are members of the **Default access** group, they inherit all permissions assigned to that group. The **Default access** group is automatically updated by Red Hat.



IMPORTANT

If your Organization Administrator modifies the **Default access** group, the group is automatically renamed to **Custom default access**. Once converted, this group is no longer automatically updated by Red Hat.

The Default admin access group

The **Default admin access** group contains only users who have Organization Administrator permissions. This group is automatically maintained, and users and roles in this group cannot be changed.

The **Default admin access** group includes many (but not all) predefined roles that provide update and delete permissions. The roles in this group usually include **administrator** in their names.

TIP

To view the roles included in the **Default access** or **Default admin access** group, log in to the Hybrid Cloud Console, navigate to **Groups** in User Access, and select the group.

Additional resources

- User Access groups

3.3. PREDEFINED ROLES ASSIGNED TO GROUPS

Understand how predefined roles in Red Hat Hybrid Cloud Console bundle permissions across multiple Red Hat Lightspeed applications to align with common user personas. Use predefined roles to reduce administrative effort, or create custom roles for more fine-tuned control over specific features.

The predefined roles are a starting point to help you control and manage user permissions. You can then use these roles to create custom roles that are tailored to your specific use cases and organization. For example, you can use the predefined granular roles to create custom roles that provide more fine-tuned control over specific features of Red Hat Lightspeed.

TIP


Across the Red Hat Lightspeed product documentation, the **Prerequisites** section for each procedure lists which predefined roles provide the permissions needed to use the features in that procedure. For example, if a procedure requires permissions to create and view remediations, the **Prerequisites** section for that procedure lists the *Remediations user* or other valid role as a recommended predefined role to use for that procedure.

Additional resources

- Predefined User Access roles

3.4. CHECK YOUR PERMISSIONS

Verify your current permissions and the roles or groups assigned to you in the Red Hat Hybrid Cloud Console. Check your permissions to troubleshoot access issues or understand your level of access to Red Hat Lightspeed applications.



NOTE

Only users with the Organization Administrator role can view the permissions of other users in the User Access settings and manage user permissions to Red Hat Lightspeed services. For more information, see the *Configure user permissions* section.

Prerequisites

- You are logged in to the Red Hat Hybrid Cloud Console.

Procedure

1. Click the **Settings** icon (⚙), then navigate to **Settings → Identity & Access Management→ My User Access**.
2. If you try to access Red Hat Lightspeed features and see a message that you do not have permission to perform this action, contact your Organization Administrator or a user with the **User Access administrator** role to request the permissions required to access those features and complete the actions you want to perform.

Verification

All of the applications that you have permissions to access are listed on this page and are grouped by product, for example, RHEL, OpenShift Container Platform, and Ansible Automation Platform.

You can also filter your permissions by application, for example, by advisor, cost management, inventory, and remediations.

Additional resources

- User Access Configuration Guide for Role-based Access Control (RBAC) with FedRAMP
- Procedures for configuring User Access

3.5. CONFIGURE USER PERMISSIONS

If you are an Organization Administrator, you can view and manage user permissions for all users in your organization. Control access to Red Hat Lightspeed and other Red Hat Hybrid Cloud Console services through the User Access interface.



IMPORTANT

If you are not an Organization Administrator, you are unable to complete this task. However, you can check your own permissions for different applications by navigating to **Settings → Identity & Access Management→ My User Access**. Contact your Organization Administrator to request more permissions.

Prerequisites

- You have logged in to the Red Hat Hybrid Cloud Console as an Organization Administrator, or you have the required administrator User Access role permissions.

Procedure

1. Click the **Settings** icon (⚙), then navigate to **Settings → Identity & Access Management→ User Access**.

Verification

From here, you can create and manage:

- **Settings → Identity & Access Management→ User Access → Roles** to determine permissions to Red Hat Lightspeed services and features

- **Settings → Identity & Access Management→ User Access → Groups** to include one or more roles to align with a specific persona, job function, or team in your organization
- **Settings → Identity & Access Management→ User Access → Users** and their assignment to groups to inherit permissions from the roles assigned to those groups

Additional resources

- User Access Configuration Guide for Role-based Access Control (RBAC) with FedRAMP
- Procedures for configuring User Access