

Header And Logo



Peripheral Links

[Donate to FreeBSD](#)

Search

Search

Site Navigation

- [Home](#)
- [About](#)
 - [Introduction](#)
 - [Features](#)
 - [Advocacy](#)
 - [Marketing](#)
- [Get FreeBSD](#)
 - [Release Information](#)
 - [Release Engineering](#)
- [Documentation](#)
 - [FAQ](#)
 - [Handbook](#)
 - [Porter's Handbook](#)
 - [Developer's Handbook](#)
 - [Manual Pages](#)
 - [Documentation Project Primer](#)
 - [All Books and Articles](#)
- [Community](#)
 - [Mailing Lists](#)
 - [Forums](#)
 - [User Groups](#)
 - [Events](#)
- [Developers](#)
 - [Project Ideas](#)
 - [GIT Repository](#)
- [Support](#)
 - [Vendors](#)
 - [Security Information](#)
 - [Bug Reports](#)
 - [Submit Bug-report](#)
- [Foundation](#)
 - [Donate](#)

FreeBSD Manual Pages

geom

man

apropos

All Sections

FreeBSD 15.1-RELEASE and Ports.quarterly

html

[home](#) | [help](#)

NAME

geom -- universal control utility for GEOM classes

SYNOPSIS

```
geom class help
geom [--libxo] class list [-a] [name ...]
geom [--libxo] class status [-ags] [name ...]
geom class load [-v]
geom class unload [-v]
geom -p provider-name
geom -t
```

DESCRIPTION

The **geom** utility is used to control various GEOM classes. A class has to be aware of **geom** communication methods, but there are also some standard commands which can be used for existing **geom** unaware classes. Here is the list of standard commands:

- help** List all available commands for the given class.
- list** Print detailed information (within the given class) about all geoms (if no additional arguments were specified) or the given geoms. This command is only available if the given class exists in the kernel. Additional options include:

-a Print information for geoms without providers.
- status** Print general information (within the given class) about all geoms (if no additional arguments were specified) or the given geoms. This command is only available if the given class exists in the kernel.

Additional options include:

-a When used with **-g**, print status for geoms without providers.

-g Report statuses for geoms instead of providers.

-s Produce script-friendly output.
- load** Load the kernel module that implements the given class. This command is only available if the class does not yet exist in the kernel and the file *geom_<class>.ko* can be found in one of the directories specified in *kern.module_path* sysctl.
- unload** Unload the kernel module which implements the given class. This command is only available if the given class is loaded as a kernel module.

Additional options include:

-p provider-name Print detailed information about the geom which provides *provider-name*.

-t Display geoms hierarchy as a tree.

--libxo

Generate output via [Libxo\(3\)](#) in a selection of different human and machine readable formats. See [xo_options\(7\)](#) for details on command line arguments.

Class-specific commands are implemented as shared libraries which are stored in `/Lib/geom/` directory and are loaded via [dlopen\(3\)](#) function when the class name is known. When a class-specific shared library exists, a direct utility should also be available under the name of `gclass`.

Currently, classes aware of `geom` are:

* CACHE	* MIRROR	* SCHED
* CONCAT	* MOUNTVER	* SHSEC
* DISK	* MULTIPATH	* STRIPE
* ELI	* NOP	* UNION
* JOURNAL	* PART	* VFS
* LABEL	* RAID	* VIRSTOR
* MD	* RAID3	

ENVIRONMENT

The following environment variables affect the execution of `geom`:

`GEOM_LIBRARY_PATH` Specifies the path where shared libraries are stored instead of `/Lib/geom/`. Multiple paths can be specified with a colon-separated list of paths.

EXIT STATUS

Exit status is 0 on success, and 1 if the command fails.

EXAMPLES

The following example shows how to set up a stripe on three disks for automatic configuration:

```
geom stripe label -v -s 65536 data /dev/da0 /dev/da1 /dev/da2
```

or:

```
gstripe label -v -s 65536 data /dev/da0 /dev/da1 /dev/da2
```

Print the list of all providers from the DISK class:

```
geom disk list
```

Unload a kernel module which implements the MD class:

```
geom md unload
```

SEE ALSO

[libgeom\(3\)](#), [geom\(4\)](#), [xo_options\(7\)](#), [gcache\(8\)](#), [gconcat\(8\)](#), [geli\(8\)](#), [gjournal\(8\)](#), [glabel\(8\)](#), [gmirror\(8\)](#), [gmountver\(8\)](#), [gmultipath\(8\)](#), [gnop\(8\)](#), [gpart\(8\)](#), [graid3\(8\)](#), [gshsec\(8\)](#), [gstripe\(8\)](#), [gunion\(8\)](#), [gvirstor\(8\)](#)

HISTORY

The `geom` utility appeared in FreeBSD 5.3.

AUTHORS

Paweł Jakub Dawidek <pjd@FreeBSD.org>

FreeBSD ports 15.quarterly February 5, 2026 *GEOM(8)*

[NAME](#) | [SYNOPSIS](#) | [DESCRIPTION](#) | [ENVIRONMENT](#) | [EXIT STATUS](#) | [EXAMPLES](#) | [SEE ALSO](#) | [HISTORY](#) | [AUTHORS](#)

Want to link to this manual page? Use this URL:
<<https://man.freebsd.org/cgi/man.cgi?query=geom&manpath=FreeBSD+15.1-RELEASE+and+Ports.quarterly>>

[home](#) | [help](#)