

DataMover

User guide

Verified offload for video production: source → verification → independent copies

For DataMover 2.16.3 · macOS and Windows
gordas.dev/datamover

Contents

1	What DataMover does	3
2	Installing on macOS	3
3	Installing on Windows	3
4	Updates	4
5	Preparing an offload	4
6	Checks before you start	5
7	Transfer and verification	6
8	The result	7
9	Delivery reports	8
10	Resuming a transfer	9
11	Settings and language	10
12	Diagnostics	10
13	Differences between macOS and Windows	11
14	Trial and activation	11
15	Known limits	11

1 What DataMover does

DataMover copies footage from a card or folder to several independent drives at the same time. The source is read **once**, and every copy is compared with the source by checksum before it gets its final name.

- **Source** — the camera card or a folder.
- **Verification** — each copy's checksum must match the source's.
- **Independent copies** — two or more drives, each with its own result and reports.

! Do not format the card until every destination shows **Verified**. DataMover lowers the risk of copying; it does not remove it.

2 Installing on macOS

Requirements: macOS 14 or later on an Apple Silicon Mac. The package is Developer ID signed and notarized by Apple, so Gatekeeper opens it without extra steps.

1. Download **DataMover.dmg** from gordas.dev/datamover.
2. Open the DMG. The window contains the **DataMover-x.y.z.pkg** package and this guide.
3. Double-click the package and follow the steps. Accept the license agreement.
4. When asked, enter your Mac's administrator password (the characters are not shown — this is normal), then press Enter.
5. Launch DataMover from the **Applications** folder.

3 Installing on Windows

Requirements: Windows 11, 64-bit (x64). On ARM64 computers the app runs through the system's x64 emulation.

1. Download **DataMover-WPF-Windows.zip** and extract it.
2. Run **DataMoverSetup.exe** and accept the license agreement.
3. The app is installed in Program Files with a Start menu shortcut. The Desktop shortcut is optional; you tick it in the wizard.

! The Windows installer has a **self-signed** signature, not a commercial certificate. Windows SmartScreen may show "Windows protected your PC" or "Unknown publisher". If you downloaded the file from gordas.dev, click **More info** → **Run anyway**.

Uninstall from **Settings** → **Apps**. This also removes DataMover's settings, local license and diagnostic logs; data of other GDC apps is left untouched.

4 Updates


At launch, DataMover checks for a new version and shows you the version number and what's new. You can also check manually from the app.

- **macOS — Download & Install** downloads the package, checks its version and signature, asks for your administrator password and restarts the app. **Later** postpones that version.
- **Windows** — in the "Actualizare disponibilă" (update available) window, **Yes** downloads the installer and opens the setup wizard; the app closes and starts again after installation. **No** postpones the update.
- An update is never installed in the background without your consent.

5 Preparing an offload

Fill in **Project** and **Card** in the top bar. They form the name of the folder created on each destination (for example 2026-09-26_PROJECT_A001).

- **Source** — drag the card or folder onto the Source area, use the add button, or pick it from the device list.
- **Destinations** — add at least one copy; for safety, use two different drives. On macOS, drag a drive onto "+ another copy" or choose its role from the device menu; on Windows, click **Copy** under the device.
- **Verification** — xxHash64 by default (fast). You can choose MD5, SHA-1, SHA-256, SHA-512 or "size only" in Settings.



macOS, preparation: the source, both copies and the warnings before start (interface in Romanian).

6 Checks before you start


Before you start, the app checks the route. **Blocking** problems disable the start button; **warnings** don't block, but are worth reading before you format the card.

Situation	Type
Destination inside the source (or the other way round)	Blocking
The same destination picked twice, nested destinations	Blocking
Missing path or no write permission, name collisions	Blocking
A copy would sit on the same drive as the source	Warning
Not enough space at a destination	Warning, with confirmation
Unusual card structure (e.g. 0-byte files)	Warning


7 Transfer and verification

Click **Start transfer**. The source is read once and written to every copy in parallel. Each file is written first with the temporary **.dmpart** extension and gets its final name only after the flush to disk and after the copy's checksum matches the source.

- Progress is shown for each destination; the figures are measured, not estimated.
- You can **Pause** or **Cancel** the transfer.
- If a drive disconnects, the problem shows up only for its destination; the other copies carry on.
- A file that changes on the card during the copy is marked unconfirmed.



macOS, transfer in progress: measured progress for each copy.




Windows, transfer in progress: the same logic in a native Windows interface.

8 The result

At the end you get one unambiguous verdict and a result for each destination.

Verdict	Meaning
Verified	Every file passed the selected verification at every destination.
Verified, with warnings	Everything is confirmed, but some files only succeeded on retry. Check the cable, card and drives.
Partial failure	At least one destination has unconfirmed files. Do not format the card.
Failure	No destination has a complete confirmed copy.
Cancelled	The transfer was stopped; confirmed files are kept.



macOS, result: each copy confirmed on its own, with its reports.

i Automatic card ejection (optional, in Settings) happens only when every destination has a confirmed copy.

9 Delivery reports

In the folder created on each destination, DataMover writes:

- **PDF and HTML** — the delivery report: the destination's verdict, a summary (files, data confirmed, duration, verification), project, card, operator and the file list with checksum and status. The HTML opens in any browser and prints on A4.
- **CSV** — the full list, one row per file (columns: file, size, source check, destination check, status, error). It is UTF-8 with a byte-order mark so accented characters read correctly.
- **MHL** — the hash list for the post-production chain of custody. It is generated only with xxHash64, MD5 or SHA-1, the algorithms the MHL standard accepts.
- **offload_checkpoint.json** — used when resuming.

DataMover

<

First page of the PDF report (test data, in Romanian).

- i** For very large transfers, the PDF and HTML show every problem plus a sample; the full list is in the CSV.

10 Resuming a transfer


If a transfer was interrupted, start it again with the same source and destinations. With **Resume automatically from an existing checkpoint** (on by default), DataMover re-reads the source and the copy of every file already confirmed: they must match the checksum saved at confirmation, otherwise the file is copied again.

- A name, size or date alone is never enough to skip a file.
- A checkpoint made with another algorithm or for another folder is ignored.
- In “size only” mode, resuming copies everything again.

- !** Resuming has been tested after simulated interruptions. Behaviour after a real power cut or a physically removed drive has not been verified yet — after such an incident, check the final result.

11 Settings and language

macOS — DataMover menu → Settings, with the General, Verification, Reports, Performance, Cloud, Account and Diagnostics tabs. In General you choose the language (Romanian, English, Spanish) and the appearance (System, Light, Dark), plus opening the destination, ejecting the card and starting automatically when a card is inserted.



macOS, Settings → General (interface in Romanian).

Windows — the **Settings** button in the top bar: verification, MHL, automatic retry, performance profile, report logo and theme. The Windows interface is in Romanian.

12 Diagnostics

DataMover keeps a local technical log. Nothing is sent automatically. If you have a problem, export the diagnostics and send us the ZIP file.

- **macOS** — Help → Export diagnostics... (or Settings → Diagnostics).
- **Windows** — the **Diagnostic** button at the bottom → Export diagnostics.
- The export contains the logs, the version and a summary of the last transfer. Paths and file names are replaced with codes; it contains no media files, passwords or license codes.

13 Differences between macOS and Windows

Both apps follow the same copy rules and produce the same kinds of reports with the same information. The interfaces are native and differ:

	macOS	Windows
Interface language	Romanian, English, Spanish	Romanian
Report language	The app's language	Windows language (ro/en/es), else Romanian
Signing	Developer ID, notarized by Apple	Self-signed (SmartScreen may warn)
Updating	Automatic install, with password	The Windows setup wizard
In-app guide	Help, in the app's language	Guide button, in Romanian

14 Trial and activation

- 7 days fully functional, no account, no card.
- After the trial, the unactivated version copies at most 2 GB per transfer.
- Activation is tied to your computer's ID and comes with a development **donation**; the current amount is shown in the app. Open Profile → Activate and send us your computer ID on WhatsApp.

15 Known limits

The scenarios below have not been verified yet. Don't consider them covered until you have tested them in your setup:

- a real power cut or hard shutdown during a copy;
- a card or drive physically removed during a transfer;
- network destinations (SMB) and exFAT drives on Windows;
- a real full disk on Windows;
- keyboard-only navigation and screen readers on Windows.