


Settings Generator



Generate settings for your game within seconds.

Table of contents

180+ pages of documentation, what the hell?	6
Beginner Guide (read this first)	7
Overview (read this second)	10
Configuration	10
Config (Settings Generator Settings)	11
Provider	12
Settings (list of settings)	12
User Interface	14
Initialization	17
Settings_INITIALIZER (optional)	17
Accessing Settings	18
Manual setting creation (optional reading)	19
Creating Settings Files	19
Adding the Settings_INITIALIZER (optional)	20
Adding UI	21
Hook up some code (optional)	22
Detailed Guide (optional reading)	24
What is it doing exactly?	24

How is it doing it? (aka "How to generate a new setting in UGUI").....	25
What are those IDs?.....	28
Creating your own Settings and Settings Provider.....	29
Initializing Settings: When are the settings applied for the first time?.....	33
Copying the example settings UI into your own game.....	35
Step 1: Create a new SettingsProvider object.....	36
Step 2: Make sure the settings are initialized (loaded) at the start.....	37
Step 3: Copy the example UI into your game.....	39
An alternative to step 3 is using your existing UI:.....	45
Step 4: (Optional) Delete or disable unused settings.....	51
Connecting a setting to a property, field or method.....	53
Combining the Settings System with other Assets.....	54
SettingsApplier.....	55
Settings.....	56
Basic Types (Bool, Int, Float, String).....	57
ColorOptions.....	57
Options.....	57
Key Combination (OLD KeyCode based input system).....	57
How to work with KeyCombinations.....	58
Input Binding: StringSetting + InputBindingConnection (NEW InputSystem).....	58
Setting Resolvers.....	59
Auto-Save.....	60
Setting Events.....	61
UI Systems Overview (IMGUI vs UGUI vs UI Toolkit).....	62
IMGUI (not supported).....	63
UGUI (fully supported).....	63
UGUI Components.....	63
PC Style & Console Style.....	64
Converting between PC and Console style.....	64
PC Style uGUI Prefabs.....	65
Color Picker UGUI & Color UGUI.....	65
Dropdown UGUI.....	66
Headline UGUI.....	67
Input Key UGUI.....	67
Input Binding UGUI.....	67
Options Button UGUI.....	68
Slider UGUI.....	69
Stepper UGUI.....	70
Textfield UGUI.....	71
Toggle UGUI.....	71
CONSOLE Style uGUI Prefabs.....	72
Color Picker Console UGUI.....	72
Input Binding & Input Key Console UGUI.....	73
Options Button Console UGUI.....	73
Slider Console UGUI.....	73
Stepper One Button Console UGUI.....	73
Stepper Two Buttons Console UGUI.....	73
Stepper One Button Steps Console UGUI.....	74

Textfield Console UGUI.....	74
Toggle Console UGUI.....	74
UGUI Helpers.....	75
Auto Navigation Overrides.....	75
Selection Event Listener.....	75
Scroll Into View On Select UGUI.....	76
SelectionUGUI.....	76
UI Toolkit (full logic, fewer components, Unity 2021.2+).....	77
UI Toolkit Resolvers.....	78
Linking a Visual Element to a Setting (guide).....	78
Linking a Visual Element to a Localization.....	81
UI Toolkit Components.....	82
DropdownField.....	82
Toggle.....	83
Slider.....	83
TextField.....	83
Helper: UIElementClickEvent.....	84
Helper: UIElementEvents.....	84
Connections.....	85
Ambient Occlusion (SSAO).....	86
Caveats (mostly URP).....	86
Anti Aliasing.....	86
Audio Mixer.....	88
Audio Paused.....	90
Audio Volume.....	90
Audio Source Volume.....	90
How to make sound groups for "effects", "music", "voice", ...?.....	90
Bloom.....	92
Color Grading (lift, gain, midtones, mixer, temperature, tint, ...).....	92
Depth Of Field.....	92
Camera Clipping / Render Distance / Draw Distance.....	92
Fog.....	93
Field Of View.....	93
Frame Rate.....	94
Full Screen.....	94
GetSetConnection<T>.....	94
Gamma.....	94
InputBindingConnection.....	94
Microphone.....	94
Motion Blur.....	95
Monitor.....	95
MSAA.....	95
Quality.....	96
Refresh Rate.....	96
Resolution.....	96
RenderScale.....	98
Shadow.....	98

Shadow Distance.....	98
Shadow Resolution.....	98
Texture Resolution.....	98
Vignette.....	98
Volumetrics Enabled (HDRP).....	98
V-Sync.....	99
Window Mode.....	99
Input Binding (Using the new Input System).....	100
Rebinding Overview.....	100
Rebinding Tutorial.....	100
Prerequisites.....	100
Adding Input Bindings.....	101
Input Binding Details & Troubleshooting (optional reading).....	104
How to resolve binding conflicts.....	108
Input Binding Caveats.....	109
Multiple Player Input Components.....	109
Working with Auto-generated script code for Actions.....	111
What about Composite Bindings?.....	112
How to display the key binding in my UI?.....	114
Scripting API (Adding custom Settings).....	115
How to get access to the API if you are using Assembly Definitions.....	115
How pull the value from a setting.....	116
How to get notified of a value change in a setting.....	117
Using the GetSetConnection<T>.....	118
Making a custom Connection class.....	120
The IConnectionWithSettingsAccess interface.....	122
Changing the save & load method.....	123
Settings Save Locations.....	123
Auto-Deleting Saved Settings (for testing).....	123
Adding custom save & load methods (code only).....	124
Localization.....	126
Third Party Localization Support (example: I2 Localization).....	127
Unity Localization Support.....	128
Localization API.....	132
Changing the language via Script.....	132
Localizing Key Control Paths.....	133
Visual Scripting (formerly BOLT).....	135
Configuration & Debugging.....	138
Input Validation.....	139
Validation via OnChange events.....	139
Validation via Connection objects.....	140
Upgrading from older versions.....	143
Actions to perform after updating to fix example scenes.....	143
Third Party Integrations.....	144
Rewired Integration.....	145
Rewired Input Remapping (Recommended).....	146

Using Rewired with Settings UI (Not Recommended).....	150
InControl Integration.....	152
TheNakedDev UpScalers (FSR, DLSS, SGSR, XeSS).....	153
(OLD) DLSS Connection (by "The Naked Dev" formerly "Alterege Games").....	153
(OLD) FSR Connection (by "The Naked Dev", formerly "Alterege Games").....	157
(OLD) SGSR Connection (by "The Naked Dev").....	160
(OLD) XeSS Connection (by "The Naked Dev").....	161
PlayMaker.....	162
MasterAudio.....	163
Common Issues / FAQ.....	164
Post Processing Settings do nothing.....	164
Post Processing Render Context Null Pointer.....	164
Post Processing not visible on mobile (Built-In render pipeline).....	164
Controller X is not working properly (Old Input System).....	164
The example scenes are all pink after updating the asset (URP or HDRP).....	164
InvalidOperationException: You are trying to read Input using	165
The Post Processing effect is not found.....	166
I have upgraded from an older version but don't see the new examples?.....	168
Rebinding input actions has no effect. Why?.....	168
How to add a "Mouse Sensitivity" setting?.....	169
There are some errors in URP or HDRP Connections but I am not using URP or HDRP?!.....	170
My settings work in the menu but not in the level?.....	171
DLSS: I have a multi camera setup and the DLSS setting does only apply to the camera tagged with "MainCamera".....	172
I can't get mouse interaction to work with the settings prefabs?.....	172
I have removed a setting but it still gets applied at the start?.....	173
I have an asynchronous connection. How should I handle this?.....	174
I have a connection that changes the value during runtime.....	178
Is there a way to have buttons/keys as icons (like a green "A" button and not "buttonSouth")?	179
How to inform users of unapplied settings?.....	180
Can I use multiple connections for one setting?.....	180
Is PlayMaker supported?.....	181
How to bind to mouse wheel up or down (mouse scroll).....	181
I get a „Got 'Kamgam.SettingsGenerator.SettingString' but can only handle types: KeyCombination" error.....	182
I get a „error CS0311: The type .." error.....	182
I get a "Cannot find action map 'gameplay' in actions" error in the InputSystemDemo.....	183
Jump works but movement does not in the InputSystemDemo.....	183
There is only on quality option called "Pc". Why?.....	184
How to remove or deprecate old settings?.....	184
How to add a "change language" menu?.....	186
PlayerInput: Input rebinding works only partially or not at all after (re)starting the game. Why?	189
I need to initialize the settings late (not automatically).....	189

180+ pages of documentation, what the hell?

First, thank you for opening the manual. I know it looks daunting.


The reason for this long documentation is that in here you will find an explanation for all the options (there are a lot) and pretty much any edge case I have heard of (FAQ).

When in doubt just follow the "[Beginner Guide](#)" and use the "**Settings Creator**" window (Window > Settings Creator). The detailed guides are for those who want to understand the inner workings of it all but usually that should not be necessary.

Beginner Guide (read this first)


For starters I recommend using the “Setting Creator” window. Once you are more familiar with how everything works you can switch to creating your settings manually if needed.

1) Open the “Setting Creator” via “**Window > Settings Creator**”




That window may look daunting but fear not. You need not touch any of the settings (yet).

HINT: General Settings for your project are under the “Provider” section and the actual settings are listed under “Settings” (that’s also where you can add your custom settings if needed).




2) Click on the “User Interface (UI)” tab on the top right.



Now here you can decide whether you want to create a new settings window from scratch (3) or add settings to an existing UI (skip to step 4). For beginners I would recommend to create a new window from scratch (3).


3) Click the “Create ... Style Window” button to create a new settings window in your scene.




HINT: All this does is basically copy the “Settings_PC (Template)” or “Settings_CONSOLE (Template)” into your scene and apply the provider to it (more on that later).

And that is all you need to do to get a basic settings window. However, I assume you want to add some custom settings for your game (most likely some input bindings). If yes please proceed with the next step which shows how to add individual settings.

4) Select the UI container (RectTransform) to which you want to add a setting to.




Then click the “Add New Setting” button at the bottom.




NOTICE: New settings will be added to the “UI Container” you have selected in the Hierarchy.

5) Choose your setting.


HINT: You can also just double-click to create it instantly.



Click “Add” to add this setting as a new child to the selected object in the UI.




A new setting will be created in the "UI Container" you have selected (below a very simple UI):



That's it :-). If you hit play now you can already use your new settings.

NOTICE: By default the creator window saves the settings resources under "Assets/Resources/SettingsGenerator".



△ For **Input Binding** please check out the Tutorial Video here -> <https://youtu.be/5RIA8PxKYUE>


If you have any question please don't hesitate to write to me under office@kamgam.com or post in the [Unity Discussions Thread](#). I am always there to help!

Overview (read this second)


This overview does explain the basics of the settings system. It answers where you setting configurations are stored and how the system is bootstrapped at the start of you game.

Configuration

The main hub for configuring the settings is the Settings Creator Window (Window > Settings Creator).




The "Configuration" tab of the creator window is just a nice UI to manage all the config data. If you want to inspect the data directly then check the Resources/SettingsGenerator folder. In there you will find all the files that make up your settings configuration.



You may wonder why the data is split into three files. It's mainly for backwards compatibility and Editor-vs-Player reasons. They are all configured via the creator window.

Here is an overview of how the data is structured:




As you can see the config (SettingsGeneratorSettings in the screenshot above) is the root of it all. It is stored in the Assets/Resources/SettingsGenerator folder and thus is part of your build. It references a default provider object which in turn references the actual settings list. The default provider should never be empty. It is the reference to the settings that will be used in the project.

NOTICE: Usually a project has only one config, one provider and one settings list. However if you also imported the examples then you will have multiple providers in your project and if you open the Creator window with an example scene opened it will automatically set the default to the example provider (it will also revert this if you open a regular scene).

When in doubt, check that the Default Provider field is set to your own settings provider.

Config (Settings Generator Settings)


While it is recommended to use the Creator Window for all your configuration I will show you the details of the config here:



As you can see the config is little more than a storage for some logging options and the default provider (also shown in the Creator Window).

Provider

The “provider details” in the creator window is actually just a view into the provider asset:




In the provider you will find options for setting initialization, save, load and most importantly a reference to the actual settings list.

HINT: You can find more details on the provider in the Detailed Guide section.

Settings (list of settings)


The “Settings Details” in the creator window is actually just a view into the settings asset:




Due to historical reasons (backwards compatibility) the settings are grouped by data type.

Okay, so far we have only dealt with configuring settings and you may ask yourself how they are actually linked to the UI and how they trigger any changes in the game code.

For this is we need a more detailed graph:




UI: Each setting has an ID and there is a component (MonoBehaviour) that can take this ID and find the setting. These components are called **Setting Resolvers** and you will find them in all the UI prefabs of the system. They are used for uGUI as well as UI Toolkit.



Code Connection: Each setting may also have a connection. If a connection is set then if the value of a setting changes it will be pushed to a connection object. The connection then executes some code based on that value.


You can make your own connections or use some of the many predefined ones:




NOTICE: You do not have to make a custom connection to react to the a value change in a setting. There are components you can use ("Setting ... Event" components) or code events you can subscribe to on a per-setting level. Creating custom connection usually is overkill.

User Interface


If you open the creator window in an empty scene you will notice that the settings list will be empty. That is because it scans the selected **UI Container** for **Setting Resolvers** and shows them in the list (you add new ones with the "+" button at the bottom).



If there are no resolvers in the scene then it will offer buttons to create a new settings window for you from scratch:



After creating a settings window in your scene you will notice that the list of settings will be filled. That's because now there are some setting resolvers in the scene and the selected UI Container in the hierarchy now contains some of these setting resolvers.




The settings in the list are actually not really all your settings but only the resolvers that have been found in your UI. You can configure them in the creator window or directly on the components in your hierarchy. I recommend to stick with the creator window if you are new to the system.

HINT: You can use the = in the creator window to change the order of the settings.

HINT: You can use the lock icon on the UI Container to keep it from changing with the hierarchy.

Some of the settings will be dimmed. Those are from resolvers that are currently inactive in the hierarchy. It's just a convenience feature.



Please notice that the settings in the list here are NOT all your settings. These are just the resolvers within the currently selected UI Container.


If you click on Edit on a setting in the list it will allow you to configure that setting but to add/remove settings you will have to go to the Configuration > Setting Details.

You may ask why? Well, one setting can have multiple resolvers (UIs). For example you may have a big settings window in the main menu of your game but also a quick settings menu in your pause screen (typically audio on/off etc. is shown in multiple locations). Therefore the setting configuration is separated from the resolvers (UI). One config can be used in many resolvers in many different places.


HINT for coders: There is an `ISettingResolver` interface and a `SettingResolver` class that you can use to make your own resolvers if you want. The resolver does not have to be a UI. It can also be an object in the game. Many of the Helper and Event components are made that way.

Resolver Details

If we take a closer look at one of the resolvers you can see that it takes three pieces of data: a `LocalizationProvider` (optional), a **settings provider** (optional since v1.68) and a setting **ID**.




The resolver uses this information to find the correct setting in the correct provider.



INFO: In older versions of the system there was no default provider and thus each resolver had to have a reference to the used provider. Since version 1.68 if the provider field is left empty it will use the default provider from the config.

Most of the examples and auto generated resolvers still set the provider explicitly. There even is a button to do it for you in the whole scene:



Initialization

You may wonder when and how the settings system is initialized.

By default it initializes using the `RuntimeInitializeOnLoadMethod` ([Unity Manual](#)) like this:

```
[RuntimeInitializeOnLoadMethod(RuntimeInitializeLoadType.AfterSceneLoad)]
```

HINT: If needed this can be disabled via the `DisableAutoInitialization` option in the provider.

This means it initializes AFTER **Awake()** and **OnEnable()** have been executed. The reason for this is that some of the Unity's internal system (like Volumes or AudioMixers) init themselves in `OnEnable()` and thus the settings system has to wait for them to be ready before it can override those settings.


IMPORTANT: **Do NOT access the settings in Awake()**. The settings code needs to wait for Unity's stuff to initialize in `Awake()` before it can apply certain saved settings. **Use Start()** instead.

Settings_INITIALIZER (optional)

You can also manually initialize the settings at the very start by using the **SettingsInitializer Prefab**. If an initializer prefab is present in the scene then the system will not auto initialize but instead use that initializer component to do it.

Why does this exist? -> Backwards compatibility. and the `DisableAutoInitialization` option. In older versions of the asset automatic initialization was not present and thus the initializer component was required. You may still find it in the examples as in those it is used to avoid using the default provider. You can also use it to force initialization if `DisableAutoInitialization` is enabled.

The initializer requires one reference, which is the `SettingsProvider`.



HINT: If you want to do some stuff before the settings are initialized then there is a "PreInitializationEvents" property on the Initializer (or the Creator Window) which you can use. Just DON'T access the settings in there as any access would automatically initialize them and the PreInitializationEvents are actually executed in `Awake()`.


Accessing Settings

You can access the settings in three ways:

1. The easiest way is to use the config and get the default provider from it like this:
`SettingsGeneratorSettings.GetSettings()` or
`SettingsGeneratorSettings.GetProvider()`

2. Another very common way is to add a public `SettingsProvider` reference to any `MonoBehaviour` that needs access to the settings:

```
public SettingsProvider SettingsProvider;
```



3. If you know your settings have already been initialized then you can use the Providers's static API. Though, this is the least recommended way.

```
SettingsProvider.LastUsedSettingsProvider.Settings
```

Getting a setting value can be done by pull (you ask for the value) or push (the value is pushed to a method).

Pulling a value from a setting:

```
var settings = SettingsInitializer.Settings;  
SettingFloat volume = settings.GetFloat(id: "volume");  
Debug.Log( volume.GetValue() );
```

Registering a callback to receive value changes:

```
Settings settings = SettingsInitializer.Settings;  
settings.GetFloat("volume").OnSettingChanged += (ISetting setting) => {  
    Debug.Log( setting.GetFloatValue() );  
};
```

HINT: There is also an "OnValueChanged" event that you can use instead of "OnSettingChanged". It takes care of the data type for you and makes the code a fair bit shorter.


Manual setting creation (optional reading)

You may have noticed that the asset comes with some example scenes. These scenes use premade Settings and SettingsProviders. You can (but shouldn't*) use those in your game. **I strongly recommend that the first thing you do is make your own SettingsProvider and Settings list.**


* Be aware that if you use the providers from the template then you will have to be very careful if you upgrade the asset in the future. The example assets will be overwritten (re-imported) by any update (your changes will be lost).

Creating Settings Files

The first thing you should do is create a folder in which your settings files will be stored. I like to name that folder "GameSettings" but you can name it whatever you like.




Within that empty folder right-click and choose:
Create > SettingsGenerator > SettingsProvider:




SettingsProvider (MyGame) ← **Name your provider** so you can find it easily in the future.


By default the provider should ask you to create a settings list (click YES).



After that you should see a settings list in you inspector, like this:



There should now be two files in your "GameSettings" folder:




If you have those files then you can proceed to next step.


Adding the SettingsInitializer (optional)

To ensure the settings system is initialized at the very start of your game previous versions of the asset required you to add a "SettingsInitializer" Prefab to the very first scene of your game.


While this is not longer necessary you may still see them in the example scenes (there they are used to force the usage of the example providers instead of the default one).



If you drag it into your scene it will automatically hook up to the last used settings provider. Don't worry, you can change it at any time.




This is how it should look like in your scene:



Adding UI


The asset contains some UI prefabs templates for you to use. Let's try the "SliderUGUI (Setting)".




Once you have dragged in the "SliderUGUI (Setting)" Prefab scroll down to the "...Resolver" Component. You'll see it requires three inputs:

1. Localization Provider (let's ignore this for now)
2. Settings Provider (the SettingsProvider asset we've just created)
3. ID (the setting ID from the Settings list asset we've just created)

Together the Provider and the ID uniquely identify a setting.



Notice the "Suggested IDs" section in the resolver:




This is a list of all the predefined settings that are in your settings list (the “Settings” asset that we created just after the SettingsProvider).

Of course you can add your own custom setting at any time but for now let’s use the existing “ambientLight” setting.

You can either type it in the ID field or you click the button in the list.

HINT: Once you have entered a valid ID the ID label will turn white.


But, what is this? Another red warning and a dialog asking about enabling a setting?



Well, the thing is that by default all your settings in the settings list are disabled. We do this so they don’t intervene with your project right away. However, once a setting is used in any UI element it will assume you want it activated. That’s what this dialog is for.

Naturally we will choose YES.

And that’s it. This is how a properly set up setting will look like:



If you hit play in the Editor and drag the slider it should change the ambient light color of your scene. HINT: Add a cube if your scene is empty to see the change. Skyboxes are indifferent to ambient light changes.

Hook up some code (optional)

If you are a coder then you can listen for changes in the setting value like this:

```
var settings = SettingsInitializer.Settings;
```

```
settings.GetFloat(id: "ambientLight").OnValueChanged += (float value) => {  
    Debug.Log(value);  
};
```

Detailed Guide (optional reading)


I promise this long guide will be easy to understand and it will help you A LOT with getting into all the details of the settings system. Go grab a cup of coffee or a tea. This will take a while :-)

There are multiple parts that play together in making the settings work.

First let's explore what it is doing and then see how it is done.

What is it doing exactly?

The settings system allows you to hook up some code with UI. The code it hooks up with are things that are often used in game settings. Like whether or not the audio is paused for example. A toggle UI might be a good fit for that. It looks like this:



And hooks up to this code:


```
public override void Set(bool audioPaused)
{
    AudioListener.pause = audioPaused;
}
```

Don't worry if you are not a programmer. The system has many code assets predefined for you and you can hook them up without ever touching any code.


How is it doing it? (aka “How to generate a new setting in UGUI”)

Let’s create that audio setting we have just seen (in UGUI).

First we need some music to play so we can hear whether or not our audio setting is working. Let’s create a “Music” game object and add an Audio Source to it. There is a nice recording of the classical “Flight of the bumblebee” in the examples (make sure “Play On Awake” is enabled).




Okay, now first we need a UI. For this demo we will use the “ToggleUGUI (Setting)” prefab. You can of course use your own UI too. The Prefabs are located under “**Runtime/Prefabs/UGUI**” within the Settings Generator folder.




If you select the toggle you will see a LOT of components in the inspector. Most of them are just for convenience and we can ignore them for now. The most important one is:

“Toggle UGUI Resolver”.




Before we make any changes let's just run our little scene and see what happens.




Okay, the settings tool tells us something about our newly added toggle ui is wrong. It complains that it has no ID. Now this is important. **IDs are how the UI finds the setting it belongs to.**

You may have guessed that we need an ID from the glaring **red** warning shown in the Toggle Resolver.

The **Toggle UGUI Resolver** is the one component which connects the UI (the **Toggle UGUI** in our case) to a setting.



But how do we know which ID we need to use? Well, the settings resolver already has a list of suggestions for us. But how is it getting those? What are they? We'll answer these questions later. For now let's just choose the "audioEnabled" ID and then test our demo again.




Okay great, the warning is gone and if we hit the toggle it pauses/unpauses the audio playback.

What are those IDs?


An ID is a unique name for a setting (so we can find it easily). The settings are defined within a **Settings.asset** file (surprise).

There is a “Settings (Template).asset” which contains all the predefined settings. You can find it within the **Resources** folder. You can either rename and change the template or duplicate it and use the new one. Keeping the template around is the recommended workflow as it allows you to go back and look into it for reference.

The settings are grouped into types. The **audioEnabled** setting can be found under **Bools** as it is a boolean (on/off).




Before we dive into the details of the “audioEnabled” setting itself let’s first talk about the other important asset within the Resources folder, the **SettingsProvider**:




The **SettingsProvider** is the object that connects the settings with any object that is interested in it (it “provides” the settings to anyone asking for them).

If you look back at the **Toggle UGUI Resolver** from before then you will notice that it has a reference to the SettingsProvider:



And the SettingsResolver has a reference to the Settings.asset




So the connection is: **Toggle UGUI Resolver** > **SettingsProvider** > **Settings** > Setting (ID)


Creating your own Settings and Settings Provider

Usually we would simply copy the "Settings (Template)" asset and delete the settings we don't need. But to show you how it works we'll do it the manual way (create everything from scratch).


Let's go back to our audio scene and make our very own Settings and SettingsProvider. You can do that via "**Right Click > Create > SettingsGenerator > SettingsProvider**".




The result will be a new SettingsProvider without a Settings asset:




Now we also create a new Settings object via: "**Right Click > Create > SettingsGenerator > Settings**".




Okay, now we have an empty Settings asset:




Let's add our own "audioEnabled" setting to the Settings asset. To do that click on the "+" at the bottom of the Bools list. It will look like this:



Click on the arrow ">" left to "(New Setting)".




Now we enter our ID "audioEnabledSelfMade" and check the "Apply Immediately" and "Default Value" checkboxes.




Okay, we have made our first setting (yay).

We still have to hook it up though (remember the "UGUI Resolver > SettingsProvider > Settings > Setting (ID)" part).


The first thing to do is to hook the Settings up with our SettingsProvider. Simply drag the settings into the "Settings Asset" field of the provider.



Next we have to let our “ToggleUGUI Resolver” know that it should use our new SettingsProvider.



Notice how the “Suggested IDs” change to the ID we have added to our own Settings asset. Update the ID to use our new setting ID.




Okay, ready? Let’s start our demo scene again.


Aaaand it does nothing !?! And there is no warning shown. How disappointing :-/

Well I admit, I tricked you. There is one last step. We have created a new setting “audioEnabledSelfMade” BUT that settings is not yet hooked up to any code (therefore it does not affect the audio volume). After all, until now it’s just a boolean with a name. How was the settings system supposed to know what we wanted it to do?

To hook it up with some code we will use a CONNECTION. Connections are objects representing code. You can assign one connection to every setting. You can find the connections within the “**Resources/Connections**” folder.



Let's go back to our Settings asset and drag in the **"AudioPausedConnection"**, like this:



Okay, now let's try that demo again.

Ah finally, it's working. Well congratulations, you have created your first setting from scratch.

If you want to see a more sophisticated setup in action then open the "Examples/FromAsset" demo.

If you are a programmer and you want to do it all in code then look into the "Examples/FromCode" demo.

If you are interested in the new [InputSystem](#) and how input binding works then look into the "Examples/InputSystemBinding" demo (please read the "[Input Binding](#)" section first).

Initializing Settings: When are the settings applied for the first time?

The settings are automatically loaded at the very first use of the Settings object. But when is that exactly? It's when you access the `SettingsProvider.Settings` property for the first time.

But again, when does that happen? It happens whenever you show (set active) one of the UI elements for the first time (when you use one of the UI resolvers to be precise).

But most games don't immediately show the settings at the start so how do we initialize the settings without showing the UI? Well, all you need is just one line of code on a game object in your very first scene. The "InputSystemBindingDemo.cs" is a nice example:

```
public class InputSystemBindingDemo : MonoBehaviour
{
    public SettingsProvider Provider;

    public void Awake()
    {
        // You may think about adding it to Awake(). DON'T (explanation below).


        // If you want custom SAVE and LOAD methods then you can do it BEFORE the
        // settings are initialized. For this Awake() is the right spot to execute.
        // UPDATE: With v1.40.0 of the asset it is recommended to use a SettingsSaver
        // object instead (see Window > Settings Creator > Provider Details > ..

        // Settings.CustomLoadMethod = customLoad; // <- Notice these are static.
        // Settings.CustomSaveMethod = customSave;
        // Settings.CustomDeleteMethod = customDelete;
    }

    public void Start()
    {
        // We have to call the settings system at least once to initialize the load.
        var _ = Provider.Settings;
    }
}
```


The key code part is the "Provider.Settings". This will init the settings system (if not yet initialized).

The other important part is that the game object you place it on has to be active and a you need to have a SettingsProvider linked, like this:



Be sure to link the right SettingsProvider if you have multiple.

Hint: There is a SettingsInitializer Prefab under ../Runtime/Prefabs.



Do not add the init code to Awake() !**

Here is why:

Some systems, like the post-processing volumes, are initialized in Awake(). If you init the settings in Awake() too then no one knows which one gets executed first (the order is not defined).

If the settings system gets initialized first, then it will not find the Post-Pro volumes (they are not there yet). This will lead to "There was no active '...' PostPro effect" warnings*.

However, if you put your settings init code in Start(). Then the volumes will already be initialized and everyone is happy.


* There is an FAQ about how to set up the post-pro volumes. It also includes information about some circumstances when the warning will be shown even if everything is properly set up (when you load your scenes asynchronously).

** In the past the recommendation was to init the settings in Awake(). Some of the demos still do.

If for some reason you must initialize the settings in Awake() then please use the [DefaultExecutionOrder(int.MaxValue)] attribute to make it execute LAST.

Copying the example settings UI into your own game.

Please notice that since v1.64 the creator window has “Create .. Window” options:



I would recommend using these. While this guide still works it is no longer needed to get a pre-made settings window quickly.

Above you have learned how to create your own settings from scratch. While it is important to know how to do this in order to understand how the settings system works it is also a bit tedious. - In this section you will learn how to integrate the examples into your existing project.


NOTICE: It is not recommended to directly use the example scenes (except for testing).

Why? → Because if you UPDATE the asset in the future then the example assets will be reset (overwritten). This happens even if you move them out of the examples folder.

That's because of the UGUI system Unity uses to track asset files. Each file has a unique GUID and upon import Unity will match these and replace the files based on their GUIDs, not matter where in the Assets folder they are.

Let's assume you already have some UI in your game and you want to replace parts of it with the settings system UI.

Your game:




Notice the EventSystem in the scene. Without an EventSystem and a GraphicsRaycaster on your canvas UI mouse clicks will not be registered. I mention this here because the demo scenes are loading the UI additively and the EventSystem is actually in the main scene. This means if you copy the demo UI into your scene you will have to make sure your scene has an EventSystem in it or else mouse clicks will not work. - Adding an EventSystem is something


experience Unity devs do automatically but I have found that for newcomers it sometimes is confusing.

Step 1: Create a new SettingsProvider object


The provider will automatically create a list of settings for you based on a template that already contains all the demo settings.



Upon creation the provider will ask you if you want to create a settings list too (pick YES):



After creation you now should have two new files (a SettingsProvider and a Settings file):




Step 2: Make sure the settings are initialized (loaded) at the start.


The settings system initializes itself whenever it is used (when a setting UI is displayed for the first time).

However, usually games do not start with the settings screen and thus you should initialize the settings manually to ensure they are loaded right at the start.



To do this add the SettingsInitializer prefab to the FIRST scene that is loaded in your game. You can find it under: **Assets/Kamgam/SettingsGenerator/Runtime/Prefabs**




HINT: You can also use the right-click menu in the hierarchy:



Upon creation the Initializer will pick a Settings Provider automatically.



Usually it picks the correct Provider automatically but it is always a doog idea to double check:



The
Initializer

has some configuration options:


Do Not Destroy: Enable if you are unloading the scene that contains the initializer. This will avoid unloading the initializer. HINT: It's okay to leave this enabled but a more modern approach is to disable this and use [additive scene loading](#) instead.

Apply OnReload: If enabled then it will re-apply the settings in Start() after reloading this scene. If DoNotDestry is disabled then this option is ignored completely.


Step 3: Copy the example UI into your game

Now this is optional, you can of course use your own UI too (see "step 3 alternative" below).


First we need to open the example scene named "Settings FromAssetDemo UI (loaded additive)":




In there we locate the SettingsContainer and copy it:




Back in our game we can simply paste it as a child of our canvas:



The demo UI is optimized for a canvas scaler of 1600x900 (16:9 ratio). Maybe you will have to scale it a bit to make it fit or update your canvas scaler.




Once it has been pasted in and placed it should look like this:





However, if we give it a try now we will notice that nothing works. Why ?!?. Well, remember the SettingsProvider we create in step 1 and 2. The example UI uses another one so we have to assign our new provider instead of the old one.


Now, you could do this manually on each UI element but let's be honest, that would be rather tedious. Luckily the "Settings Creator" Window has a handy button for that. Let's open it and check it out:



Pay close attention to the chosen Provider. It may be the wrong one "SettingsProvider (FromAsset) (S...". We need to change that to the one we created in step 1 which was "SettingsProvider (MyGame) .."




Then press the "Back" button at the bottom to get to the Provider view:




Here you will find the "Apply Provider to ..." button. If you press it then it will search the whole scene and set the provider of all the UI elements to "Settings Provider (MyGame)".

After pressing the button you will probably see a lot of log message (that's fine) and maybe some warnings (those need attention):




The warnings are telling us that for some parts the provider could not be set (usually the “Save”, “Apply”, ... buttons). For those we have to set the provider manually which is a nice exercise since you are new to the system anyways.


The logs show us that five buttons need to be fixed manually. Luckily we can just click on the warning to get taken to the problematic buttons. Let's start with the “Save” button.




If you check out the Inspector of that button you will notice that there is a UnityEvent registered which has a reference to a SettingProvider. It's a bit hard to see but if you click it you will notice that it still point to the “from Asset” provider, which is wrong.



To fix it we have to drag in the "SettingsProvider (MyGame)".




Make sure you also choose the correct method ("Save") again (sadly Unity seems to forget this once a new provider is assigned):



Repeat this process for all five buttons and then save your scene.

HINT: Unity Events are multi-editable so you can select all the buttons in the hierarchy and assign the provider (just make sure you don't forget to update the methods).

HINT: Use the "Apply Provider .." button again to check for remaining warning. If none are displayed then everything is fine.




And that's it. No all the settings should work normally (except maybe for the Post Processing stuff which requires you to setup up post processing in your game if you want that).

An alternative to step 3 is using your existing UI:

If you do not want to use the examples UI but your very own then this is how you can hook your UI up with the settings system you created in steps 1 and 2.

Let's say your game UI looks like this:



And you want to replace the Audio On/Off trigger with the settings. You have to make a choice here.


Do you want to:

- (A) Keep using your own UI and simply hook it up with the settings system.
- (B) Copy in the UI from the settings scene.

We'll cover both scenarios below.



A: Hook your UI up with the settings system

For this we have to add a "ToggleUGUIResolver" component.



You may have noticed that the resolver also added a "Toggle UGUI" component.

1. Make sure the "Toggle" property is hooked up with the Toggle (usually it does this automatically).
2. We also have to configure it to use the proper settings provider ("MyGame SettingsProvider (FromAsset)" in this example).
3. And finally we have to choose one of the predefined settings. In this case we use the "audioEnabled" settings as this will toggle the audio.




And that's it. It works the same for any other UI element.

B: Copy in the UI from the settings.


If you want to use the premade UI from the example then first drag in the scene you copied into your game scene. In the end we will not use that scene file but it is convenient to keep it around so we can copy from it.

Once dragged in it may look a bit messy. Like this:


Hint: The canvas may hide behind your game UI. Try increasing the SortOrder to make it visible.




Don't worry about about any changes to the demo UI. We will not save it and remove it from your game once we are done. Now all we need to do is find the "Sound toggle":




Once we have it let's duplicate it (CTRL/CMD + D):



And move it to our game UI:




Now that we have what we wanted we can remove the scene. We do not need it anymore. Don't save it.




We have successfully copied the toggle to your game UI.


It should look something like this (new parts marked yellow):




We can now delete our old toggle and position the new one.



Finally we need to make sure the toggle uses our new settings provider and is hooked up to the correct setting, namely "audioEnabled".




If you want you can remove all the unnecessary helper components too.




And that's it.

Step 4: (Optional) Delete or disable unused settings.


You may have noticed some logs in play mode when using the settings. These are there because the example asset includes ALL settings and some are only working if set up correctly (post-pro for example).



In case you are not using them you can clean up your settings asset to only use those that you are using. For this open the settings asset of your game and remove whatever you don't need.




After deletion please also delete any stored settings, or else the system will try to restore them.



Thanks for reading it all. I wish you all the best for your game!

Connecting a setting to a property, field or method.

By using the “Setting Receiver Generic Connector” component you can make a setting change any property, field or method (if the method takes the right parameter that is).



The “Setting” is where you choose what the setting source and in the “Receiving Property” you choose the target. Whenever the setting value changes it will trigger an update on the target.

Here is a short video that demonstrates how it is used:

<https://www.youtube.com/watch?v=3SE8hGVEgkY>

It works with any public property, field or method if that method takes only one parameter of the appropriate type. It's just one component but very powerful in what you can do with it.

HINT: You can mix float/int.

INFO: Please do not use the GenericConnector as an event system (i.e. don't call it every frame). It uses reflection (caches the types etc. but still) and therefore it will always be a fair bit slower than making a proper custom connection or using the event components.

Combining the Settings System with other Assets

You may have noticed that the settings are only applied at certain points in time (i.e. when the menu is used or whenever you call "Settings.Apply(changedOnly: false);".

If you are using other assets in your game it may happen that these will override your settings.

Most common are audio assets setting the master volume on your AudioListener. This may lead to the situation that you have muted the master audio in the settings menu, yet in your level the audio still plays as loudly as ever.

You may have a setup like this:



First Frame

SettingsSystem

Sets the Volume at level start to 0

Every Frame in the Level

AudioManager(s) - could be multiple if you use multiple Assets
Sets the Volume to something else.



Repeats every frame.

As you can see in the image above the third-party assets are continually setting the master volume, effectively negating any effect of your settings. Since the settings system can not know what code or assets you use it can't prevent that.

The proper way to fix this is to forward the settings value to whatever third-party system you are using.

The control flow should be like this:

SETTINGS SYSTEM → THIRD-PARTY-ASSET → YOUR-LEVEL


If you have both the settings system and some third party asset control a value at the same time then these two systems will fight over who takes priority. At worst the results are random applications of the setting values. Sometimes the settings system will win, sometimes the third-party asset. It's impossible to know.

The not-so-proper (really bad) way is to use the "SettingsApplier". Really, you should fix this properly.

SettingsApplier

If you are not loading your scene additively (meaning you unload your menu scene) then you probably have to re-apply your settings on level load. There is a prefab called "SettingsApplier" to make this step easier.

You can find it under **Kamgam > SettingsGenerator > Runtime > Prefabs**:



Provider: Don't forget to set the correct provider.

ApplyOnStart: By default the applier is configured to apply all settings on Start().


ApplyOnStartDelay: If you know that some other scripts are also being executed in Start() then you may want to delay the execution a little bit. Be aware though: timing based fixed are always bad.

ApplyOnLateUpdate: I strongly suggest you only use this for debugging to find out if another system is also setting the same values as the settings system. Please refer to the "Combining the Settings System with other Assets" section for more details on why using Update() is a bad idea.

Settings Ids: Instead of applying ALL settings you can also apply only a subset. In the example above we only apply the "audioMaterVolume" and nothing else.

Settings

Most Settings are based on simple types. There are some predefined ones but you can also invent your own.



ID:

Each settings has a unique ID which identifies it globally.

Apply Immediately:

Each setting has an “Apply Immediately” switch. If enabled then any changes to the setting will be propagated to the connection immediately (if there is a connection). Usually this should be set to enabled. Though for some settings it is better to disable it (“resolution” dropdown for example). If disabled then the user will have to hit the “apply” button to actually apply the changes.

Groups:

Each settings can be part of one or more groups. Groups can be used to perform actions only on a subset of settings (resetting only the key-bindings for example).

Default Value:

Each setting can have a default value (that’s the value used for reset and at first boot). If the settings has a connection (meaning it gets its values from a dynamic code source) then the default value will be ignored (it is pulled from the connection instead, unless ..).


Ignore Connection Default:

If enabled then the default value is never pulled from the connection. Instead the setting is used.

Connection Object:

Each settings can have one connection. A connection object is just a wrapper for some code that should be executed if the setting value changes or if the setting is applied (see “Apply Immediately” above).

All these things can also be configured via the scripting API. You can find a fully scripted example in the “Examples/FromCode” directory.



Basic Types (Bool, Int, Float, String)

These are generic settings to create custom settings from. You can use a `GetSetConnection<T>` to hook them up to any method in your game.

Colors

Save and load any color value.

ColorOptions

Let the user pick from a list of colors.

Options


If you want the player to choose only from a limited set. You give it a list of names (A, B, C) and it tells you with an index (0,1,2) which option the player selected.

Key Combination (OLD KeyCode based input system)

TLDR: For the OLD key code system use `SettingKeyCombination`. For the NEW InputSystem use a `StringSetting` + an `InputBindingConnection` as documented in the [Input Rebinding](#) section.

Key Combination settings are used for key code storage. They support old and new key codes and key combinations.

NOTICE: A `KeyCombination Settings` does NOT do any input binding. It simply receives and stores the pressed keys as a `UniversalKeyCode` (enum). It does not interact with your `InputActions` at all. It does not send any events or messages.



HINT: There is a static class `"Kamgam.UGUIComponentsForSettings.InputUtils"` that contains some useful methods for dealing with input detection.

How to work with KeyCombinations

There is a static class "Kamgam.UGUIComponentsForSettings.**InputUtils**" that contains some useful methods for dealing with input detection (getting key codes from settings for example).

If you use the old input system then the **SettingKeyCombination** and the **KeyCombination** class will both have two methods **GetKeyCode()** and **GetModifierKeyCode()**.

HINT: There is a class called "**SettingKeyCombinationEvent**" that implements listening for certain key combo events (down, up, hold). You can use it directly or copy it and make your own modifications (if you are using **KeyCombination** settings that is).

Input Binding: StringSetting + InputBindingConnection (NEW InputSystem)

If you are using the new [InputSystem](#) then the recommendation is to use [Input Actions](#) instead of key codes. Therefore if you are using the new **InputSystem** please use a **String Setting** in combination with an **InputBindingConnection** and the **InputBindingUGUI (Setting)** Prefab.

The [Input Rebinding](#) section contains a detailed guide on how to generate the **InputBindingConnections** for your string settings. You can also find a demo of this under **Asset/Kamgam/SettingsGenerator/InputSystemBinding**.


But why not use a **KeyCombination**? Using key combos directly is more a thing of the past and the new [InputSystem](#) does away with them in favour of [Input Actions](#). **Input Actions** provide a nice abstraction and you can also use the automatic [Input Rebinding](#) for them.

HINT: There is a static class "Kamgam.UGUIComponentsForSettings.**InputUtils**" that contains some useful methods for dealing with getting direct access to input key codes (like in the old system). While it is not recommended to use it for the new [InputSystem](#) it can be handy at times.


Setting Resolvers

If you want to hook up a UI with the settings system you need something to make that connection. Any object can be a resolver as long as it implements the **ISettingResolver** interface. It does not have to be a UI.

There are some predefined UI Resolvers (see folder "Runtime/Scripts/Resolvers"). These are implementations for the UGUI components (see above).



A typical resolver looks like this:



The "Settings Provider" is a reference to the settings provider asset (see section "Overview").

The "Localization Provider" is a reference to the localization provider (see section "Localization").

The "ID" is where you will have to enter the ID of the setting you want to connect to.


NOTICE: Not every setting is compatible with every resolver. The "Suggested IDs" will only list compatible IDs. If you enter an incompatible ID then you will receive a "type mismatch" error like this:

SettingsGenerator: SGSettingResolver: Type mismatch for ID 'resolution'. Got 'Kamgam.SettingsGenerator.SettingOption' but can only handle types: Bool.

Some resolvers can take multiple setting types. A slider for example can take float or int settings.

Auto-Save


Auto save is disabled by default. To enable it you have to check the "Auto Save" checkbox on the SettingsProvider. Please make sure you change this on the right one (the one used by your resolvers on the UI).



Auto save will NOT save immediately after a settings has changed. It will wait for "Auto Save Wait Time in Sec" and then save. This is done to avoid saving too often, for example if a slider is dragged. If a setting is changed within the wait time then the wait will restart.

Setting Events

Setting Events are components you can use in your scene to react to settings value changes. The demo scene contains a demo list of all the events.



HINT: Most events can take multiple setting types. For example the SettingBoolEvent can actually take int, float, bool, color and string values. It interprets them in a “boolean” manner.

Each event has an “OnValueChanged” UnityEvent which you can use to react to value changes.

NOTICE: If the event object is active at the game start then it will be triggered once upon setting initialization. It will trigger again if “TriggerOnStart” is enabled, effectively triggering it twice.

The events themselves work similar to a SettingResolvers (they actually are resolvers with some extra features). They require a SettingsProvider and a setting ID to work.

Triggering an event means pulling the setting value from the setting and triggering the OnValueChanged event with it.

Trigger On Start: If enabled then the event will be triggered in Start().

Trigger On Enable: If enabled then the event will be triggered in OnEnable().

Trigger If Disabled: If set to false then this event will not trigger if the gameobject or component is disabled.

On Value Changed: The Unity event that will be triggered whenever the setting is changed.

NOTICE: The event registers itself on the setting in OnEnable(). So if the object starts disabled then it will NEVER be triggered not matter what this was set to.

HINT: You can force registration for initially disabled objects via the Register() and Unregister() methods.

UI Systems Overview (IMGUI vs UGUI vs UI Toolkit)

As you may know there are three UI Systems. Here they are listed from OLD to NEW.

IMGUI:

Immediate GUI (used primarily in the Editor but you can also make game ui with it). It's the oldest system and you really should not use it anymore except in rare occasions.

UGUI:

The current standard. This is the most widely used and supported gui system. If an asset in the store says "ui" on it then in 99% of cases it's means UGUI. I recommend you keep using UGUI until UI Toolkit is ready for prime time (which in my opinion will be in about 1-2 years).

UI Toolkit (aka UIElements):

This is the newcomer system. It works quite differently than ugui since it uses XML (UXML) and a CSS subset (USS) to define your UI. The most notable change is that you no longer have a hierarchy in the scene and thus you can not add any components (MonoBehaviours) to the individual elements.

The settings system has rudimentary support for UI Elements. The code aspects all work (all connections are supported) but there are much fewer ready-made UI components.

Please read the "UI Toolkit" section for more details.

NOTICE: There was a significant change in the UI Toolkit in **Unity 2021.2**. At that point the UI Toolkit switched from being a package (com.unity.ui) to an internal module. This means that you do not have to install the UI Toolkit in Unity 2021.2+, it is already there included.

This also means that the old package, and with it Unity versions older than 2021.2, have dropped out of UI Toolkit support.

The old UI Toolkit package does not work very well and is no longer Supported by Unity. **It is therefore strongly suggested to only use UI Toolkit in Unity 2021.2+.** The settings system may drop UIToolkit support for Unity below 2021.2 in the future (as Unity did).


IMGUI (not supported)

IMGUI is the old legacy UI system. There are no read-made UI components or resolvers for it. However the code parts can be hooked up if you are a programmer. To do soe you will have to implement the resolver interface for your IMGUI elements.

UGUI (fully supported)


UGUI Components

The settings generator contains a set of UGUI prefabs that you can use to create your UI. They are the visual representation of the settings. These components are located in the "Runtime/Prefabs/UGUI" folder.



You can of course use your own UI components. Though you probably would have to write UI Resolvers for them (more on UI Resolvers below).

Each UI prefab has some components attached. The most important one is the "UI Resolver" (details below). The others are mainly convenience components (see "Helpers" section).



PC Style & Console Style

For most UI prefabs there are two variations. One is the default (I called it “PC style”) and the other is more suitable for consoles (“Console style”).


Converting between PC and Console style

You can convert between the two styles without having to re-enter any data or localization text.

To do that use the Right-Click menu and choose: UI > Unified Settings > Convert To > ...

It offers options to convert to and from console styles.

HINT: These conversions have full Undo/Redo support. Just give it a try.



HINT 2: If the object name has a section formatted like “(something)” then this will also be carried over to the converted element.



PC Style uGUI Prefabs

When searching for component prefabs make sure you are not accidentally using the components from the “Libs/UGUIComponentsForSettings” library. These are the base prefabs.


You should use the prefabs from the “Runtime/Prefabs/UGUI” folder. The major difference between the two is that the latter are already prepared for use as settings UI while the former are just UI components with no special purpose.

Color Picker UGUI & Color UGUI

The Color picker allows the user to pick from a list of colors. It is supposed to be customized by you to represent the colors you want. By default it only contains two colors (ColorPickerButtonUGUI).



If you need more colors then duplicate the buttons and specify the color within each button.



The ColorPickerUGUI Resolver does not care how the UI looks as long as it can find some ColorPickerButtonUGUI components within the ColorButtons game object. You do not have to specify the colors in the UI, you can also specify them in the Settings asset or via a dynamic connection.

Dropdown UGUI

Shows a list of options from which the user can pick one.




The Dropdown options can be specified in three places:


- A) Within the “Options” of the TextMeshPro Dropdown.
- B) In the Settings asset
- C) Dynamically through a connection.

If C is present then it will override A and B.

If B is present then it will override A.



There are some variations of prefabs available. For example there is a “DropdownUGUIWithLabel (Setting)” prefab which adds a label on top of the dropdown.



Headline UGUI


Just a label with a line beneath it. No settings related stuff here.

A light blue rectangular box with the word "Controls" in a dark blue, sans-serif font. A thin horizontal line is positioned directly beneath the text.

Input Key UGUI

Key-Binding UI. It has an active and an inactive state. It listens for key, mouse and button inputs.

NOTICE: The InputKey does NOT perform any input binding. Use the InputBindingUGUI instead.



Input Binding UGUI

Key-Binding UI. The look and interaction is identical to the KeyCombination UI.




The difference is in the used setting (a simple String Setting) and the Connection (InputBindingConnection). It performs an interactive rebind using the new InputSystem. However to do this it requires a bit of setup. Please read the ["Input Binding"](#) section before use.

Options Button UGUI

Similar to Options but it simply iterates through the options and shows the current one in the center. It is best suited for mobile devices or very short lists where a dropdown would be to cumbersome.


There are two variations of that Prefab:

OptionsButtonUGUI (Setting)




Despite showing two arrows this is just one button which cycles through the options.

OptionsArrowButtonsUGUI (Setting)



This one has two buttons (previous and next).

The Options Button has two addition settings:



"Loop" will define whether or not the options will lopp if the end is reached.

"Enable Button Controls" will define whether or not the value can be change with the arrow keys or controller left stick. This is enabled on the console variation of the options button.

Slider UGUI

The slider is built based on the default Unity Slider.





You can specify a value format which is based on the c# [Standard Numeric Format](#).

You can also specify a step size (default is 10 for a range from 0 to 100).


Keep in mind that controllers and gamepads usually only move the slider by one step size increment per button press. Don't make the step size too small or else console players will complain.

Some values (min, max, int/float) are configured directly on the Unity Slider.




Stepper UGUI

The stepper is similar to a slider but it makes the steps more explicit. This one is useful for touch interfaces or for options with few values.



You can specify a value format which is based on the c# [Standard Numeric Format](#). You can also specify a step size, min/max value and whether or not it should round to whole numbers.




Textfield UGUI



Allows the player to enter a text.


Toggle UGUI

Use this for anything that needs to be either on or off. It is based on the Unity default Toggle.



CONSOLE Style uGUI Prefabs

You can find these prefabs in the "ConsoleStyle" subfolder of the regular uGUI prefabs.




Their functionality is the same as the PC versions so please refer to the documentation above for details. This section will focus on where they differ (look & additional features) from the PC versions.

HINT: Remember you can use the Right-Click > UI > Unified Settings > Convert To > .. menu to convert between PC and CONSOLE UIs.

NOTICE FOR CODERS: Both the PC and Console versions use the very same C# classes so you can swap out the UI without changing any of your code.

The most notable difference between PC and Console UIs is that console UIs stretch across the full width and they have a subtle selection highlight in the background:



Below you can see the look of these components. If their functionality differs from the PC version then it will be noted here. Otherwise please refer to the documentation above.

Color Picker Console UGUI




Shows the colors in a line left to the selected color field.

Input Binding & Input Key Console UGUI



Options Button Console UGUI



If selected the user can change the value in both directions depending on the key/button that is pressed. Supported arrow buttons and controller left stick.

HINT: It also support mouse input. Depending in where the "button" is clicked the value will increase or decrease.

Slider Console UGUI



Stepper One Button Console UGUI

The difference between a stepper and an options button is that the stepper displays a numeric value while the options button displays an arbitrary list of strings. There are multiple variations of the stepper.



Stepper Two Buttons Console UGUI



Stepper One Button Steps Console UGUI


This variation is a bit special as it does not display the value directly but instead it instantiates the game object that is called *_Template (usually that's "StepperStepConsoleUGUI"):



Textfield Console UGUI



Toggle Console UGUI



UGUI Helpers


Various components are attached to the UGUI components to help out with common tasks.

Auto Navigation Overrides

TLDR: Use this instead of the "explicit" navigation mode.


Usually auto navigation does a fine job, but sometimes it is better to set the selection by hand. The simple approach would be to use "explicit" mode instead. Sadly in explicit mode the selection will just do nothing if the target is disabled.

It would be more desirable to fall back on dynamic selection if the explicit selection does not find a valid target. This is what the overrides are for. Think of them as explicit values which fall back on auto select if the specified target can not be selected.




Selection Event Listener

The selection event listener allows to register callbacks for selection events. It's just a forwarder of `ISelectHandler`, `IDeselectHandler` method calls.



Scroll Into View On Select UGUI

If a UI component is selected within a scroll view then it is desirable for that elements to scroll into view (become visible). This is especially handy if a controller or gamepad is used as these can select off-screen elements too.




SelectionUGUI


You will find a SelectionUGUI object within all UGUI component prefabs. These are the selection highlights for controller & gamepad input.

They look like this:

not selected selected (notice the border)



You can customize them for all elements by editing the "SelectionUGUI" prefab.



UI Toolkit (full logic, fewer components, Unity 2021.2+)

UI Toolkit is the newcomer system and (possible) future of UI making in Unity.

Terms linked to it are "UI Elements", "Visual Elements", "Visual Tree", "Unity Style Sheets", "UXML", "USS", "com.unity.ui" (old), "UnityEngine.UIElementsModule" (new).

It works quite differently than ugui since it uses an XML file (.uxml) and a CSS subset (.uss) to define your UI. The most notable changes are:

A) you no longer have a hierarchy in the scene and

B) you can not add any components (MonoBehaviours) to UI elements.

The settings system has rudimentary support for UI Elements. The code aspects all work (all connections are supported) but there are much fewer ready-made UI components.


NOTICE: There was a significant change in the UI Toolkit in **Unity 2021.2**. At that point the UI Toolkit switched from being a package (com.unity.ui) to an internal module. This means that you do not have to install the UI Toolkit in Unity 2021.2+, it is already always there. The min version of the package that does support UIToolkit is **com.unity.ui 1.0.0-preview.18 (used in Unity 2020.3.30f1+)**

This also means that the old package, and with it Unity versions older than 2021.2, have dropped out of UI Toolkit support.

The old UI Toolkit package does not work very well. **It is therefore strongly suggested to only use UI Toolkit in Unity 2021.2+.** Actually, based on my experience I would suggest using it only in Unity 2023 LTS (yes, 2023).


The settings system ~~may~~ will drop UIToolkit support for Unity versions below 2021.2 versions in the future (as Unity did).

Here is how a typical UI Toolkit interface looks like in the hierarchy (not much to see).



UI Toolkit Resolvers

One of the key differences between UGUI and UI Toolkit is that in UI Toolkit there is no scene hierarchy (instead there is the “Visual tree” based on .uxml files). You may have noticed that we can not add any MonoBehaviour Components to the elements in the UI Builder.




Therefore (sadly) we have to generate our own means of adding custom code.

The settings generator works around this limitation by adding components to the scene which are linked to visual elements via **class names***.

*This may be changed in the future to use Bindings but at the time of writing the implementation was still a [work-in-progress](#). Same goes for [localizations](#).

Linking a Visual Element to a Setting (guide)

First let's look at what we usually have at the start. Here is a DropdownField in the UI Builder:



Notice the marked area on the right. There we can add custom class names to the element. You can find information on what a “class name” is in the [Unity Manual](#) (basically it's just a string).

Now to establish a link to a visual element we first need a way to find it inside the UIToolkit Hierarchy (aka Visual Tree). Note: this is NOT the scene hierarchy!

Since [binding for runtime](#) is still a [work-in-progress](#) we need some other way of identifying the elements. To do this we will use the “class names”. We will add a unique class name to every element that should be used by the settings system.

Step 1: Add a unique “set_” class name

Let’s add the class name. **Make sure that it starts with “set_”**. This is the signal to the settings system that the class name is meant for a setting (example: “set_whatEver”). Also **make sure the class name is unique** or else the settings system will have trouble differentiating it from other classes. Hint: Using the setting id after the “_” is a nice way of keeping it unique.

Step 1: Select the element and type in the class name (set_[your-setting-id])




Step 2: Press the “Add Style Class” button to add the class.




Step 2: Check if the class was added. Sadly if you have a typo in it you will have to delete and reenter (hopefully Unity will improve that workflow some day).

Don’t forget to hit “Save” in the UI Builder afterwards:




Step 2: Generate the resolver components


Okay now that we have added some class names we can generate those components we need (the setting resolvers). To do that **Right-Click** on the UIDocument in your scene and choose **Settings Generator > Create Resolvers**.



This will generate a child object inside the UIDocument.




Select the "SettingResolvers" object and check in the inspector that it has a SettingsProvider assigned. By default it will use the first one it finds but maybe you want a different one.



Once you have the right provider assigned hit the "Create or Update Resolvers" button.

Now if you unfold the "SettingResolvers" you should find a resolver matching the drop down:



The class name you have set should be listed in the “Binding Class” field. This tells the resolver which visual element (DropDownField) it belongs to.

You may have also noticed that the ID has been prefilled too. That was also done based on your class name. The class name without the “set_” part is the ID (set_**difficulty**).

However, you can change both the BindingClass and ID here at any time.

Don’t forget to save the scene after generating the resolvers!


Now you can keep adding “set_” class names to your ui elements and press that “Create or Update Resolvers” button. NOTICE: it will always regenerate all the setting resolvers from scratch.

If you choose your class names well you will never have to touch the resolver components.


Linking a Visual Element to a Localization

It’s the same workflow as with the settings. The only difference is that instead of the “set_” prefix you have to use “loc_” in your class names.


Step 1:



Step 2:



Result:




UI Toolkit Components

At the moment there are no custom made components for UI Toolkit. However there is a range of resolvers and helpers supporting Unity's existing UIElement components. You can find them used in the demo under:


Assets/Kamgam/SettingsGenerator/Examples/UIToolkit/SettingsUIToolkitDemo.

To inspect them open the SettingsMenu.uxml in the UIBuilder window.




DropDownField

Use the default Unity DropDownField from the Library in the UI Builder. It can be connected to an option setting via a **"DropDownFieldUIElementResolver"**.




Toggle

Use the default Unity Toggle from the Library in the UI Builder. It can be connected to an boolean setting via a **"ToggleUIElementResolver"**.




Slider

Use the default Unity Toggle from the Library in the UI Builder. It can be connected to an boolean setting via a **"SliderUIElementResolver"**.



TextField


Use the default Unity Toggle from the Library in the UI Builder. It can be connected to an boolean setting via a **"TextFieldUIElementResolver"**.



Helper: UIElementClickEvent

This is more of a general helper than a setting related component. You can add it as a CHILD to the UIDocument and specify some query criteria to target one (or more) elements. It then allows you to add UnityEvents for clicking. You can find the prefab under:

Assets/Kamgam/SettingsGenerator/Libs/UIToolkitComponentsForSettings/Runtime/Prefabs/UIElementClickEvent




Helper: UIElementEvents

Same as UIElementClickEvent just with many more events (pointer, key, drag, focus, blur, change).


Connections

There is an extensive list of predefined connections. All of them support HDRP, URP and Built-in renderers.

ScriptableObjects: As explained in the "Overview" section connections can be hooked up with settings to drive the value from code. You can find them under Resources/Connections.



CODE: Most of the connections are split into three partial classes (Built-In, HDRP, URP). You can find the implementations within the Runtime/Scripts/Connections folder.



Ambient Light

Controls the ambient light intensity.


Ambient Occlusion (SSAO)

On/Off for Screen Space Ambient Occlusion. There are some caveats with this one.

Caveats (mostly URP)

In URP Ambient Occlusion is only supported in URP 10+ (Unity 2020.2).

In URP SSAO has to be added as a `RendererFeature` to the `ForwardRenderer`. It is NOT part of the normal post processing stack.



In URP the performance cost of SSAO is always paid since it is always enabled. To really disable it you will have to set the static property **AmbientOcclusionConnection.UseActiveStateToDisable** to true.

NOTICE: If you enable it then the functionality of SSAO depends on the availability of the disabled shader variants. These may be stripped from builds. You will have to disable shader stripping under `ProjectSettings > Graphics > URP Global Settings > Shader Stripping` (both "post pro" and "unused").


See: <https://forum.unity.com/threads/turn-urp-ssao-on-and-off-at-runtime.1066961/#post-8613702>

In HDRP disabling the shadows will also disable SSAO within the shadows. If anyone finds a workaround for this then please let us know.

Anti Aliasing

Selectable options are based on your renderer settings. For MSAA check out the section below.

This connection two extra options. "Limit To Main Camera" (which has no effect in the BiRP but URP and HDRP)




"Include MSAA" adds MSAA options to the anti aliasing list (disabling the other options if chosen). MSAA is only supported in URP and HDRP and forward rendering.

HINT: You can also use the dedicated MSAA option if you want to combine MSAA and other AA solutions.


Audio Mixer

Allows to control exposed parameters of [AudioMixers](#).


It requires you to expose the parameters for modification and you will need one Connection per parameter.




If you double-click the parameter in the dropdown you can rename it.



The connection will need the name of the parameter so it can find it.





Be careful with the values you plugin into it. Don't start off with 20dB Volume! Your audio equipement may not like that too much.

Audio Paused

On/Off for Audio: Pauses the Audio Listener (useful for global audio on/off).

Audio Volume

Controls the global Audio Listener volume (it changes the "AudioListener.volume" value). Useful for a master volume setting. For volume controls of individual audio sources please use the "AudioSourceVolume".

Audio Source Volume


Controls the volume of one or more specific AudioSource Components. It does NOT use a connection object in the setting.

How to make sound groups for "effects", "music", "voice", ...?

TLDR:


- 1) Create a float setting for reach group (do NOT add a Connection, leave it empty).
- 2) Add AudioSourceVolumeConnectionComponents to AudioSources and specify the id.

To control volumes by "group" please add one float setting for each (like musicVolume, effectVolume, ...). Do NOT add a VolumeConnection.



Since AudioSources live on GameObjects in the scene they require you to add an AudioSourceVolumeConnectionComponent.

Like this:



In the example above the `AudioSourceVolumeConnectionComponent` controls only one `AudioSource` but you can add more. You can also have multiple components referencing the same ID.

NOTICE: The audio effect volume in the demo is not controlled by a `VolumeConnection` setting but a normal **float** setting.

The `AudioSourceVolumeConnectionComponent` will create a `VolumeConnection` on-demand in `Start()` and use that. But this part is automatic and hidden from the user so you may not even notice it.

The important part is that **you can use as many `AudioSourceVolumeConnectionComponents` with as many different (or equal) setting ids as you want**. There is no dedicated place to define groups like music/fx/voices (except for the float settings section).

Bloom

On/Off for the bloom post processing effect.

Color Grading (lift, gain, midtones, mixer, temperature, tint, ...)

The color grading connections support: lift, gamma, gain, shadows, midtones, highlights, mixer (red, gree, blue), brightness (BiRP only), hue, saturation, temperature and tint.

They also support more options than listed here but only for some RPs since not all are supported on all render pipelines. Please check the `ColorGradeConnection.ColorGradeEffect` enum for more infos on that.

Depth Of Field

On/Off for the depth of field post processing effects.

Camera Clipping / Render Distance / Draw Distance

Controls the near or far clipping plane of the camera (either main camera or one that is marked with a `CameraClipMarker` component).

Fog

Enable or disable fog.


Field Of View

The field of view allows you to change the field of view on any camera.



NOTICE: It does automatically detect newly added cameras so you do not have to do anything if your camera is switching. If a new camera is detected the “set field of view” logic is executed and all cameras that qualify will have their fov set.

The FieldOfViewConnection has two parameters:



“UseMain” means it will try to change the field of view on the camera that is tagged with “MAIN_CAMERA”.

“UseMarkers” means it will try to change the field of view on all cameras that have the “FieldOfViewMarker” component added to it. This way you can explicitly specify what cameras to affect.

By default both options are enabled.

HINT: If you want to disable the fov auto-apply mechanism then simply set both “UseMain” and “UserMarkers” to false.


Frame Rate

Options to control the target frame rate. Default options are: 30, 60 and 120.

Full Screen

On/Off of for full screen mode.

NOTICE: The “FullScreen” connection and the “Window Mode” connection should NOT be used at the same time as they can contradict each other, like this:



Is fullscreen now ON or OFF?

What will happen in this case is that first the FullScreen will be disabled by the FullScreenConnection (checkbox) but afterwards it will be enabled by the WindowModeConnection (drop down). This will result in an ugly window bar being visible for one or two frames. That's why you should only use one OR the other. In the examples both are added only for demonstration purposes.

GetSetConnection<T>

A generic connection which you can use to forward a value directly to a callback function.

Gamma

Range for the gamma correction post processing effect (-1 to +1).

InputBindingConnection

This connection stores the bound key for an action as a string.
For more details please refer to the **Input Rebinding** section.

Microphone

Allows you to pick from a list of microphones. It uses the [Unity API](#) to fetch a list of available devices. The connection also mirrors the API so you can record directly from the selected device.

NOTICE: This API is not supported in WebGL (see: <https://discussions.unity.com/t/webgl-and-microphone/570642/71>)

Here is an example:

```
using Kamgam.SettingsGenerator;
using UnityEngine;

public class RecordAudio : MonoBehaviour
{
    public SettingsProvider Provider;
    public AudioSource Source;

    public void StartRecording()
    {
        var connection = Provider.Settings.GetOption("microphone")
            .GetConnection() as MicrophoneConnection;
        Source.clip = connection.StartRecording(false, 3, 44100);
    }

    public void StopRecordingAndPlay()
    {
        var connection = Provider.Settings.GetOption("microphone")
            .GetConnection() as MicrophoneConnection;
        connection.EndRecording();
        Source.Stop();
        Source.Play(0);
    }
}
```

Motion Blur

On/Off for the motion blur post processing effect. NOTICE: URP does not have a per-object motion blur. This means for example that an object rotating in place will not be blurred. More on that in the [Unity manual](#).

Monitor

Allows you to switch the display monitor of the main window. ⚠ NOTICE: This requires Unity 2021.2 or higher since that's when Unity added the monitor switching API.

MSAA

MSAA is a separate anti aliasing algorithm. It's not part of the default demos but you can easily add it just like any other option (drop down) setting. Please be aware that in HDRP this required quite some digging into Unitys code (aka reflections) to make this work. Depending on your shader stripping settings this may not work in HDRP (no reports of trouble yet but I like to mention it just in case).

MSAA only does anything when using the forward rendering path. If you use deferred, this setting is ignored as using MSAA with deferred rendering is difficult or in some cases impossible.

Quality

Changes the global quality setting. Options are taken from the graphics quality settings automatically.

HINT: The options are taken straight from ProjectSettings > Quality for the options. Which means in Unity 6+ you will probably only get one "Pc" option by default.

Refresh Rate

Options for monitor refresh rates. Options are taken from the refresh rates supported by the monitor.

NOTICE: Whether or not the actual refresh rate is changed depends on the OS and the hardware. Usually refresh rates can only be changed on exclusive window mode on Windows. The refresh rate has no effect in the Editor.

If you want to control the fps of your application use the "[Application.targetFrameRate](#)" API in combination with and int setting or the "FrameRateConnection".

The refresh rate connection as some options:

CacheRefreshRates (default: true)

If enabled then the refresh rates are queried only once from the system and are then reused.

LimitToCurrentResolution (default: false)

If enabled then only those refresh rates which are usable with the current resolution are listed. That list may be much shorter than the full list (often just one).

MinRate (default: 0)

Refresh rate in Hz. Refresh rates below this are ignored. Equal rates are still included.

MaxRate (default: 1000)

Refresh rate in Hz. Refresh rates above this are ignored. Equal rates are still included.

Resolution

Options for the game resolution. Options are taken from the resolutions supported by the monitor.

NOTICE: The resolution has no effect in the Editor.

The resolution connection as some options:

CacheResolutions (default: true)

Disable if the resolutions change very often.

LimitToCurrentRefreshRate (default: false)

If enabled then only those resolution options which match the current resolution refresh rate are listed. That list may be much shorter than the full list.

LimitToUniqueResolutions (default: true)

If enabled then only one resolution per frequency will be listed.

For example there may be two resolutions: 640x480 @60Hz and 640x480 @75Hz

If enabled then only one of these will be in the list. It will choose the one which has the closest frequency to the currently used frequency.

SkipRefreshRatesWith59Hz (default: true)

If enabled then then resolutions with a refresh rate of 59 Hz will be skipped if (and only if) there is an alternative with 60 Hz.

AddRefreshRateToLabels (default: false)


Should the refresh rate (frequency) be added to the labels.

Example without: 1024x768

Example with: 1024x768 (60Hz)

Custom Resolutions (default: empty)

If not empty then this will be used as the base list of resolutions instead of whatever Unity detects. NOTICE: Since Unity 2022.2 the refresh reate is defined by a numerator and a denominator (60000 and 1001 for 60 Hz for example).

**Allowed Aspect Ratios** (default: empty)

A list of allowed aspect ratios. Since it's a float precise matches are not a good tool. Therefore the allowed delta of the aspect ratios can be controlled by "Allowed Aspect Ratio Delta".

Add Custom Resolution Option If Windowed (default: false)

If enabled then a custom resolution option will be added as the very first option. Very handy for games in windowed mode.

RenderScale

Only supported in URP. It allows you to set the render scale on the current quality render asset.

NOTICE that the render scale is a property of an ASSET in the editor. Therefore all changes to it will automatically persist while being used in the Editor but NOT in a build!

ReapplyOnQualityChange (default: false)

Should the render scale be set again if the quality level has been changed? Usually no since most times higher quality level also means higher render scale.

DefaultRenderScale (default: 1.0f)

The default render scale that should be used ONLY if no render asset has been found. Usually the initial render scale value is taken from your render asset.

Shadow

On/Off for shadows (and contact shadows if you use HDRP).

Shadow Distance

Options for max shadow distance. The options are based on your graphics quality settings. HINT: The options are taken straight from ProjectSettings > Quality which means in Unity 6+ you will probably only get one "Pc" option by default.

Shadow Resolution

Options for max shadow map resolutions. The options are based on your graphics quality settings. Notice: the shadow resolution is spread out over the shadow distance. Thus the highest shadow resolution with the lowest shadow distance gives the best quality (that's a little counter intuitive).

Texture Resolution


Options for texture resolutions. The default options are: full-res, 1/2 res, 1/4 res, 1/8 res.

Vignette

On/Off for the vignette post processing effect.

Volumetrics Enabled (HDRP)

On/Off for the Volumetrics > Enable toggle on all lights.




V-Sync

On/Off for vertical sync.

Window Mode

Use this if you need more control than just "full screen on/off". Otherwise use the "Full Screen" setting. You rarely need this.

NOTICE: The "FullScreen" connection and the "Window Mode" connection should NOT be used at the same time as they can contradict each other, like this:




Is fullscreen now ON or OFF?

What will happen in this case is that first the FullScreen will be disabled by the FullScreenConnection (checkbox) but afterwards it will be enabled by the WindowModeConnection (drop down). This will result in an ugly window bar being visible for one or two frames. That's why you should only use one OR the other. In the examples both are added only for demonstration purposes.

Input Binding (Using the new Input System)

Rebinding Overview

In Unity 2019+ the new [InputSystem](https://docs.unity3d.com/Packages/com.unity.inputsystem@1.5/manual/Concepts.html) was introduced. Among other things it also features the possibility of binding inputs to actions.



Source: <https://docs.unity3d.com/Packages/com.unity.inputsystem@1.5/manual/Concepts.html>


There are four different ways how you can interact with the input system. Please check out the docs for an in-depth description:

<https://docs.unity3d.com/Packages/com.unity.inputsystem@1.5/manual/Workflows.html>

Rebinding Tutorial

Prerequisites

To support Input rebinding the **settings system requires an InputActions asset**. Usually this is created automatically by Unity if you use the new input system. It looks like this:




NOTICE: Methods that do not use an input action asset like Embedded Actions and Direct Input access are not supported because there simply is no way for the Settings System to know where in your code the actions are and how to access them. - However if you are a programmer then you can forward the binding path via the `AddChangeListener()` API of the connection.

The input actions asset is needed because the settings system needs to know what input actions (bindings) do exist so it can connect the Settings and UI with it.


Adding Input Bindings

If you have just created a new settings window the you will notice that in the controls section there are not settings yet. It looks like this:




In this section we will follow the instructions from the red text in detail. However, if you prefer a video then here is a recording of the process -> <https://www.youtube.com/watch?v=5RIA8PxKYUE>


1) Open the creator window




2) Navigate to the Configuration Tab and open the Provider Details.




3) Drop your Input Actions asset into the Input Action Asset slot (you will have to scroll down).



4) Click the "Create Input Binding Settings" button.




If asked confirm to create the settings for the bindings:




Okay, now you have created the input binding settings (you should see some logs in the console) and if you unfold the Settings section you will find them in the String settings section.

5) The last step is to add the settings to your UI. In the default settings window a good location is the layout in the Controls tag scroll view.



In the settings list you can filter by "InputBinding" as all the input binding settings are prefixed by that by default. HINT: You may want to delete the red text before adding bindings.



And that's it. Enjoy your input bindings :-)

Input Binding Details & Troubleshooting (optional reading)

Here is shown how you would do it all manually, step by step. Since version 1.74 of the asset this is no longer necessary (see tutorial above) but it illustrates nicely how it all fits together.

We know the input actions asset is needed because the settings system needs to know what input actions (bindings) do exist so it can connect the Settings and UI with it.

To connect a binding with a setting we have to generate an **InputBindingConnection** object for each binding in the InputAction asset. The following section will show how that is done in detail.

Overview:


HINT: You can find a complete example under:

Assets/Kamgam/SettingsGenerator/Examples/InputSystemBinding.






1) Generating the InputBinding Connections

Let's assume you have an [InputActions Asset](#) like this:



To generate the InputBinding Connections from it you can right-click on the asset and then choose **SettingsGenerator > Create InputBindingConnections**.

This will generate one InputBindingConnection for each Binding you have in the Input Actions Asset. If you add or remove Input Actions later then you should repeat the process and your Connections will be updated. **Don't delete your connections or you will have to reconnect them with the settings (see step 2).**



Info: Each Connection is linked to a Binding via two things.

A) the Actions Asset and B) the Binding GUID (see image

on the right). Usually you can just leave the connections


objects alone after creation. However if needed you can edit

the linked GUID manually or via the "Available Bindings"

buttons. The bold "ID →" line tells you which Binding the current "Binding Id" belongs to.

2) Link InputBinding Connections to Settings

You have linked the Input Actions Asset with connections but you still need to link these connections with your settings. For each Input you would like to control you will have to create a StringSetting and drag in the corresponding connection.




It's a bit cumbersome but you will only have to do this once (as long as you don't delete your connection objects).

Now the rest works just like it does for all the other settings. You drag in the UI and use the Resolvers ID field to link the UI to the Setting. Like this:


3) Configuring the Rebinding UI

You may have noticed that the Input Binding UGUI script has a special section "Input Binding".




If you open it you will see some configuration options. These are used to LIMIT the inputs this UI will react to. This is useful for example to limit a MOVE action for a controller to only take Thumb Sticks and ignore buttons ("`<Gamepad>/<Stick>`").

This magic "`<Gamepad>...`" string is called an "Input Control Path" and is documented in the [Unity Manual](#).



Another example of restricting a UI to only allow Keyboard input:



The [InputControlPaths](#) are used in the [Interactive Rebinding](#) process.

Ignore Control Paths:

These paths are ignored (see [WithControlsExcluding](#)). By default there already are some paths in this list (global list):

- "`<Pointer>/position`" // Don't bind to mouse position
- "`<Pointer>/delta`" // Don't bind to mouse movement deltas
- "`<Pointer>/{{PrimaryAction}}`" // Don't bind to controls such as leftButton and taps.
- "`<Mouse>/clickCount`" // Don't bind to mouse click count events

You can choose to either override or extend them via the **"Local Config Behaviour"** dropdown.

Abort Control Paths:

These paths behave like the [WithControlsCancelingThrough](#) option. By default there already are some paths in this list (global list):

- "<Keyboard>/escape",
- "<Gamepad>/start"

You can choose to either override or extend them via the **"Local Config Behaviour"** dropdown.

NOTICE:

There is a quite [nasty error in the 1.3. version of the InputSystem](#). If you can, then please upgrade to version 1.4.1. or higher. The Settings System contains a workaround for this error but it may not cover 100% of all cases.

Control Having To Match Path:

Here you can limit which controls the UI will react to. It works like the [WithControlsHavingToMatch](#) option.


Binding Path:

At runtime this shows the currently bound path. It also is used as a fallback path to display if something fails.

How to resolve binding conflicts

It may happen that a player tried to bind an input to a key or button that is already bound to another action. Usually the system does nothing to prevent that and it will simply trigger both actions if that button is pressed.

However, this may not be the desired behaviour. In version 1.40+ there is an option called "BlockOnBindingConflict" on the BindingResolver. If enabled then duplicate bindings will simply be blocked (reverted immediately). Sadly, if you have already created your UI, you will have to enable it on each entry manually because it was kept disabled by default to remain backwards compatible.



HINT: You can also register a static resolver function via "InputBindingUGUIResolver.ResolveBindingConflictFunc" which can be used to display a warning dialog (or do something else). If you don't set it, it will simply revert the binding if a conflict is detected (default behaviour).

NOTICE: If you use it then you have to return true or false in that function to signal whether the binding should be allowed (true) or denied (false).

Input Binding Caveats


The InputSystem is still somewhat new to many developers and there are some noteworthy oddities when using it.

Multiple Player Input Components

Multiple PlayerInput components should only be used if you want to support local multiplayer and there should only be one single PlayerInput component per player. Unity will (secretly) make copies of your input actions asset for each of them at runtime ([source](#)). This may be surprising and can lead to binding issues if multiple components are used for one and the same player. My advice: stick to just one or don't use PlayerInput at all.


Since version 1.74 the settings system will change the bindings on ALL instance of the input asset you have specified in the Provider section in the Settings Creator window.

If you want the old behaviour back that only updated the first copy of the input actions then you can enable this in the provider by enabling "Dont Apply Binding Overrides To All Instances":



Most often what users intend by using multiple PlayerInput components is just to get easy access to the input bindings in a different location. Sadly this is NOT a workflow that Unity supports (imho they should advertise this much clearer in the component). Each Player Input component is considered to be a separate player.

Here is an example showing the effect at runtime:



Notice the “(Clone)” in the PlayerInput at runtime.

Sadly this can not be avoided. Don’t get fooled by the “MyPlayerScript” Unity offers in their documentation. It does not work for this use-case.

NOTICE: You may think that using different Default Maps would work but it does not. The PlayerInput will always check if there are other PlayerInputs and will make a copy if there are.

SOLUTION: Keep “Dont Apply Binding Overrides To All Instances” turn off. This will ensure the system updates the bindings on ALL instances.

However, if you really have local multiplayer then you will have to enable that option and let the settings system know which action asset instance you want to change the bindings on via the


```
Provider.Settings.SetInputActionAsset(actionAssetForPlayerOne);
```

method (call this before showing the controls UI so the binding changes will be triggered only on that asset).

Working with Auto-generated script code for Actions

If you are using an input actions asset then you can choose to generate a [c# actions class](#).

Now, the issue here is that if you use the c# class it will create a new INSTANCE of the actions at runtime.



Will point to the wrong input actions asset if the c# class is being used.

NOTICE: Since version 1.73 of the settings asset it will take care of this automatically by applying the bindings to all instances of the input action asset. In older version you had to manually notify the settings system via the


```
Provider.Settings.SetInputActionAsset (actionAssetForPlayer);
```

method.


What about Composite Bindings?

The settings system uses the `InputActionsAsset.ApplyBindingOverrideWithResult()` API to set the new binding. Sadly this API does not (yet?) support composite bindings. Here is my guess why:

A composite binding means a value (`Vector2`) is derived from multiple other bindings (WASD keys or a thumbsticks for example):



Now, if we try to rebind a whole composition at once the system is actually missing some information. For example: If we try to rebind the "left stick" composition from above to a keyboard then should the "W" key always "be up" or could it be something else? – Initially this is defined by YOU in the actions asset for each composition but in a dynamic environment the system would have to make that decision for you.



What if you now decided to bind something new (a VR controller for example) to the composite binding? Then the system does not know what "up", "down", "left" ... etc. should be.

When implementing this I assumed the `InputActionsAsset.ApplyBindingOverrideWithResult()` API would just assign some reasonable defaults (like the directions of a thumbstick), but instead it just throws an error like this:

```
InvalidOperationException while resolving binding  
'Move:<Gamepad>/rightStick' in action map ..
```

That sucks.

Since I have not yet found a reliable way to do binding overrides for a whole composition at once I decided that (for now) composite bindings are NOT supported.

However, the contents of you initial composite are supported (connection objects are generated for all of them).


What does this mean?

It means that you will have to make one settings UI entry for each of your composite sub-bindings* instead of using just one composite entry for "movement". In the example above that would be one for UP, DOWN, LEFT and RIGHT movement.

It's a bit inconvenient, I know, but sadly, that's the best I could do for now.

If anyone stumbles across a solution for overriding composite bindings then please let me know.


* Starting with version 1.34.0 the System supports a limited set of composite bindings, namely "OneModifierComposites" for keyboards (i.E. multi key combos).




To make a binding support multiple keys you have to add a "OneModifier" composite to it and add as many key bindings as you want to support. If a player then uses only one key for that binding all the other keys in it will simply be set to <Keyboard>/anyKey which effectively makes it behave like a single key binding.

You can find an example of this in the InputBinding demo scene. The "SpecialMove" is a composite binding.

NOTICE: Don't forget to assign the COMPOSITION connection to your setting not one of the children:



HINT: Each part of the composite binding uses the default localization process so you can localize each key separately. The separator "&" is localized via the "CompositeControlSeparator" term.




HINT: The wait time for key combos is controlled by the static

"InputBindingForInputSystem.WaitForKeyComboDuration" API. The default value is 0.3 seconds.

HINT-HINT: You can use the pre initialization events of the SettingsInitializer to change it.

How to display the key binding in my UI?

By adding the **SettingsBindingDisplay** component to a Textfield (both TMPro or Unity default are supported) you can fill that Textfield automatically with the bound key combination.



HINT: It will also try to localize it first which you can use to inject images via sprites (see FAQ "Localizing Key Control Paths").

HINT: **SettingsBindingDisplay** also has a static API `GetSettingBindingDisplayName(..)` which you can use to convert settings ids to human readable text (handy for tutorial messages).

Take care if you have keyboard and controller bindings for the same action. In that case you will have to choose manually which id to localize depending on what control scheme the user is currently using.

Scripting API (Adding custom Settings)

There are three ways to connect a setting to your custom code:

- Fetch the value of a setting manually.
- Using the `GetSetConnection<T>`
- Making a custom `Connection` class

More on those in the sections below.

Getting a setting value can be done by pull (you ask for the value) or push (the value is pushed to a method).

Pulling a value from a setting:


```
var settings = SettingsInitializer.Settings;  
SettingFloat volume = settings.GetFloat(id: "volume");  
Debug.Log( volume.GetFloatValue() );
```

Registering a callback to receive value changes:

```
Settings settings = SettingsInitializer.Settings;  
settings.GetFloat("volume").OnSettingChanged += (ISetting setting) => {  
    Debug.Log( setting.GetFloatValue() );  
};
```

How to get access to the API if you are using Assembly Definitions

You may have noticed that the `Kamgam.SettingsGenerator` namespace is not immediately available in your script if you are using assembly definitions. That's because the settings system uses Unity's [Assembly Definitions](#) system to reduce compile times. This means the code is wrapped in a separate assembly. To use it you will have to add an `asmdef` file to your code and reference the `SettingsGenerator` runtime assembly like this:



How pull the value from a setting


Your entry point to accessing the settings system is always a `SettingsProvider` Asset. The easiest way to get one is to make it a public property of a `MonoBehaviour`, like this:

```
using System.Collections;
using System.Collections.Generic;
using UnityEngine;
using Kamgam.SettingsGenerator;

public class GetSettingValueTest : MonoBehaviour
{
    public SettingsProvider Provider;
}
```

Notice the use of the "Kamgam.SettingsGenerator" namespace.

Once you have that you need to drag in the `SettingProvider` asset in the inspector (make sure you use the right one if you have multiple providers).



Now you can fetch any setting object via the `GetOrCreate...()` methods.

To get the actual value use the `GetValue()` method (or the `OnSettingChanged` event, more on that below).

Like this:

```
public class GetSettingValueTest : MonoBehaviour
{
    public SettingsProvider Provider;

    protected SettingFloat _musicVolumeSetting;

    public void Start()
    {
        // I'd recommend caching settings that are used often.
        _musicVolumeSetting = Provider.Settings.GetOrCreateFloat("audioMusicVolume");
    }

    public void Update()
    {
        float volume = _musicVolumeSetting.GetValue();
        Debug.Log($"Music Volume: {volume}");

        // HINT: You can also fetch values directly from the settings object:
        // Provider.Settings.GetValue<float>("audioMusicVolume");
    }
}
```

And that's it. If you want you can explore the API of the settings object. It has many features.

How to get notified of a value change in a setting.


Your entry point to accessing the settings system is always a SettingsProvider Asset. The easiest way to get one is to make it a public property of a MonoBehaviour, like this:

```
using System.Collections;
using System.Collections.Generic;
using UnityEngine;
using Kamgam.SettingsGenerator;

public class GetSettingValueTest : MonoBehaviour
{
    public SettingsProvider Provider;
}
```

Notice the use of the "Kamgam.SettingsGenerator" namespace.

Once you have that you need to drag in the SettingProvider asset in the inspector (make sure you use the right one if you have multiple providers).



Now you can fetch any setting object via the **GetOrCreate...()** methods.

To get notified of a change you can use the **OnSettingChanged** event.

Like this:

```
public class GetSettingValueTest : MonoBehaviour
{
    public SettingsProvider Provider;

    public void Start()
    {
        var musicVolumeSetting = Provider.Settings.GetOrCreateFloat("audioMusicVolume");
        musicVolumeSetting.OnValueChanged += onChanged;
    }

    private void onChanged(float value)
    {
        Debug.Log($"Value: {value}");

        // HINT: There is also a OnSettingFloatChanged event that you can use to access
        // the setting object if needed.
    }
}
```

And that's it. If you want you can explore the API of the settings object. It has many handy features.

Using the GetSetConnection<T>

There is a premade Connection called GetSetConnection<T>. You can use it to register two methods. One to get the value from the setting and one to send the value to the setting.

The code would look like this (from the code example in the asset):

```
/// A simple int for a slider from 0 to 100 (the range is defined in the UI).
/// It defines a percentage of how strong the health regeneration should be.
protected int _healthRegeneration;

protected void addHealthRegenerationPercentage(Settings settings)
{
    // This setting will react to changes in the setting and propagate those
    // to the local field "_healthRegeneration".
    //
    // To connect a setting (data) with some logic we use Connection objects.
    // These are very simple. They have a Get() and a Set(value) method.
    //
    // Get() means getting a value from the connection and saving it in the setting (pull).
    // Set(value) means sending a new value to the connection (push).
    // There are many specialized predefined Connections (like the "FrameRateConnection").
    //
    // For this example we use a simple generic GetSetConnection<T> connection.
    // This connection does nothing except forward Get() and Set(value) calls to
    // some other methods (getter and setter).

    var connection = new GetSetConnection < int > (
        getter: getHealthRegeneration, // executed if connection.Get() is called.
        setter: setHealthRegeneration // executed if connection.Set(value) is called.
    );

    // Now that we have our connection we need to hook it up with our setting.
    // In fact at first boot we also have to create our setting. Luckily there
    // is a handy GetOrCreateInt() method so we don't have to worry about that.
    var healthSetting = settings.GetOrCreateInt(

        // Each setting needs an ID.
        id: "healthRegeneration",

        // The default value is the fallback default value used if no connection is
        // set. In this case we are using a connection and the default value is pulled
        // initially from that connection. Therefore we actually don't need to specify it.
        // defaultValue: false

        // We want to use a connection to get/set the values.
        connection: connection
    );

    // If all you need is to listen for changes in a setting then you may not even need a
    // Connection object. There is a healthSetting.AddChangeListener() method which you
    // can use for that.
}
```

```

// This simply returns the current state of "_healthRegeneration".
// This getter is called at the very first use of the setting
// and the return value will be stored as the default value (used
// if you call setting.ResetToDefault()).
//
// It may also be called at any time by the settings system and
// should return the current state of the value in your game.
//
// If this value is changed from outside the settings system, then
// you need to call setting.PullFromConnection() to update the internal
// value of the setting.
//
// "Pull" in this context is meant as from the view point of the setting.
// I.e. "pull the value from the connection into the setting and update the UI".
// During this pull process connection.Get() is called which calls
// this getter.
//
// There is also a setting.PushToConnection() method which does the opposite.
// It pushes the value from the setting into the connection (connection.Set())
protected int getHealthRegeneration()
{
    // This is where you would add your game specific code.
    return _healthRegeneration;
}

// This simply sets the local field and logs the new value.
protected void setHealthRegeneration(int value)
{
    // This is where you would add your game specific code.
    _healthRegeneration = value;
    Debug.Log("Health regeneration has been set to: " + value);
}

```

Making a custom Connection class

The settings system reduces any setting into basic types (bool, Color, float, int, string, ...). To connect a setting to some custom code you have to implement an interface called `IConnection<T>`.

The interface is really simple:

```
public interface IConnection<TValue> : IConnection
{
    public delegate void OnChangedDelegate(TValue value);

    // This is where all the magic happens.
    public TValue Get();
    public void Set(TValue value);

    // Don't worry. There is a base class implementing these for you (see below).
    public void AddChangeListener(OnChangedDelegate listener);
    public void RemoveChangeListener(OnChangedDelegate listener);
}
```

You need to create a new Connection class implementing that interface. All the premade connections are made like this too.

Here is the VSync connection for example:

```
public class VSyncConnection : Connection<bool>
{
    public override bool Get()
    {
        return QualitySettings.vSyncCount != 0;
    }

    public override void Set(bool vSyncEnabled)
    {
        QualitySettings.vSyncCount = vSyncEnabled ? 1 : 0;
        NotifyListenersIfChanged(vSyncEnabled);
    }
}
```

You may have noticed that it does not implement the `IConnection` interface directly but instead extends a generic class `Connection<bool>` (where `bool` is the type of what the `Get()` method returns and what the `Set(value)` takes).

Using the generic base class spares you the work of implementing `AddChangeListener()` etc. . Just override `Get` and `Set(value)` and you have a fully functional connection.

Now this is a complete Connection and you can use it in code. BUT you can not yet use your new Connection in the ScriptableObject Assets (`Settings.asset`). To enable this you will also have

to implement a Scriptable Object for your Connection (and then instantiate it). We can use some of our base classes to spare us typing all the repetitive code.

Here is how the SO class for the VSyncConnection looks like:

```
namespace Kamgam.SettingsGenerator
{
    [CreateAssetMenu(fileName = "VSyncConnection", menuName =
"SettingsGenerator/Connection/VSyncConnection", order = 1)]
    public class VSyncConnectionSO : BoolConnectionSO
    {
        protected VSyncConnection _connection;

        public override IConnection<bool> GetConnection()
        {
            if(_connection == null)
                Create();

            return _connection;
        }

        public void Create()
        {
            _connection = new VSyncConnection();
        }
    }
}
```

Now you can create an SO Asset and use it for any setting matching the type (bool in this case).

If you are not a coder then maybe you are able to do it with the VisualScripting package and the GetSetConnection, though it's cumbersome compared to the code solution.

The **ICollectionWithSettingsAccess** interface


Add it to a connection if that connection needs to know what settings object it belongs too. If this is added to a connection then the settings system will notice and call `SetSettings(Settings settings)` after load but before `InitializeConnection()`.

An example of a connection using this is the `QualityConnection`.

NOTICE the plural there. The interface gives your connection access to ALL settings not just the ones this connection is used by. If you want to get the settings that use this exact connection then use the `Settings.GetSettingsWithConnection(ICollection connection, ..)` or `GetSettingsWithConnectionByType()` methods.

Changing the save & load method

In the "Provider Details" section of the Creator Window you can pick a "saver" object (currently PlayerPrefs and JSON are supported).



HINT: If you derive from SettingsSaveBase then you can easily create your own saver objects.


Settings Save Locations

By default they are saved in the PlayerPrefs which is Unitys mechanism for saving player preferences and they are stored in different locations depending on your platform ([Player Prefs Unity Docs](#)). On Windows they are actually stored in the registry, not a file.

If you have configured the JSON Settings Saver then they are stored in the Application.DataPath. A default path set by Unity for storing data. It also differs per platform ([Unity Docs](#)).

Auto-Deleting Saved Settings (for testing)

In v1.71+ there is a "Delete Saved Settings At Start" checkbox. If checked it will have the settings automatically deleted at the start (useful for testing). Please remember to disable this once you make your final build!



Adding custom save & load methods (code only)

As mentioned above you can create your own saver objects by deriving from `SettingsSaveBase` BUT you can also set custom save/load/delete methods at runtime.

You can override the methods used for save, load and delete on the Settings.

To do this set the static: **Settings.CustomSaveMethod**, **Settings.CustomLoadMethod** and **Settings.CustomDeleteMethod** methods. If you change one of these then you should always change all three.

Under Assets/Kamgam/SettingsGenerator/Examples/SaveLoadCustomization you will find a file named "**SettingsInitializerSaveLoadToFile.cs**". It contains a demo of how to override the save & load methods (json file).

NOTICE: It is important that you set these BEFORE the Settings are used for the very first time or else it will still use the default method.

That's why the class uses the `[DefaultExecutionOrder(-10)]` Attribute.

SettingsInitializerSaveLoadToFile.cs:

```
using System.IO;
using UnityEngine;

namespace Kamgam.SettingsGenerator.Examples
{
    // Make sure this runs before any normal Awake code.
    [DefaultExecutionOrder(-10)]
    public class SettingsInitializerSaveLoadToFile : MonoBehaviour
    {
        void Awake()
        {
            Settings.CustomLoadMethod = load;
            Settings.CustomSaveMethod = save;
            Settings.CustomDeleteMethod = delete;
        }

        // Let's save the json data into a file instead of Player Prefs.
        string getFilePath(string key)
        {
            return Application.dataPath + "/" + key + ".json";
        }

        void delete(string key, Settings settings)
        {
            var filePath = getFilePath(key);
            if (File.Exists(filePath))
            {
                File.Delete(filePath);
            }

            // Delete .meta file in editor
#if UNITY_EDITOR
            if (File.Exists(filePath + ".meta"))
#endif
        }
    }
}
```

```

        {
            File.Delete(filePath + ".meta");
            UnityEditor.AssetDatabase.Refresh();
        }
#endif
    }

    void save(string key, Settings settings)
    {
        var json = SettingsSerializer.ToJson(settings);
        if (!string.IsNullOrEmpty(json))
        {
            var filePath = getFilePath(key);
            // Write to tmp file first.
            File.WriteAllText(filePath + ".tmp", json, System.Text.Encoding.UTF8);

            // Check if tmp file now exists.
            // If you want to be extra sure you could do a validity check of .tmp.
            if (File.Exists(filePath + ".tmp"))
            {
                // Delet existing
                if (File.Exists(filePath))
                {
                    File.Delete(filePath);
                }
                // Finally move the tmp file.
                File.Move(filePath + ".tmp", filePath);

                // Log path (for testing)
                Debug.Log("Saved to: " + filePath);
            }
        }
    }

    #if UNITY_EDITOR
        UnityEditor.AssetDatabase.Refresh();
    #endif

}


void load(string key, Settings settings)
{
    var filePath = getFilePath(key);
    if (!File.Exists(filePath))
        return;

    var json = File.ReadAllText(filePath, System.Text.Encoding.UTF8);
    if (!string.IsNullOrEmpty(json))
    {
        SettingsSerializer.FromJson(json, settings);
    }
}
}

```

Localization

Each textfield in the UGUI components comes attached with a Localize component. There you can enter a term that will then be looked up in the LocalizationProvider.



It is a fairly rudimentary localization system but for the settings it is sufficient. You can easily replace it with some dedicated localization system like [i2 Localization](#) (see "ILocalization.SetDynamicLocalizationCallback")

Third Party Localization Support (example: I2 Localization)

To quickly integrate a third-party localization you can configure the included localization to forward all translation requests to another object.

The example below shows how this can be done for the popular [I2 Localization](#) asset. You can find a script template named "LocalizationInitializerTemplate" in the "Libs/LocalizationsForSettings/Runtime" folder.

NOTICE: Please do not edit the template directly. Copy it, rename the class and move it to /Assets (outside the settings system folders). This will ensure it can access any i2l classes.

```
using UnityEngine;
using Kamgam.LocalizationForSettings;

/// <summary>
/// Usually the localization does NOT need and initialization as it is
/// initialized on demand. However, if you want to bind another localization
/// solution to it then this may be a handy template.
/// </summary>
[DefaultExecutionOrder(-11)] // Not strictly necessary. Just to be sure it runs before settings.
public class I2LocalizationSettingsInitializer : MonoBehaviour
{
    /// Don't forget to hook this up with the right provider in the inspector.
    public LocalizationProvider Provider;

    public void Awake()
    {
        var localization = Provider.GetLocalization();

        // Tell the settings localization to ask I2L for translations.
        localization.SetDynamicLocalizationCallback(dynamicLocalization);

        // Hook into I2 Localization and listen for language changes.
        I2.Loc.LocalizationManager.OnLocalizeEvent += onI2LLocalizeEvent;
    }

    protected void onI2LLocalizeEvent()
    {
        // Trigger language change event to force a refresh on all translations.
        var localization = Provider.GetLocalization();
        localization.TriggerLanguageChangeEvent();
    }

    protected string dynamicLocalization(string term, string language)
    {
        string translation;

        if (!I2.Loc.LocalizationManager.TryGetTranslation(term, out translation))
        {
            var localization = Provider.GetLocalization();
            // Get translation without dynamic (to avoid infinite loop).
            translation = localization.Get(term, ignoreDynamic: true);
        }

        return translation;
    }
}
```

Unity Localization Support

Here is an example implementation of a MonoBehaviour that enables Unity Localization usage.

```
using System.Collections;
using System.Collections.Generic;
using System.Linq;
using UnityEngine;
using Kamgam.LocalizationForSettings;
using UnityEngine.Localization;
using UnityEngine.Localization.Settings;

namespace Kamgam.SettingsGenerator
{
    [DefaultExecutionOrder(-11)] // <- Just to be extra sure.
    public class UnityLocalizationSettingsInitializer : MonoBehaviour
    {
        [Tooltip("Don't forget to hook this up with the right provider in the inspector.")]
        public LocalizationProvider Provider;

        [Tooltip("Add your localization table names here. This will search for settings localizations in all the tables listed here.")]
        public List<string> TableNames = new List<string>() { "Localizations" };

        [System.Serializable]
        public class LanguageToCode
        {
            /// <summary>
            /// Settings system localization language name (like "English", "German").
            /// </summary>
            [Tooltip("Settings system localization language name (like 'English', 'German').")]
            public string LanguageName;

            /// <summary>
            /// Unit's locale identifier (like "en", "de", ..)
            /// </summary>
            [Tooltip("Unity's locale identifier (like 'en', 'de', ..)")]
            public string LocaleCode;
        }

        [Tooltip("Conversion list from settings language names to Unity locale code (i.e. 'English'
        <-> 'en'.")]
        public List<LanguageToCode> SettingsLangToLocaleCode = new List<LanguageToCode>()
        {
            new LanguageToCode() { LanguageName = "English", LocaleCode = "en" },
            new LanguageToCode() { LanguageName = "German", LocaleCode = "de" }
        };

        [Tooltip(
        localization."If enabled then setting the language in the settings localization will update Unity
        localization." +
        "Useful if you have a language setting based on the settings localization.\n\n" +
        localization."Usually it's fine to keep this turned off since the chosen language is driven by Unitys
        localization.")]
        public bool UpdateUnityLocalizationFromSettingsLanguage;

        public string SettingsLanguageNameToLocaleId(string language)
        {
            language); var langToCode = SettingsLangToLocaleCode.FirstOrDefault(l => l.LanguageName ==
            if (langToCode != null)
```

```

        return langToCode.LocaleCode;
    return language;
}

public string LocaleIdToSettingsLanguageName(string localeId)
{
    var langToId = SettingsLangToLocaleCode.FirstOrDefault(l => l.LocaleCode == localeId);
    if (langToId != null)
        return langToId.LanguageName;
    return localeId;
}

protected bool _initialized = false;

public void Awake()
{
    var localization = Provider.GetLocalization();

    // Tell the settings localization to ask Unity localization for translations.
    localization.SetDynamicLocalizationCallback(dynamicLocalization);

    // Hook into Unity Localization and listen for language changes.
    LocalizationSettings.Instance.OnSelectedLocaleChanged += onUnityLocaleChanged;
}

IEnumerator Start()
{
    yield return LocalizationSettings.InitializationOperation;

    _initialized = true;

    // Async inform the settings of new localizations.
    var locale = LocalizationSettings.Instance.GetSelectedLocale();
    updateSettingsLanguageFromUnityLocale(locale);
}

private void updateSettingsLanguageFromUnityLocale(Locale locale)
{
    if (locale != null)
    {
        // Convert from Unity locale to settings
        var settingsLanguage = LocaleIdToSettingsLanguageName(locale.Identifier.Code);

        // Set the language in the settings localization based on the given locale.
        var localization = Provider.GetLocalization();
        if (localization.GetLanguage() != settingsLanguage)
            localization.SetLanguage(settingsLanguage);
        else
            localization.TriggerLanguageChangeEvent();
    }
}

private void onUnityLocaleChanged(Locale locale)
{
    updateSettingsLanguageFromUnityLocale(locale);
}

protected string dynamicLocalization(string term, string language)
{
    if (!_initialized)
        return term;
}

```

```

        if (!TryGetTranslation(term, language, out var translation))
        {
            // If not found in Unity localization then fall back on built in localization.
            var localization = Provider.GetLocalization();

            // Get translation without dynamic (to avoid infinite loop).
            translation = localization.Get(term, ignoreDynamic: true);
        }

        return translation;
    }

    public bool TryGetTranslation(string term, string language, out string translation)
    {
        // Set the locale based on the language name
        if (UpdateUnityLocalizationFromSettingsLanguage)
        {
            var selectedLocale = LocalizationSettings.Instance.GetSelectedLocale();
            if (!languageMatchesLocale(language, selectedLocale))
            {
                var locale =
                    LocalizationSettings.AvailableLocales.Locales.FirstOrDefault(locale =>
                        languageMatchesLocale(language, locale));
                if (locale != null)
                {
                    LocalizationSettings.SelectedLocale = locale;
                }
            }
        }

        // Get the table and entry
        foreach (var tableName in TableNames)
        {
            var table = LocalizationSettings.StringDatabase.GetTable(tableName);
            if (table == null)
                continue;


            var entry = table.GetEntry(term);
            if (entry != null)
            {
                translation = entry.GetLocalizedString();
                return true;
            }
        }

        translation = term;
        return false;
    }

    protected bool languageMatchesLocale(string language, Locale locale)
    {
        return locale != null && (locale.LocaleName == language
            || locale.name == language
            || locale.Identifier.Code == language);
    }
}

```

And this is the setup in a scene. Notice that you will have to enter your localization table name and you can also match them to the Unity localization Codes:



Localization API

Changing the language via Script

If you have a reference to the localization provider then this is just one line. Here is an example:


```
using Kamgam.LocalizationForSettings;
using System.Collections;
using System.Collections.Generic;
using UnityEngine;

public class ChangeLanguageTest : MonoBehaviour
{
    // Don't forget to draop in the provider in the inspector.
    public LocalizationProvider LocProvider;

    void changeLanguageTest()
    {
        // "English" and "German" are predefined in the default localization.
        LocProvider.GetLocalization().SetLanguage("YourLanguageName");
    }
}
```

Localizing Key Control Paths

To localize the text that is used for the key controls you can use the control paths as keys for the localization system. The system automatically searches in the localization before it tries to auto convert the control paths to readable text.




You can find more info on how to create sprites in TMPro here:

<https://docs.unity3d.com/Packages/com.unity.textmeshpro@4.0/manual/Sprites.html>

You may ask: How do you know what term to use in the localization?

The used binding path is visible on the InputBindingUGUI component at runtime:



Visual Scripting (formerly BOLT)



Visual Scripting requires a manual setup (let BOLT know the settings exist). Don't worry this will take only a minute.

Here are the steps:


Go to **Edit > Project Settings > Visual Scripting**:

- 1) Add **Kamgam.SettingsGenerator** to the "Node Library"
- 2) Add the Settings Types (**SettingsProvider**, **Settings**, all the **Setting..**) to the "Type Options"
- 3) Hit "**Regenerate Nodes**" to apply the changes.


Step 1



Step 2




Step 3




You can then retrieve any setting via its ID.

It looks like this (a simple example which disables the object if audio is disabled):




Configuration & Debugging

If a setting does not do what you want despite it being set up correctly then you can enable verbose logging to see if that gives you a clue.



Setting the LogLevel to “Log” will show you all the messages.



Input Validation

Sometimes (especially with text) you may wish to validate the input. Here is a guide on how to achieve this for a string setting. For convenience we will use the “playerName” settings from the demo scene.

There are two options for how you could achieve this (via a custom OnChange event script or a custom connection object).

Validation via OnChange events

```
using System.Collections;
using System.Collections.Generic;
using UnityEngine;
using Kamgam.SettingsGenerator;
using System;

namespace YourGame
{
    public class StringWithValidationTest : MonoBehaviour
    {
        public SettingsProvider SettingsProvider;
        public Settings Settings => SettingsProvider.Settings;

        public void Start()
        {
            Settings.GetString("playerName").OnStringSettingChanged += onSettingChanged;
        }

        private void onSettingChanged(SettingString setting)
        {
            // Get the value and validate/change it.
            string rawValue = setting.GetValue();
            string sanitizedValue = rawValue.Replace("aaa", "");

            // Write the changed value back to the setting.
            // propagateChange = false is important or else you would get endless loops.
            setting.SetValue(sanitizedValue, propagateChange: false);

            // Propagate the change to UI (update the text in the textfield).
            Settings.RefreshRegisteredResolvers(setting);
        }
    }
}
```

This script will replace all occurrences of “aaa” in a text. It does it by updating the setting value in the on change event.

Validation via Connection objects

One way of hooking up some validation code to a setting is making a connection object. Below you will find the code for a very simple text validation. All it does is store the text in the "Value" property of the connection and it automatically removes all instances of tripple-a sequences (i.e.: "testaaa" will become "test" because the "aaa" will be removed).

```
using System.Collections;
using System.Collections.Generic;
using UnityEngine;
using Kamgam.SettingsGenerator;

namespace YourGame
{
    public class StringWithValidationConnection :
        Connection<string>,
        IConnectionWithSettingsAccess
    {
        public Settings Settings;

        // This is where the value is stored at runtime.
        // In your game this probably is some external
        // service or your save-game or something.
        [System.NonSerialized]
        public string Value;

        public override string Get() => Value;
        public Settings GetSettings() => Settings;

        public void SetSettings(Settings settings)
        {
            Settings = settings;
        }

        public override void Set(string value)
        {
            if (string.IsNullOrEmpty(value))
                return;

            // The actual validation. Do whatever you need here.
            Value = value.Replace("aaa", "");

            // Refresh all string values that are using this connection.
            Settings.PullFromConnection(this, propagateChange: true);

            // Force and update on all UI elements that are using this connection.
            Settings.RefreshRegisteredResolversWithConnection(this);
        }
    }
}
```

Notice that the actual validation code is trivial: `Value = value.Replace("aaa", "");`

To hook up the connection we also want a connection asset. This is not strictly necessary since we could do this via code too but it is very convenient.

```
using System.Collections;
using System.Collections.Generic;
using UnityEngine;
using Kamgam.SettingsGenerator;


namespace YourGame
{
    [CreateAssetMenu(fileName = "StringWithValidationConnection", menuName =
"SettingsGenerator/Connection/StringWithValidationConnection", order = 4)]
    public class StringWithValidationConnectionSO : StringConnectionSO
    {
        [System.NonSerialized]
        protected StringWithValidationConnection _connection;

        public override IConnection<string> GetConnection()
        {
            _connection = new StringWithValidationConnection();
            return _connection;
        }


        public override void DestroyConnection()
        {
            if (_connection != null)
                _connection.Destroy();

            _connection = null;
        }
    }
}
```

Now with all the code set up we can create the connection object ..



.. and assign it to the playerName setting.



NOTICE 1: Strictly speaking this is not a validation before assign. It's more a validation after the value has changed. If you are using an OnSettingChanged event to listen for changes to this setting you will first receive the unvalidated raw value and then immediately afterwards you will get the validate value.

NOTICE 2: If you want to use this connection for multiple input fields then you will have to generate a new SO asset for each setting. Otherwise all the settings would write into the same single "Value" field of the connection object and overwrite each other.

And that's it.

Upgrading from older versions


This asset follows the [Semantic Versioning](#) scheme. This means is the new version is no major version upgrade then there should be no breaking changes in the code.

Actions to perform after updating to fix example scenes

Some Unity versions require special assets (like URP and HDRP for rendering or the new input system). Upon first import these are detected and installed automatically. However after an UPDATE of the asset this is may not be done automatically.

You will have to trigger the import manually by calling:

Tools > Settings Generator > Debug > Import Packages



If there still are errors or things are not wokring (like post pro effect) then try to restart Unity.

Please contact support under office[a]kamgam.com if there still are errors afterwards.

Third Party Integrations


Over time some kind users (an other asset devs) have contacted me with recommendations for custom integrations. Here is a list of custom connections and integrations (with some rudimentary tutorials)

NOTICE #1: Please notice that I do not have any influence on these third party assets.

NOTICE #2: These assets may not support all render pipelines or Unity versions that Unified Settings do support. Please check the corresponding asset page for more information.

I'll try to keep my implementations up-to-date, yet realistically I only update them if someone pokes me (tells me something is broken) and if I have time to do it. Continuous testing all of these assets would be too much work for me. I also have no influence on the quality of these assets. Some may be abandonned or broken in the future. I reserve the right to drop support for any third party asset at any time. Please contact the creator of the asset (not me) for support. - Thank you for understanding.

The code of these thirparty implementations can be found here (usually in the form of a custom Connection class):



Rewired Integration

I have thought about this for a while now since it keeps getting asked. I have arrived at the conclusions that I would recommend to use the Rewired [Control Mapper](#) for your Input Rebinding UI if you are using Rewired.

For the full discussion please go to this forum thread:

<https://forum.unity.com/threads/unified-settings-game-options.1382952/#post-9028486>

Rewired is an explicit Input System it already covers all your needs in terms of input binding. It would say it is more advanced than the settings system input. It features multi user bindings, input calibration for thumb sticks,

You can mix the Settings System and Rewired.

Use Rewired for the Input UI and the settings system for the rest.

Adding a wrapper around Rewired would only add some new complexity and it would always be behind in features compared to the original.

If Rewired did not have it's own save and UI system then it would make sense to add one in the settings system. But since Rewired already has these I don't think it is a worthwhile endeavour to try to replace it.

You can install the Rewired Control Mapper via:

Window > Rewired > Extras > Control Mapper > Install


If you just rip out the input controls from the Settings System UI and add in the Rewired Control Mapper (ControlMapper Prefab) you should be ready to go (in case you have Rewired setup up already).

I know this may not be the answer you wanted but I really think adding yet another layer of abstraction around Rewired is not the way to go. If you are using Rewired, best use it all the way.

If you are not sure how to add Rewired to the existing settings UI then there is a tutorial in the next section.



Rewired Input Remapping (Recommended)

- 1) Install the Mapper via Window > Rewired > Extras > Control Mapper > Install
- 2) Remove the existing inputs. Select the in the UI and delete them:



You may also want to delete the reset controls button (or your change it to access the rewired ControlMapper).

- 3) Copy the rewired parts from the ControlMapper demo. You probably already have a "Rewired Input Manager" and a "RewiredEventSystem". If you do then use them instead. The important part of the UI is the ControlMapper Prefab.



4) Now, sadly, we have to UNPACK the prefab. We have to do that because the Prefab root uses a Transform instead of a RectTransform, yet we need it to have a rect transform to integrate it into our canvas.

4.1) Right-Click the prefabs and choose Prefab > Unpack


4.2) Right on top the the Control Mapper create a new empty object and name it "ControlMapper".

4.3) Copy the control mapper component from the unpacked ControlMapper onto the new object.




4.4) Move (don't copy!) the whole Canvas from the unpacked ControlMapper into the new object.

4.5) Delete the old ControlMapper Prefab.


Now you should have something looking like this:.



5) Make sure the canvases all have proper rect transform sizes and scales (they tend to reset to 0/0/0 when copied or moved). Also make sure the internal data of the new ControlMapper (scroll way down) are linked to the right canvas elements.



In the end, if you hit play then your UI should look like this:




Here are the docs on how to [design \(theme\) the Rewired UI](#). The creator of Rewired opted to use the Unity UI theming system instead of a prefabs based approach like the settings system uses.

And that's it.


Using Rewired with Settings UI (Not Recommended)

It is recommended to use the Rewired included UI and remapping (see “Rewired Input Remapping” above). The reason is that Rewired has some more advanced features for controllers than a generic solution like the settings system.

However, if you want to keep using the settings UI for inputs then you can use the EXPERIMENTAL Rewired integration. First thing to do it to let the system know you are using Rewired. For that call Tools > Settings Generator > Third Party > Rewired Setup.



This will add a define to the symbols:



Once you have done that you can use the **RewiredUtils** class in your code.

RewiredUtils allows you to convert a UniversalKeyCode to IControllerTemplateButton, like this:

```
using Kamgam.SettingsGenerator;
using System.Collections;
using System.Collections.Generic;
using UnityEngine;

public class RewiredUtilsTest : MonoBehaviour
{
    void Update()
    {
        var btn = RewiredUtils.UniversalKeyCodeToIControllerTemplateButton(
            Kamgam.UGUIComponentsForSettings.UniversalKeyCode.GamePadSouth);
        if (btn != null)
            Debug.Log(btn.value);
        else
            Debug.Log("No gamepad used yet.");
    }
}
```

Please notice that you will be in charge of reacting to changes in the values on the controls.


NOTICE: Due to the code structure of Rewired it can happen that the RewiredUtils class may

break in future releases of Rewired (it uses some Rewired internal code constants). It's unlikely to break easily yet I can not make any guarantees, thus please consider this API EXPERIMENTAL.


InControl Integration

If you are using the new input system then I recommend skipping [InControl](#). This section here is for those who are using the old Input System and want to use the KeyCombination settings (UniversalKeyCode) with InControl.

First step would be to let the settings system know InControl is used:



This will add a define to the symbols:




Once that define is set you will be able to use the **InControlUtils** class to convert between InControl controls and UniversalKeyCodes.

I recommend using "InControlUtils.UniversalKeyCodeToControlFunc(UniversalKeyCode keyCode)" since that will return a function that always returns the correct InControl control.

```
var speedSetting = Settings.GetKeyCombination("controller.speed");  
var speed = InControlUtils.UniversalKeyCodeToControlFunc(speedSetting .GetValue().Key);  
bool isSpeedPressed = speed().IsPressed;
```

TheNakedDev UpScalers (FSR, DLSS, SGSR, XeSS)


Formerly known as "Alterego Games" the "The Naked Dev" developer has created implementations for many upscalers. The important part to know is if you are using the OLD or the NEW version of these assets. If you have a "TND Upscaler Framework" package then you are using the new (much simpler) system.



<- this means you are using the new system.

The new system makes using the upscalers very easy. Please follow the [TND manual here](#) for setup instructions.

Once you have set it up you can make a new options settings using the "TheNakedDevUpscalerConnection". NOTICE: You only need this once for ALL the TND upscalers (it controls whichever upscaler is currently used by the TND system).



If you are on the OLD version (you don't have the TND Upscaler Framework in your packages) then you will have to follow the upscaler specific guides below:

(OLD) DLSS Connection (by "The Naked Dev" formerly "Alterego Games")

The "AlteregoDLSSConnection" add support for the [DLSS Anti Aliasing Asset](#) by Alterego Games.


NOTICE: The developer rebranded to TheNakedDev. However to remain backwards compatible the old name was kept.

NOTICE: Newer versions that use packages and the TNDUpscaler component do NOT require the extra setup as described below. If you are on the newer versions all you need is a single one of the TND Connections which will control the TNDUpscaler which in turn decides what upscaler to use.

If you encounter any DLSS related issues, you can contact Alterego Games by emailing to info@thenakeddev.com, joining their [discord](#) in the "Unity Tools" channel or on the [Unity Forum](#).


To use it you will have to install the Alterego DLSS package and the NVIDIA package (instructions are in the DLSS manual that ship with the package). Please notice that the NVIDIA package will not install automatically. You will see the install link once you add DLSS to your post-processing layer on your camera.

To verify you have DLSS properly installed and set up please check the script defines. If DLSS is installed you should see two defines (DLSS_INSTALLED and AEG_DLSS).




Here is how you enable DLSS on your post processing layer:

NOTICE: At the moment you can use either the normal AntiAliasing or DLSS. If DLSS is enabled




on the camera the regular AntiAliasing options will do nothing (DLSS has taken over).

Here is how the DLSS options look at the moment (notice the “off” option for turning DLSS off):




Notice the option labels are not localized. I'll leave localization to you. To localize them simply add the terms to the LocalizationProvider like any other setting localization.


There is a premade "AlteregoDLSSConnection" object which you can use in the settings.




Simply drop it in as the Connection Object:



In the UI the DLSS setting works just like any other options setting. Notice that the DLSS dropdown is not part of the default demo. You will have to add a new options dropdown on your own.



And that's it. Here is the result after I added DLSS to the demo scene (that's some nice anti aliasing):



(OLD) FSR Connection (by “The Naked Dev”, formerly “Alterego Games”)


The “AlteregoFSR2Connection” add support for the [FSR2 Asset](#) by Altergo Games. Despite its name is also supports FSR3 (I kept the name for backwards compatibility reasons).

NOTICE: The developer rebranded to TheNakedDev. However to remain backwards compatible the old name was kept.


NOTICE: Newer versions that use packages and the TNDUpscaler component do NOT require the extra setup as described below. If you are on the newer versions all you need is a single one of the TND Connections which will control the TNDUpscaler which in turn decides what upscaler to use.

If you encounter any DLSS related issues, you can contact Altergo Games by emailing to info@thenakeddev.com, joining their [discord](#) in the “Unity Tools” channel or on the [Unity Forum](#).

After installation you will have to add the FSR2 component to your camera (more details on that are in the FSR2 manual):




Here is how the FSR 2 options look:




Notice the option labels are not localized. I'll leave localization to you. To localize them simply add the terms to the LocalizationProvider like any other setting localization.

There is a premade "AlteregeFSR2Connection" object which you can use in the settings.

Simply drop it in as the Connection Object:



In the UI the FSR2 setting works just like any other options setting. Notice that the FSR2 dropdown is not part of the default demo. You will have to add a new options dropdown on your own.



Inspector

DropdownUGUIWithLabel (FSR2)

Static

Tag Untagged Layer UI

Variant Open Select Overrides

▶ Rect Transform

▶ Canvas Renderer

▶

Drop Down UGUI (Script)

▶

Dropdown - TextMeshPro

▶ Auto Navigation Overrides (Script)

▶ Selection Event Listener (Script)

▶ Scroll Into View On Select UGUI (Script)

▼

DropDownUGUIResolver

Settings Provider

Localization Provider

ID

This Setting uses a CONNECTION.

Suggested IDs:

SettingsProvider (FromAsset) (Settings Provider)

LocalizationProvider (Localization Provider)

fsr

fsr


(OLD) SGSR Connection (by “The Naked Dev”)

The “NakedDevSGSRConnection” allows you to use SGSR in your project. It does require the SGSR [package](#) from the asset store and it assumes you have integrated it with the component on the CAMERA (especially important if you use the BuiltIn-RP).

NOTICE: The developer rebranded to TheNakedDev. However to remain backwards compatible the old name was kept.

NOTICE: Newer versions that use packages and the TNDUpscaler component do NOT require the extra setup as described below. If you are on the newer versions all you need is a single one of the TND Connections which will control the TNDUpscaler which in turn decides what upscaler to use.


Here is the URP example (with the SGSR render feature added):



For a more detailed integration guide please check the manual of the asset:

https://docs.google.com/document/d/1s8tQYdpSMZRLf1gndRSekam-t9FYGE_e9QLgVJAbeH8

Once you have it properly set up you can use the SGSR connection for an option setting:



(OLD) XeSS Connection (by “The Naked Dev”)


The “NakedDevXeSSConnection” allows you to use XeSS.

It does require the XeSS [package](#) from the asset store and it assumes you have integrated it with the component on the CAMERA (especially important if you use the BuiltIn-RP).

NOTICE: The developer rebranded to TheNakedDev. However to remain backwards compatible the old name was kept.

NOTICE: Newer versions that use packages and the TNDUpscaler component do NOT require the extra setup as described below. If you are on the newer versions all you need is a single one of the TND Connections which will control the TNDUpscaler which in turn decides what upscaler to use.


Here is the URP example (with the XeSS render feature added):



For a more detailed integration guide please check the manual of the asset:



https://docs.google.com/document/d/1nb1cdNNc9zzmvbDbwPERKm21g_Cp8o9V2sjVV1JsQNM

Once you have it properly set up you can use the XeSS connection for an option setting:




PlayMaker

There is rudimentary playmaker support. You can listen to setting changes and extract settings values like this:



For more advanced stuff you would have to use PlayMakers scripting extension methods.




Please contact support if you have any specific needs.



MasterAudio

There is some support for the most commonly used MasterAudio settings. Namely mute, unmute and volume for masters, playlists, groups and buses.

MasterAudio support is not enabled by default. After installation you will have to enable it via:



Once it is enabled you can use the predefined MasterAudio connections or make some yourself for your playlists, buses and sound groups.



Common Issues / FAQ

Post Processing Settings do nothing

Solution: For Built-In renderer projects you need to install the post processing stack package from the package manager AND you will have to add a PostProcessing Layer to your camera and a PostProcessing Volume to your scene. Check out the examples under "Examples/FromAsset". They already include a proper PostProcessing setup.

URP: Make sure you have "PostProcessing" enabled on your main camera.

URP: Make sure that you are NOT using the Built-In postprocessing stack v2 package (URP has its own PostPro stack included).

Post Processing Render Context Null Pointer

You are getting an error like this:

```
NullReferenceException: Object reference not set to an instance of an object
UnityEngine.Rendering.PostProcessing.AmbientOcclusion.IsEnabledAndSupported
(UnityEngine.Rendering.PostProcessing.PostProcessRenderContext context) (at
Library/PackageCache/com.unity.postprocessing@2.1.3/PostProcessing/Runtime/
Effects/AmbientOcclusion.cs:179)
```

Solution: Recreate the PostProcessing Layer component on your camera or switch the Inspector to debug mode and set the "PostProcess Resource" to a valid resource (see [forum](#)).

Post Processing not visible on mobile (Built-In render pipeline)

Post processing support for the built-in render pipeline is very hit and miss on mobile. Don't use Built-In PostPro on mobile. Use the URP renderer instead. It comes with its own PostProcessing stack and that one works on mobile too.

Controller X is not working properly (Old Input System)

Controller support for the OLD input system is based on the standard xbox controller layout. I encourage you to use the NEW InputSystem which has a much better controller abstraction included. If you are fixed to the old system then I'd recommend using [InControl](#) for controller abstraction.


The example scenes are all pink after updating the asset (URP or HDRP)

URP and HDRP require different materials (shaders). After first install the tool imports these automatically but, depending on what version you are using, it may not do it after an update.

You will have to trigger the import manually by calling:

Tools > Settings Generator > Debug > Import Packages

After that all the example materials should be fixed.





If you are not using the example scenes anymore then this step is not necessary. The settings system will work just fine if you don't do it. It's just the materials and example scenes that are changed by this not the system itself.

InvalidOperationException: You are trying to read Input using ..

InvalidOperationException: You are trying to read Input using the UnityEngine.Input class, but you have switched active Input handling to Input System package in Player Settings.

This may happen after upgrading the asset if you run the game without opening the scene first. Please open the demo (not the ui) scene once (it will fix itself automatically).

You can also fix it manually by using the Input Module Fixer > "Fix" button




The Post Processing effect is not found


This will result in a warning like "There was no ambient occlusion setting found .." or "There was no active 'AmbientOcclusion' PostPro effect (BuiltIn) found."

Basicall what you need is three prerequisites for post pro effects to work:


1) You have to add a PostPro Volume with a profile containing 'Ambient Occlusion' to your post pro Volume. Please also make sure it is enabled.



2) Make sure the layers of your camera and the PostProcessing-Layer component do match and that all the components are active.



3) If your Volume is NOT a global volume (global checkbox off) then you will have to add a Trigger Collider (a collider with "trigger" enabled). Place the collider directly on your Post-process Volume.



The demo scenes

(Assets/Kamgam/SettingsGenerator/Examples/FromAssets/SettingsFromAssetDemo) contains a working setup of this for you to look at. The demo uses the default "water" layer for post effects. You may want to change this.

A good test whether or not your setup is correct is if you see the effect in the "Game" view (is there some ambient occlusion). If you don't see it then the settings system will also not find it.

You may see these logs even if everything set up correctly. Here is why:

At the start the settings system searches for volumes with post pro effects in all currently loaded scenes. However, if you are loading the scenes that contain the post-pro effects later (via code) then the settings system will log these messages because it can not find them at the start.


This has far reaching consequences because at the very first load the settings system will search for the post-pro effects to GET the default values. It does this to answer questions like: "Should bloom be ON or OFF when the game is loaded for the first time?". If it can not find any bloom effect then that's when you see the warning message.

If you want to dive into how it searches for the post-pro effects then you can find the code in the "SettingsVolume.cs" class in "FindDefaultVolumeComponent<T>()" - It returns the active component of the first found global volume or a volume that is child of the main camera. This means that if your volume is a local volume somewhere in the scene then it will not be found (except if it's a child of the main camera).

The logs may also show if you initialize the settings system in Awake(). That's because the volumes initialize in Awake() too and thus they may be available only after the settings system was already initialized. To avoid this simply initialize the settings in Start() instead of Awake().

I have upgraded from an older version but don't see the new examples?

They are part of the fixes. Please import them manually by calling this:



Rebinding input actions has no effect. Why?

Either you have an error in your setup or (if the rebinding works in the demo) you are using the generated c# input actions class. If you do, then you will have to reassign the actions asset at runtime like this:

```
public class Test : MonoBehaviour
{
    YouInputActionsClass inputControls;
    public SettingsProvider SettingsProvider;

    void Start()
    {
        if (inputControls == null)
        {
            inputControls = new YouInputActionsClass();
        }


        var settings = SettingsProvider.Settings;
        settings.SetInputActionAsset(inputControls.asset);
    }
}
```

For more details please refer to the Input Binding section.

How to add a “Mouse Sensitivity” setting?

You may have noticed that there is no MouseSensitivityConnection despite that being one of the most common settings found in many games. It is on the list of features to investigate, though it is not an easy one to add. The sensitivity value itself would need to be fed into whatever Character Controller is used (and sadly there are many different ones). Also the settings system can not know what changes have been made to the controller (i.e. if your code overrides the value too, which would generate a conflict).

At the moment the recommend way is to simply add a float setting and use that as a multiplier for your mouse sensitivity. Like this:



In your code you can then fetch that value like this:

```
// "SettingsProvider" is the SettingsProvider asset.
```

Settings Provider **SettingsProvider (FromAsset) (Settings P**

```
var multiplier = SettingsProvider.Settings.GetOrCreateFloat("mouseSensitivity");
```

The correct place and time to use the “multiplier” variable depends on your setup. This is the tricky part. You may apply it within the character controller or in your input code.

Please ask the developer of your character controller on how to best apply a mouse sensitivity value.

There are some errors in URP or HDRP Connections but I am not using URP or HDRP?!

UPDATE: As of version 1.9.1 this should no longer happen.


This happens if you have two render pipelines installed at the same time. There are three render pipelines: Built-In (the old standard), URP (Universal) and HDRP (High Definition).

The Settings Generator uses the installed packages information to guess which render pipeline you are using. If URP or HDRP are installed it will assume that you are actually using those.

The system tries to find out what pipeline you are using automatically. Though, if you have multiple installed it will enable the code for all of them (via `#ifdef`). This leads to duplicate code (one for each pipeline).

Please make sure you only have one render pipeline installed at once!

Possible Errors: Null References, Duplicate Connection, .. already defines a member ...



If you are NOT using URP or HDRP then please double-check in the [PackageManager](#) that these packages are NOT installed. They may have unexpected names like URP, which is named "Universal RP" in the package manager.

If you are using only the Built-In renderer then please uninstall the URP (Universal Render Pipeline) package and also uninstall the HDRP (High Definition Render Pipeline) package.


If you are using the URP (Universal Render Pipeline) then make sure you do uninstall the HDRP (High Definition Render Pipeline) package and the other way around.

Maybe also restart Unity once after uninstalling the packages . It sounds ridiculous but it sometimes helps.

EXAMPLE:


Let's assume you are not using URP but the URP classes show some errors after import.

Make sure to uninstall URP if you are using Built-In or HDRP.



If you open the file with the error in your IDE (VisualStudio) then the code should be greyed out since you are not using URP.

It should look like this:



```
1  #if KAMGAM_RENDER_PIPELINE_URP
2  using System.Collections.Generic;
3  using UnityEngine.Rendering;
4  using UnityEngine.Rendering.Universal;
5  using UnityEngine;
6
7  #if UNITY_EDITOR
8  using UnityEditor;
9  #endif
10
11 namespace Kamgam.SettingsGenerator
12 {
13     public partial class AmbientOcclusionConnection : Connection<bool>
14     {
15         /// <summary>
16         /// Using the active state has the disadvantage that the functionality is dependent
17         /// on the "disabled" shader variants. These may be stripped from builds.
18         /// If you turn this on then you should disable shader stripping under
19         /// ProjectSettings > Graphics > URP Global Settings > Shader Stripping (both "post pro" and "unused").
20         /// See: https://forum.unity.com/threads/turn-urp-ssao-on-and-off-at-runtime.1066961/#post-8613702
21         /// </summary>
```

If the code is not greyed out then you still have references to URP assemblies in your project. Find those and remove them (usually removing from the package manager is enough)

My settings work in the menu but not in the level?

There are two common reasons for this:


- A) Some third party asset is resetting the settings (maybe even every frame).
- B) You have unloaded your UI scene and you do not have set "DoNotDestroy" on the Settings Initializer and you do not use a SettingsApplier in your scene.

Please refer to the "[Combining the Settings System with other Assets](#)" section at the beginning of the manual for more details on how to fix these.


DLSS: I have a multi camera setup and the DLSS setting does only apply to the camera tagged with “MainCamera”.

The settings system assumes that usually the camera with the MainCamera tag is the one you want to configure with the settings. If you want to specify a camera without tags then you can add the “SettingsMainCameraMarker” component to a camera and enable “CheckForCameraMarker” on the connection.

Add this to your camera:



Enable Marker Search in the connection:




I can't get mouse interaction to work with the settings prefabs?

Solution: It may be that you are missing an **EventSystem** in your scene (usually by adding a new canvas one is created automatically).

The thing is that in the demo (where the UI is loaded additively) the EventSystem is in the main scene (not the UI scene). Therefore if you copy only the UI scene into your project you will have to make sure that your scene already has an EventSystem in it.

Usually people already have one but this can be easily overlooked.

Remember: For interaction with canvases you need a RayCaster on the canvas AND and active EventSystem in the scene.



I have removed a setting but it still gets applied at the start?

If you upgrade your game and you remove a setting but the player has saved the setting it may happen that this setting (since it still exists in the players saved data) will be applied. I admit this is a rather rare use-case but to make absolutely sure an old setting is never ever loaded you can use the static "Settings.AddToDeactivateBeforeInit(settingId);" API. It works like this:

```
using UnityEngine;
using Kamgam.SettingsGenerator;

[DefaultExecutionOrder(-11)]
public class DeactivationTest : MonoBehaviour
{
    public void Awake()
    {
        Settings.AddToDeactivateBeforeInit("audioEnabled");
    }
}
```

Notice the "DefaultExecutionOrder" is -11 because the static code has to run before the Initializer (which is set to order -10 by default).

NOTICE: For future versions of the asset I will change it to ignore any settings that is not in the settings asset list (as it should have been from the start). I consider this a bug and the code above is just a workaround until I get to properly fix it.

I have an asynchronous connection. How should I handle this?

I have posted an example in this discussions thread (demo code is also below in case the link does not work):

<https://discussions.unity.com/t/settings-game-options/905251/111>

One (rather brutal) solution would be to not use the initializer and don't use (initialize) the settings system at all before everything that's asynchronous is done. However, that would mean all your settings would not be applied until the async stuff is loaded (which is not very nice). I would not recommend this.

What I do recommend is to show "replacement" option labels instead of an empty list (like 10 "Loading ..." entries). Ideally the number of labels matches the final amount of options you will have. That way the settings system can already show (and experienced users can select) an option.

Within your Connection I would then cache (store in a local int) the selected value. In that regard the connection acts as if it was a synchronous connection. The settings system will be happy.

Now after loading has finished you can update the labels and apply the selected (cached) value (or ignore it, that's really up to you).

Don't forget to call `SettingsInitializer.Settings.RefreshRegisteredResolvers()`; to force update the option labels in the UI, otherwise users may have to close and reopen your settings UI to see the change.

You can also opt to only show one "Loading ..." label while it is loading but then you should also trigger a `settings.Save()` operation after the loading has finished as auto-save may have stored to value as index 0 (that's why I would recommend to pre-fill the labels with as many options as you will have in the end [or more]).

Here is the code for a demo async connection:

```
using System.Collections.Generic;
using UnityEngine;

namespace Kamgam.SettingsGenerator
{
    public class AsyncDemoConnection : ConnectionWithOptions<string>,
        IConnectionWithSettingsAccess
    {
        protected List<string> _labels;

        // The value cache for when the system is not yet initialized.
        protected int _cachedSelection = 0;

        // Flag to check if initialized.
```

```

protected bool _initialized = false;

// Reference to settings so we can use it to force an update on the concerned
resolvers.
protected Settings _settings;

// Usually this would come from your async backend but for testing this will do.
protected int _fakeBackendSystemValue = 1;

async void delayedInit()
{
    // Fake a delay of 3 seconds.
    await System.Threading.Tasks.Task.Delay(3000);

    // Update the labels with the final options.
    _labels.Clear();
    _labels.Add("Martin");
    _labels.Add("Rita");
    _labels.Add("Claus");

    // Mark as initialized (now it's ready for synchronous use).
    _initialized = true;

    // Send the cached value to the now initialized backend
    // This is where you have to decide whether you use the cache value to init
    // or the value from the backend.
    // Usually the backend is the better choice.
    // Set(_fakeBackendSystemValue);
    Set(_fakeBackendSystemValue);

    // Force an update on all the resolvers that have a settings that uses this
connection.
    _settings.RefreshRegisteredResolversWithConnection(this);
}

public override List<string> GetOptionLabels()
{
    if (_labels == null)
    {
        _labels = new List<string>();

        // Add as many (or more) options as you will have in the end.
        _labels.Add("Loading ..");
        _labels.Add("Loading ..");
        _labels.Add("Loading ..");

        delayedInit();
    }
    return _labels;
}

public override void SetOptionLabels(List<string> optionLabels)
{
    _labels = new List<string>(optionLabels);
}

public override void RefreshOptionLabels()

```

```

    {
        _labels = null;
        GetOptionLabels();
    }

    public override int Get()
    {
        if (_initialized)
            return _fakeBackendSystemValue;
        else
            return _cachedSelection;
    }

    public override void Set(int value)
    {
        if (!_initialized)
            _cachedSelection = value;
        else
            _fakeBackendSystemValue = value;

        NotifyListenersIfChanged(value);
    }

    // IConnectionWithSettingsAccess (set will be called automatically)

    public void SetSettings(Settings settings)
    {
        _settings = settings;
    }

    public Settings GetSettings()
    {
        return _settings;
    }
}
}

```

And here the SO for it:

```

using UnityEngine;

namespace Kamgam.SettingsGenerator
{
    [CreateAssetMenu(fileName = "AsyncDemoConnection", menuName =
    "SettingsGenerator/Connection/AsyncDemoConnection", order = 4)]
    public class AsyncDemoConnectionSO : OptionConnectionSO
    {
        protected AsyncDemoConnection _connection;

        public override IConnectionWithOptions<string> GetConnection()
        {
            if (_connection == null)
                Create();

            return _connection;
        }
    }
}

```

```
public void Create()
{
    _connection = new AsyncDemoConnection();
}

public override void DestroyConnection()
{
    if (_connection != null)
        _connection.Destroy();

    _connection = null;
}
}
```

I have a connection that changes the value during runtime.

Question: My connection value changes during runtime. How do I notify the setting and resolver (UI) of this change?

If the connection changes the value itself then you have to update the setting and resolver manually by calling both `PullFromConnection()` to update the setting value and `RefreshRegisteredResolversWithConnection()` to update the resolver (UI).

That's because it usually is the other way around (the resolver pushing and pulling values from the connection), so there is no automation for updating the setting if the connection changes (which usually does not happen).

The thing is, you can still do it all from within the connection. If you add the **ICollectionWithSettingsAccess** interface to your connection you will get access to the settings instance and you can query it for settings that use your connection object.

```
public void SetSettings(Settings settings)
{
    _settings = settings;
}


public Settings GetSettings()
{
    return _settings;
}

// Force an update on the setting values that use this connection.
_settings.GetSettingsWithConnection(this).PullFromConnection();

// Force an update on all the resolvers that have a setting that uses this connection.
_settings.RefreshRegisteredResolversWithConnection(this);
```

Is there a way to have buttons/keys as icons (like a green "A" button and not "buttonSouth")?

Yes, if you are using a TextMeshPro Textfield then you can do it via the localization and styles or sprites (see "Localizing Key Control Paths" section above).




You can find more info on how to create sprites in TPro here:

<https://docs.unity3d.com/Packages/com.unity.textmeshpro@4.0/manual/Sprites.html>


You may ask: How do you know what term to use in the localization?

The used binding path is visible on the InputBindingUGUI component at runtime:



How to inform users of unapplied settings?

In the "FromAsset" demo there is a Demo of the SettingsCheckForUnapplied component. You can use it to trigger actions if a settings UI is deactivated while some settings are still unapplied.



Can I use multiple connections for one setting?



Yes but only via script. There are some MultiConnectionBool/Int/... classes. They have an internal list of connections which they forward the value to.

NOTICE: Since getting the value is ambiguous (multiple connections) the first valid one will be used (or the defined DefaultConnection).

The recommendation is still to only use one connection per setting. If you want to control multiple things each should have a separate setting.


Is PlayMaker supported?

Yes but not with all functions. You can listen to setting changes and extract settings values:




How to bind to mouse wheel up or down (mouse scroll)

It is a bit tricky because the input system usually prefers "<Mouse>/scroll" over more specific paths like "<Mouse>/scroll/up" or "<Mouse>/scroll/down". That's why in the example below only "<Mouse>/scroll/up" and down are allowed but not "<Mouse>/scroll". To still allow all normal buttons you have to allow keyboard and gamepad too.




This does not require any special treatment in the input actions. You can just use a regular button for this:




I get a „Got 'Kamgam.SettingsGenerator.SettingString' but can only handle types: KeyCombination" error.

This is probably because you were trying to do InputBinding but you combine a StringSetting (which is the correct setting for input binding) with an InputKeyUGUI prefab (which are NOT for input binding, those are for the old KeyCode system).



You have to use the InputBinding prefabs for that instead. With these it will work:




I get a „error CS0311: The type .." error.

More precisely the error might be: "There is no implicit reference conversion from 'UnityEngine.Rendering.PostProcessing.ColorGrading' to 'UnityEngine.Rendering.VolumeComponent'." or similar.

This indicates that you have a mix of CoreRP (URP or HDRP) and Built-In RP PostProcessing installed. Those are not compatible because the CoreRPs come with their own included post processing ([source](#)):


If you can please check in the package manager if the "Post Processing" package is installed and if it is please uninstall it:




Once uninstalled please restart Unity and it should work again (maybe you will have to reinstall the settings asset but usually that's not necessary).

I get a "Cannot find action map 'gameplay' in actions" error in the InputSystemDemo.

Sadly this is a known bug in Unity Editor ([source](#)).



To fix it please go to the Player and assign a different (or null) action asset.




Then revert back to the original. If fixed it should show "gameplay" as the default below.



Jump works but movement does not in the InputSystemDemo.


If in your project you already have an InputActions asset (which you do in Unity 6 for example) then you will have to set the input actions demo one as the new default in order for Unity to pick up on the actions.

You can do this by clicking the “Assign” button in the actions or by changing it directly in the Input Actions settings.



There is only on quality option called “Pc”. Why?


The quality options are taken from the ProjectSettings > Quality. Starting with Unity 6 there are only two options in there by default called “Mobile” and “Pc” and only the Pc option is enabled for the Pc target. The settings system uses these options for the quality dropdown. If you want to add more please add them there and they will show up automatically in your settigs. The same is true for the shadow distance.



How to remove or deprecate old settings?

Usually if a setting has been saved it will be loaded automatically upon start even if it was removed from the settings list (loaded settings take precedence). However, if you want the


system to automatically delete settings that are no longer in the list then you can enable this in the provider details like this:




How to add a “change language” menu?

My recommendation would be to:


1) Create a "language" setting and add the language names as the options (HINT: order them the same way they are ordered in the localization).



2) Add the options button to your UI (with the new "language" id).



3) Listen for a change and then set the language according to the selected option.
Below is a class that does this for you. Notice the matching indices from step 1 are used:



```
using System.Collections;
using System.Collections.Generic;
using Kamgam.LocalizationForSettings;
using UnityEngine;
```

```

using Kamgam.SettingsGenerator;

public class LanguageChanger : MonoBehaviour
{
    public SettingsProvider SettingsProvider;
    public LocalizationProvider LocalizationProvider;

    void Start()
    {
        var langSetting = SettingsProvider.Settings.GetOption("language");
        langSetting.OnValueChanged += onLanguageChanged;
    }

    private void onLanguageChanged(int index)
    {
        // index = index of the language label in the options list.
        // If the language labels are the same order as the languages
        // in the localization then
        // we can simply use the index to set the language. Otherwise
        // we would have to map them.
        LocalizationProvider.GetLocalization().SetLanguageIndex(index);
    }
}

```

HINT 1: In this setup we did not add any localization translations for the language button the it will never be translated and thus will show each language in it's native tongue (just make sure your font does support all of them).

HINT 2: Make sure to also change the language in any other localization system you are using (swaping the font atlas for example).

HINT 3: I left initializing the language option with the current language out of this example for simplicity but you could do that in the Start() of the LanguageChanger.

```

// Init with current language.
langSetting.SetValue(LocalizationProvider.GetLocalization().GetLanguageIndex());

```

PlayerInput: Input rebinding works only partially or not at all after (re)starting the game. Why?

TLDR: Do not use multiple PlayerInput components unless you do make a local multiplayer game (see manual above for more infos on that).

NOTICE: Since version 1.73 of the settings asset it will take care of this automatically by applying the bindings to all instances of the input action asset. In older version you had to manually notify the settings system via the

```
Provider.Settings.SetInputActionAsset(actionAssetForPlayer);
```

method.

Please check out the InputBinding Caveats section in the manual above for more details.

I need to initialize the settings late (not automatically)

TLDR: Use the DisableAutoInitialization on the provider.

Assets like the AdvancedSceneManager may load an empty scene at the very start and not all of your prefabs (like MasterAudio) may be present at that time. Since the settings loads automatically with the first scene it may cause problems. To work around this you can enable the "DisableAutoInitialization" option in the CreatorWindow > ProviderDetails. If you disable it then the settings will initialize if you place a SettingsInitializer prefab in your scene OR once any settings UI is shown for the first time.