JUPITER

# Jupiter Io

## Route your program feed to multiple Zoom rooms.

One central distribution point for your live program.
Independent picture and audio controls for every destination.

## How it works

Send your approved program into Io. Each satellite joins a destination Zoom meeting and delivers that same program as a camera or screen share, with audio controlled separately.




### A satellite is a destination participant

It is not another source feed. A saved satellite profile holds the destination meeting, passcode, display name, and output mode. Hosts still control admission and sharing permissions.

**Open Io:** app.jupiter.events/admin/jupiter-io

01 / SOURCE SETUP

# Bring your program into Io

Start with a clean picture and a working audio feed in your encoder.

1

## Prepare the source

For a hardware production: ATEM or another switcher → capture device → OBS or Telescope. Check the complete program picture and sound before sending.

2

## Allow the encoder and copy destination

Open **Manage ingest** on the encoder computer. Choose **Use this computer's public IP**, then **Allow encoder IP** and confirm. Mac/Windows lookup commands are below the field. Choose **Copy connection**; keep its secret URL private.

3

## Configure the encoder

In OBS: **Settings → Stream → Custom**. Paste the copied URL into **Server** and leave **Stream Key** blank. Follow Io's saved **Encoder setup** guidance. In Telescope, use the URL as the send destination.

4

## Start receiving, then send

Choose **Start receiving** in Io. Then start streaming in OBS or sending in Telescope. Stop the old encoder before switching computers. Repeat the IP step on the new computer.

5

## Confirm incoming media

Check Io's video and audio indicators. **Take snapshot** checks the incoming program only; the audio meter indicates program input levels. Confirm final playback in the destination Zoom meeting.

### Using a Zoom meeting as the source?

The alternate Zoom-source path requires the source host to admit Io Source and grant SDK recording permission for raw media access. The HDMI/SRT path does not require that source-meeting permission.

02 / SATELLITE SETUP

# Send to your Zoom rooms

Create a destination profile, join the meeting, then enable the program output.

1

### Create or edit a profile

Click **Add satellite** for one new profile. Use **Quantity to add** for several. Save a name, Zoom meeting ID, passcode, and output mode. **Edit satellite** changes an existing profile.

2

### Choose the right picture path

Use **Screen share** for presentations; the host must allow sharing. Use **Camera** for participant video. Delivered quality depends on Zoom and destination settings.

3

### Connect and check admission

Click **Connect**. A satellite may wait for the meeting host or for admission from a waiting room. Confirm the actual state before treating it as connected.

4

### Enable picture and audio independently

Turn on **Share** or **Camera**, then unmute program audio. New satellites start with picture and audio off. Reconnecting retains saved controls. **Original Sound** does not unmute audio.

5

### Verify in the destination meeting

Check picture, framing, sharing permission, and sound in Zoom. A successful Io connection or input snapshot alone does not prove what attendees see or hear.

### Editing and cleanup

Disconnect before changing a meeting, passcode, or output mode. Connected satellites can still be renamed. A blank existing passcode keeps the saved one. **Delete satellite** is available after stopping and asks for confirmation.

03 / LIVE OPERATION

# See the route. Check the room.

Use the matrix for selection and the destination meeting for final confidence.




Example routing

**Matrix controls**

Green + solid link:
connected

Dim red + dashed link:
not connected

Cyan outline:
selected for an action

**Expand satellite view** opens the orbital map. Click a satellite, drag a connector from Io, or drag on empty space to lasso several. Then click **Connect selected** or **Disconnect selected**. Dragging alone does not change connections.

## If something is not working

| | |
|---|---|
| **Waiting for host** | Start the destination meeting, or check its join-before-host and waiting-room settings. |
| **Connected, no picture** | Check source video, Share/Camera state, and the destination host's sharing permissions. |
| **No sound** | Check encoder audio, program input levels, and the satellite microphone. The current relay is mono. |
| **Failed or stale** | Open Failure report for the reported reason and last update. Disconnect before retrying; repeated failures need controller investigation. |

**Finish safely:** Disconnect destination satellites, stop the encoder, then stop receiving in Io. Up to 50 profiles can be configured; practical concurrent capacity depends on the deployment. Zoom permissions and delivered quality still apply.