



Cisco UCS Director Installation on VMware vSphere, Release 6.0

First Published: 2016-09-16

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <http://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

© 2016 Cisco Systems, Inc. All rights reserved.



CONTENTS

Preface

Preface v

Audience v

Conventions v

Related Documentation vii

Documentation Feedback vii

Obtaining Documentation and Submitting a Service Request vii

CHAPTER 1

Overview 1

Cisco UCS Director 1

Features and Benefits 2

Physical and Virtual Management Features 4

POODLE Vulnerability 5

Cisco UCS Director for VMware vSphere 5

Prerequisites 5

Minimum System Requirements for a Single-Node Setup 5

About Licenses 7

Fulfilling the Product Access Key 8

Upgrading a Single Node 8

CHAPTER 2

Installing Cisco UCS Director 9

Installing Cisco UCS Director on VMware vSphere 9

Configuring the Network Interface using Shelladmin 11

Changing the Default Password 12

Updating the License 12

Reserving System Resources 13

Changing the Maximum Packet Size 13

CHAPTER 3

Restarting Cisco UCS Director 15

Restarting Cisco UCS Director 15

APPENDIX A

Ports 17

Cisco UCS Director TCP and UDP Port Usage 17

Port List 18

Multi-Node Port Requirements 20



Preface

- [Audience, page v](#)
- [Conventions, page v](#)
- [Related Documentation, page vii](#)
- [Documentation Feedback, page vii](#)
- [Obtaining Documentation and Submitting a Service Request, page vii](#)

Audience

This guide is intended primarily for data center administrators who use Cisco UCS Director and who have responsibilities and expertise in one or more of the following:

- Server administration
- Storage administration
- Network administration
- Network security
- Virtualization and virtual machines

Conventions

Text Type	Indication
GUI elements	GUI elements such as tab titles, area names, and field labels appear in this font . Main titles such as window, dialog box, and wizard titles appear in this font .
Document titles	Document titles appear in <i>this font</i> .
TUI elements	In a Text-based User Interface, text the system displays appears in <code>this font</code> .

Text Type	Indication
System output	Terminal sessions and information that the system displays appear in <i>this font</i> .
CLI commands	CLI command keywords appear in this font . Variables in a CLI command appear in <i>this font</i> .
[]	Elements in square brackets are optional.
{x y z}	Required alternative keywords are grouped in braces and separated by vertical bars.
[x y z]	Optional alternative keywords are grouped in brackets and separated by vertical bars.
string	A nonquoted set of characters. Do not use quotation marks around the string or the string will include the quotation marks.
< >	Nonprinting characters such as passwords are in angle brackets.
[]	Default responses to system prompts are in square brackets.
!, #	An exclamation point (!) or a pound sign (#) at the beginning of a line of code indicates a comment line.

**Note**

Means *reader take note*. Notes contain helpful suggestions or references to material not covered in the document.

**Caution**

Means *reader be careful*. In this situation, you might perform an action that could result in equipment damage or loss of data.

**Tip**

Means *the following information will help you solve a problem*. The tips information might not be troubleshooting or even an action, but could be useful information, similar to a Timesaver.

**Timesaver**

Means *the described action saves time*. You can save time by performing the action described in the paragraph.

**Warning****IMPORTANT SAFETY INSTRUCTIONS**

This warning symbol means danger. You are in a situation that could cause bodily injury. Before you work on any equipment, be aware of the hazards involved with electrical circuitry and be familiar with standard practices for preventing accidents. Use the statement number provided at the end of each warning to locate its translation in the translated safety warnings that accompanied this device.

SAVE THESE INSTRUCTIONS

Related Documentation

Cisco UCS Director Documentation Roadmap

For a complete list of Cisco UCS Director documentation, see the *Cisco UCS Director Documentation Roadmap* available at the following URL: http://www.cisco.com/en/US/docs/unified_computing/ucs/ucs-director/doc-roadmap/b_UCSDirectorDocRoadmap.html.

Cisco UCS Documentation Roadmaps

For a complete list of all B-Series documentation, see the *Cisco UCS B-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/b-series-doc>.

For a complete list of all C-Series documentation, see the *Cisco UCS C-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/c-series-doc>.

**Note**

The *Cisco UCS B-Series Servers Documentation Roadmap* includes links to documentation for Cisco UCS Manager and Cisco UCS Central. The *Cisco UCS C-Series Servers Documentation Roadmap* includes links to documentation for Cisco Integrated Management Controller.

Documentation Feedback

To provide technical feedback on this document, or to report an error or omission, please send your comments to ucs-director-docfeedback@cisco.com. We appreciate your feedback.

Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, using the Cisco Bug Search Tool (BST), submitting a service request, and gathering additional information, see [What's New in Cisco Product Documentation](#).

To receive new and revised Cisco technical content directly to your desktop, you can subscribe to the [What's New in Cisco Product Documentation RSS feed](#). RSS feeds are a free service.



Overview

This chapter contains the following sections:

- [Cisco UCS Director, page 1](#)
- [Cisco UCS Director for VMware vSphere, page 5](#)
- [Prerequisites, page 5](#)
- [Minimum System Requirements for a Single-Node Setup, page 5](#)
- [About Licenses, page 7](#)
- [Upgrading a Single Node, page 8](#)

Cisco UCS Director

Cisco UCS Director is a complete, highly secure, end-to-end management, orchestration, and automation solution for a wide array of Cisco and non-Cisco data infrastructure components, and for the industry's leading converged infrastructure solutions based on the Cisco UCS and Cisco Nexus platforms. For a complete list of supported infrastructure components and solutions, see the [Cisco UCS Director Compatibility Matrix](#).

Cisco UCS Director is a 64-bit appliance that uses the following standard templates:

- Open Virtualization Format (OVF) for VMware vSphere
- Virtual Hard Disk (VHD) for Microsoft Hyper-V

Management through Cisco UCS Director

Cisco UCS Director extends the unification of computing and network layers through Cisco UCS to provide you with comprehensive visibility and management of your data center infrastructure components. You can use Cisco UCS Director to configure, administer, and monitor supported Cisco and non-Cisco components. The tasks you can perform include the following:

- Create, clone, and deploy service profiles and templates for all Cisco UCS servers and compute applications.

- Monitor organizational usage, trends, and capacity across a converged infrastructure on a continuous basis. For example, you can view heat maps that show virtual machine (VM) utilization across all your data centers.
- Deploy and add capacity to converged infrastructures in a consistent, repeatable manner.
- Manage, monitor, and report on data center components, such as Cisco UCS domains or Cisco Nexus network devices.
- Extend virtual service catalogs to include services for your physical infrastructure.
- Manage secure multi-tenant environments to accommodate virtualized workloads that run with non-virtualized workloads.

Automation and Orchestration with Cisco UCS Director

Cisco UCS Director enables you to build workflows that provide automation services, and to publish the workflows and extend their services to your users on demand. You can collaborate with other experts in your company to quickly and easily create policies. You can build Cisco UCS Director workflows to automate simple or complex provisioning and configuration processes.

Once built and validated, these workflows perform the same way every time, no matter who runs the workflows. An experienced data center administrator can run them, or you can implement role-based access control to enable your users and customers to run the workflows on a self-service, as needed, basis.

With Cisco UCS Director, you can automate a wide array of tasks and use cases across a wide variety of supported Cisco and non-Cisco hardware and software data center components. A few examples of the use cases that you can automate include, but are not limited to:

- VM provisioning and lifecycle management
- Network resource configuration and lifecycle management
- Storage resource configuration and lifecycle management
- Tenant onboarding and infrastructure configuration
- Application infrastructure provisioning
- Self-service catalogs and VM provisioning
- Bare metal server provisioning, including installation of an operating system

Features and Benefits

The features and benefits of Cisco UCS Director are as follows:

Feature	Benefit
Central management	• Provides a single interface for administrators to monitor, provision, and manage the system across physical, virtual, and bare metal environments • Provides unified dashboards, reports, and heat maps, which reduce troubleshooting and performance bottlenecks

Feature	Benefit
Self-service catalog	• Allows end users to order and deploy new infrastructure instances following IT-prescribed policies and governance
Adaptive provisioning	• Provides a real-time available capability, internal policies, and application workload requirements to optimize the availability of your resources
Dynamic capacity management	• Provides continuous monitoring that indicates real-time infrastructure consumption to improve capacity planning and management • Identifies underutilized and overutilized resources
Multiple hypervisor support	• Supports VMware ESX, ESXi, Microsoft Hyper-V, and Red Hat hypervisors
Computing management	• Monitors, manages, and provisions physical, virtual, and bare metal servers, as well as blades • Allows end users to implement virtual machine life-cycle management and business continuance through snapshots • Allows administrators to access server utilization trending analysis
Network management	• Provides policy-based provisioning of physical and virtual switches and dynamic network topologies • Allows administrators to configure VLANs, virtual network interface cards (vNICs), port groups and port profiles, IP and Dynamic Host Control Protocol (DHCP) allocation, and access control lists (ACLs) across network devices
Storage management	• Provides policy-based provisioning and management of filers, virtual filers (vFilers), logical unit numbers (LUNs), and volumes • Provides unified dashboards that allow administrators comprehensive visibility into organizational usage, trends, and capacity analysis details.

Physical and Virtual Management Features

Physical Server Management • Discover and collect configurations and changes • Monitor and manage physical servers • Perform policy-based server provisioning • Manage blade power • Manage the server life cycle • Perform server use trending and capacity analysis • Perform bare metal provisioning using preboot execution environment (PXE) boot management	Virtual Computing Management • Discover, collect, and monitor virtual computing environments • Perform policy-based provisioning and dynamic resource allocation • Manage the host server load and power • Manage the VM life cycle and snapshots • Perform analytics to assess VM capacity, sprawl, and host utilization
Physical Storage Management • Discover, collect, and monitor storage filers • Perform policy-based provisioning of vFilers • Provision and map volumes • Create and map Logical Unit Number (LUN) and iGroup instances • Perform SAN zone management • Monitor and manage network-attached storage (NAS) and SAN-based storage • Implement storage best practices and recommendation	Virtual Storage Management • Discover, collect, and monitor storage of vFilers and storage pools • Perform policy-based storage provisioning for thick and thin clients • Create new datastores and map them to virtual device contexts (VDCs) • Add and resize disks to VMs • Monitor and manage organizational storage use • Perform virtual storage trend and capacity analysis
Physical Network Management • Discover, collect, and monitor physical network elements • Provision VLANs across multiple switches • Configure Access Control Lists (ACLs) on network devices • Configure the storage network • Implement dynamic network topologies	Virtual Network Management • Add networks to VMs • Perform policy-based provisioning with IP and DHCP allocation • Configure and connect Virtual Network Interface Cards (vNICs) to VLANs and private VLANs • Create port groups and port profiles for VMs • Monitor organizational use of virtual networks

POODLE Vulnerability

To avoid POODLE vulnerability, SSL Version 2 and SSL Version 3 are disabled on Cisco UCS Director north-bound HTTP interface by configuring Apache Tomcat to allow only TLS . Hence, any north-bound applications accessing Cisco UCS Director through REST API will be connected through TLS. Also, the browsers will be connected to Cisco UCS Director through TLS. For more information, refer <http://tools.cisco.com/security/center/content/CiscoSecurityAdvisory/cisco-sa-20141015-poodle>.

Cisco UCS Director for VMware vSphere

Cisco UCS Director can be hosted on VMware vSphere or vCenter as well as HyperV Manager.

**Note**

The appliance and boot-up logs are located in the `/var/log/ucsd` directory.

- `install.log` contains the one time appliance installation logs.
- `bootup.log` contains the appliance boot-up sequence information, such as startup messages for the database and infrastructure services.

Prerequisites

- Installation of VMware vSphere or vCenter
- Configure a user account with system administrator privileges on VMware vCenter
- Cisco UCS Director deployed on a VMware vSphere host

Minimum System Requirements for a Single-Node Setup

The minimum system requirements depend on the number of VMs you plan to manage. We recommend deploying a Cisco UCS Director VM on a local datastore with a minimum of 25 MBps I/O speed, or on an external datastore with a minimum of 50 MBps I/O speed.

**Note**

- For optimal performance, reserve additional CPU and memory resources. We recommend that you reserve the following resources in addition to the minimum system requirements listed in the tables below: CPU resources of more than or equal to 3000MHz, and memory reservation of more than or equal to 4GB. You should add more vCPUs if the Cisco UCS Director VM's CPU usage is consistently high.
- The minimum memory required for the infrmgr service is automatically set during deployment. However, if you want to modify the memory for the infrmgr service, edit the infrmgr.env file available in the following location:

/opt/infra/bin/inframgr.env

In this file, update the "MEMORY_MAX" parameter to the value you want. After changing this parameter, restart the service for the changes to take effect. The default memory settings are MEMORY_MIN=128m and MEMORY_MAX=6144m.

For information about minimum system requirements for a multi-node setup, see the [Cisco UCS Director Multi-Node Installation and Configuration Guide](#).

Up to 2,000 VMs

If you plan to manage up to 2,000 VMs, the Cisco UCS Director environment must meet at least the minimum system requirements in the following table.

Table 1: Minimum System Requirements for up to 2,000 VMs

Element	Minimum Supported Requirement
vCPU	4
Memory	12 GB
Hard Disk	100 GB

Up to 5,000 VMs

If you plan to manage no more than 5,000 VMs, the Cisco UCS Director environment must meet at least the minimum system requirements and recommended configurations in the following tables.

Table 2: Minimum System Requirements for up to 5,000 VMs

Element	Minimum Supported Requirement
vCPU	8
Memory	20 GB
Hard Disk	100 GB

Table 3: Minimum Database Configuration

Element	Minimum Supported Configuration
thread_cache_size	100
max_connections	1000
innodb_lock_wait_timeout	100
query_cache_size	128 MB
innodb_buffer_pool_size	4096 MB
max_connect_errors	10000
connect_timeout	20
innodb_read_io_threads	64
innodb_write_io_threads	64

About Licenses

You must obtain a license to use Cisco UCS Director, as follows:

- 1 Before you install Cisco UCS Director, generate the Cisco UCS Director license key and claim a certificate (Product Access Key).
- 2 Register the Product Access Key (PAK) on the Cisco software license site, as described in [Fulfilling the Product Access Key](#), on page 8.
- 3 After you install Cisco UCS Director, update the license in Cisco UCS Director as described in [Updating the License](#), on page 12.
- 4 After the license has been validated, you can start to use Cisco UCS Director.

Fulfilling the Product Access Key

Before You Begin

You need the PAK number.

-
- Step 1** Navigate to the [Cisco Software License website](#).
- Step 2** If you are directed to the Product License Registration page, you can take the training or click **Continue to Product License Registration**.
- Step 3** On the Product License Registration page, click **Get New Licenses from a PAK or Token**.
- Step 4** In the **Enter a Single PAK or TOKEN to Fulfill** field, enter the PAK number.
- Step 5** Click **Fulfill Single PAK/TOKEN**.
- Step 6** Complete the additional fields in **License Information** to register your PAK:

Name	Description
Organization Name	The organization name.
Site Contact Name	The site contact name.
Street Address	The street address of the organization.
City or Town	The city or town.
State or Province	The state or province.
Zip or Postal Code	The zip code or postal code.
Country	The country name.

- Step 7** Click **Issue Key**.
The features for your license appear, and you receive an email with the Digital License Agreement and a zipped license file.
-

Upgrading a Single Node

For more information on upgrading see [Cisco UCS Director Upgrade Guide, Release 6.0](#).



Installing Cisco UCS Director

This chapter contains the following sections:

- [Installing Cisco UCS Director on VMware vSphere, page 9](#)
- [Configuring the Network Interface using Shelladmin, page 11](#)
- [Changing the Default Password, page 12](#)
- [Updating the License, page 12](#)
- [Reserving System Resources, page 13](#)
- [Changing the Maximum Packet Size, page 13](#)

Installing Cisco UCS Director on VMware vSphere



Note

We recommend that you use VMware vCenter for OVF deployment. VMware vCenter versions 5.x and above are supported. OVF deployment wizards support only IPv4 addresses. If you require IPv6, you can deploy OVF and use the shelladmin option to configure IPv6 address.

Before You Begin

You need administrator privileges to connect to VMware vCenter. Cisco UCS Director requires a user account with system administrator privileges to discover, manage and automate VMware vCenter configuration from Cisco UCS Director. These operations include creating, deleting and modifying VMs, ESXi hosts and clusters, datastores and datastore clusters, standard and DV switches, and virtual network port groups.

**Note**

If you do not want to use DHCP, you need the following information: IPv4 address, subnet mask, and default gateway.

-
- Step 1** Log in to VMware vSphere Client.
- Step 2** In the **Navigation** pane, choose the **Data Center** for Cisco UCS Director deployment.
- Step 3** Choose **File > Deploy OVF Template**.
The **Deploy OVF Template** window appears.
- Step 4** In the **Source** pane, do one of the following to choose your OVF source location:
- Browse to the location, choose the file, and click **Open**.
 - Deploy from a URL on your local area network. Replace *FQDN* (Fully Qualified Domain Name) with the IP address or domain name, and click **Next**.
- Step 5** In the **OVF Template Details** pane, verify the details, and click **Next**.
- Step 6** In the **End User License Agreement** pane, read the license agreement, and click **Accept**. Click **Next**.
- Step 7** In the **Name and Location** pane, do the following:
- a) (Optional) In the **Name** field, edit the VM name.
 - b) From the **Inventory Location** area, choose the inventory location where Cisco UCS Director is being deployed, and click **Next**.
- Note** If Data Center was chosen in a previous step, option b is not available.
- Step 8** In the **Host/Cluster** pane, choose the required host, cluster, or resource pool, and click **Next**.
- Step 9** In the **Storage** pane, choose the location to store Cisco UCS Director VM files, and click **Next**.
- Step 10** In the **Disk Format** pane, choose one of the following radio buttons and click **Next**:
- **Thick Provisioned (Lazy Zeroed)** format—To allocate storage immediately in thick format. This is the recommended option.
 - **Thick Provisioned (Eager Zeroed)** format—To allocate storage in thick format. It might take longer to create disks using this option.
 - **Thin Provisioned** format—To allocate storage on demand as data is written to disk.
- Step 11** In the **Network Mapping** pane, choose your network and click **Next**.
- Step 12** In the **Properties** pane, enter the following information and click **Next**:
- Root Password
 - Shelladmin Password
 - Management IP Address
 - Management IP Subnet Mask
 - Gateway IP Address

Note If the root password and shell admin password are not configured, default values are used.

The management IP address and management IP subnet mask are set to 0.0.0.0 to use DHCP by default.

Step 13 In the **Ready to Complete** pane, verify the options selected, and click **Finish**.

Step 14 Make sure you have sufficient vCPU and memory to power on the VM.

Step 15 Power on the VM.

Note If the **Power on after deployment** check box on the **Ready to Complete** pane is checked, the appliance powers on automatically after deployment.

Step 16 After the appliance has booted up, transfer the Cisco UCS Director IP address (from the IP address that is shown) into a supported web browser to access the **Login** page.

Step 17 On the **Login** page, enter `admin` as the username and `admin` for the login password.

Note Change your admin password after this initial login.

Step 18 On the menu bar, choose **Administration > License** and click the **License Keys** tab.

Step 19 Click **Manage Personalities**.

Step 20 In the **Personality Configuration** dialog box, check the check box for the required personalities. You can check either **UCSD** or **Big Data** or both personalities if required.

Step 21 Click **Submit**.

Configuring the Network Interface using Shelladmin

This procedure is optional.

Step 1 Log in to the Cisco UCS Director VM console with the following credentials:

- a) User—shelladmin
- b) Password—changeme

If you have already logged into the shelladmin and changed the default password, use your new password instead.

After you have logged in, you can choose `Change shelladmin password` to change the default password.

Step 2 Choose `Configure Network Interface`.

Step 3 At the `Do you want to Configure DHCP/STATIC IP [D/S]` prompt, enter one of the following choices:

- If DHCP is enabled, enter `D` (IP addresses are assigned automatically)
- To configure static IP, enter `S`, and then choose the interface you want to configure at the next prompt followed by the option to select IPv4 or IPv6. This is followed by the confirmation of the interface selected and the version of IP for which you select `Y` to continue. Then enter the following details:
 - IP address
 - Netmask
 - Gateway

- DNS Server 1
- DNS Server 2

Step 4 Confirm when prompted.

Changing the Default Password

Change the default password for administration after initial logging.

-
- Step 1** On the menu bar, choose **Administration > Users and Groups**.
- Step 2** Click the **Users** tab.
- Step 3** Choose the administration user for which you want to change the default password.
- Step 4** Click **Change Password**.
- Step 5** In the **Change Password** dialog box, enter the new password and confirm it.
- Step 6** Click **Save**.
-

Updating the License

Before You Begin

If you received a zipped license file by an email, extract and save the license (.lic) file to your local machine.

-
- Step 1** Choose **Administration > License**.
- Step 2** Click the **License Keys** tab.
- Step 3** Click **Update License**.
- Step 4** In the **Update License** dialog box, do the following:
- To upload a .lic file, click **Browse** to the base license's file and select the .lic file, then click **Upload**.
- Step 5** Click **Submit**.
The license file is processed, and a message appears confirming the successful update.
-

Reserving System Resources

For optimal performance, we recommend reserving extra system resources for Cisco UCS Director beyond the minimum system requirements listed in [Minimum System Requirements for a Single-Node Setup](#), on [page 5](#).



Note For more information about how to reserve system resources, see the VMWare documentation.

-
- Step 1** Log in to VMware vCenter.
 - Step 2** Choose the VM for Cisco UCS Director.
 - Step 3** Shut down the VM.
 - Step 4** In VMware vCenter, click the **Resource Allocation** tab to view the current resource allocations, and click **Edit**.
 - Step 5** In the **Virtual Machine Properties** pane, edit resource allocations by choosing a resource and entering the new values.
 - Step 6** Verify that the new resource allocations have been made.
-

Changing the Maximum Packet Size

The default maximum packet (query) size for the Cisco UCS Director database queries is 4 MB. If one or more of your pods requires a larger size, we recommend that you increase the configuration of the maximum packet size to 100 MB. For example, the import of large open automation modules typically requires a larger packet size.



Note For a multi-node setup, perform this configuration on the inventory database and monitoring database nodes.

-
- Step 1** In the shelladmin, choose `Login as Root` to log in to Cisco UCS Director.
 - Step 2** Navigate to the `/etc` folder.
 - Step 3** Open the `my.cnf` file and locate the `max_allowed_packet` parameter.
 - Step 4** Change the value of the `max_allowed_packet` parameter to `max_allowed_packet=100M`
 - Step 5** Save the `my.cnf` file.
 - Step 6** In the shelladmin, stop and restart the Cisco UCS Director services on every node, as follows:
 - a) Choose `Stop services`.
 - b) To verify that all services are stopped, choose `Display services status`.
 - c) After all services have stopped on the node, choose `Start services`.
-



Restarting Cisco UCS Director

This chapter contains the following sections:

- [Restarting Cisco UCS Director, page 15](#)

Restarting Cisco UCS Director

If you see errors after installing Cisco UCS Director, log in to the Secure Shell (SSH) client and run scripts to verify whether services are running or not.

Step 1 Using the Cisco UCS Director IP address, log in with the following credentials:

- a) User—shelladmin
- b) Password—changeme

If you have already logged into the shell admin and changed the default password, use your new password instead.

After you have logged in, you can choose `Change shelladmin password` to change the default password.

Step 2 To display the status of all services, choose `Display services status`.
If this option is not available, you can use SSH to restart the services.

Step 3 Verify that the following services appear:

1. broker
2. controller
3. eventmgr
4. idaccessmgr
5. inframgr
6. websock
7. tomcat
8. flashpolicyd
9. mysqld
10. infradb

Note Services that start in the background do not appear in the window.

- Step 4** Choose `Stop` services.
- Step 5** To verify that all services are stopped, choose `Display services status`.
- Step 6** To restart services, choose `Start services`.
-



Ports

This appendix contains the following sections:


- [Cisco UCS Director TCP and UDP Port Usage, page 17](#)
- [Port List, page 18](#)
- [Multi-Node Port Requirements, page 20](#)

Cisco UCS Director TCP and UDP Port Usage

This section provides a list of the TCP and UDP ports that Cisco UCS Director uses for connections and communications with external applications or devices.

The following figure shows the network ports used for communication between the Cisco UCS Director appliance and managed devices, ESX servers, Bare Metal Agent, PowerShell Agent, NTP, and Active Directory.

Figure 1: Cisco UCS Director TCP and UDP Port Usage



Port List

Default Port	Protocol	Description
22	TCP	SSH
80	TCP/UDP	HTTP
443	UDP	HTTPS
27000/7279/8082 (Mgmt)	TCP	Citrix licensing
2598/1494/2112/2513	TCP	Virtual Desktop Agent for Desktops
67/68	UDP	DHCP
389/636 3268/3269	TCP/UDP TCP	Active Directory
53	TCP/UDP	DNS
123	TCP/UDP	NTP
3306	TCP/UDP	MySQL

Default Port	Protocol	Description
8787/5900-5964	TCP	Cisco UCS Director + VNC Connectivity
3389	TCP/UDP	Cisco UCS Director + RDP Connectivity
80/443/8080	TCP/UDP	Cisco UCS Director + NetApp Connectivity
80/443	UDP	Cisco UCS Director + Cisco UCS Manager Connectivity
80/443	UDP	Cisco UCS Director + vCenter Connectivity
3389	TCP/UDP	RDP
135/445	TCP	SMB/RPC
88	TCP/UDP	Kerberos
137	TCP/UDP	NetBIOS Name (nbname)
138	TCP/UDP	NetBIOS datagram (nbdatagram)
139	TCP	NetBIOS session (nbsession)
80/443	UDP	Desktop Delivery Controller <--> vCenter
8080 through ICA	TCP	Desktop Delivery Controller <--> Virtual Desktops
1494/2598/2512/2513	TCP	Users (Citrix Recvr) <--> Virtual Desktops
389/636 (LDAP Ports)	TCP/UDP	Desktop Delivery Controller <--> Active Directory
389/636, 3268/3269, 53	TCP/UDP	Virtual Desktops <--> Active Directory + DNS
5985/5986	TCP	PowerShell Agent <--> XenDesktop through WinRM
43891	TCP/UDP	Cisco UCS Director <--> PowerShell Agent
80/8081	TCP	XenApp
902	TCP	VMwareESXi host management and VM customization and to execute VIX tasks
903	TCP	VMwareESXi host management and VM customization and to execute VIX tasks (for VMware vCenter releases prior to 5.0)
9443	TCP	VMware vSphere Web Client HTTPS (to access HTML5 based VM console in vCenter 6.0 and above)

Default Port	Protocol	Description
7343	TCP	VMware vSphere Web Client - HTML5 Remote Console, HTTPS (vCenter 5.5 Update 2 and later)

Multi-Node Port Requirements

The ports listed in [Cisco UCS Director TCP and UDP Port Usage, on page 17](#) are applicable for both single and multi-node setups.

For a multi-node setup, the following ports need to be opened between the nodes:

- From the primary and service node(s) to database nodes: port 3306
- From the primary node to service node(s): ports 80 and 443