Q Search

Installation methods 安装方法

Standalone installer

独立安装程序

Homebrew 自制

Docker 码头工人

Upgrading uv 升级紫外线

Shell autocompletion

Uninstallation 卸载

Next steps 后续步骤

WinGet WinGet (温格)

GitHub Releases GitHub 发布

PyPI PyPI的

Scoop 舀

Cargo 负责

Shell 自动补全

Introduction 介绍 Getting started 开始 Installation 安装 First steps 第一步 Features 特征 Getting help 获取帮助 Guides 指南 Installing Python 安装 Python Running scripts 运行脚本 Using tools 使用工具 Working on projects 从事项目 Publishing packages 发布包 Migration 迁移 > Integrations 集成 > Concepts 概念 Projects 项目

uv

Tools 工具 Python versions Python 版本 Configuration files 配置文件 Package indexes 包索引 Resolution 分辨率 Build backend 构建后端 Authentication 认证 Caching 缓存 Preview features 预览功能 The pip interface pip 接口 >

Reference 参考

Installing uv 安装 uv

Getting started 开始

Installation methods 安装方法

Install uv with our standalone installers or your package manager of choice. 使用我们的独立安装程序或您选择的包管理器安装 uv。

Standalone installer 独立安装程序

uv provides a standalone installer to download and install uv:

macOS and Linux macOS 和 Linux Windows 窗户

UV 提供了一个独立的安装程序来下载和安装 UV:

Use curl to download the script and execute it with sh: 使用 curl 下载脚本并使用 sh 执行:

\$ curl -LsSf https://astral.sh/uv/install.sh | sh

If your system doesn't have curl, you can use wget:

如果你的系统没有 curl, 你可以使用 wget:

Request a specific version by including it in the URL:

\$ wget -q0- https://astral.sh/uv/install.sh | sh

通过在 URL 中包含特定版本来请求特定版本:

\$ curl -LsSf https://astral.sh/uv/0.8.4/install.sh | sh

🔥 Tip 提示 The installation script may be inspected before use: 使用前可以检查安装脚本: macOS and Linux macOS 和 Linux Windows 窗户 \$ curl -LsSf https://astral.sh/uv/install.sh | less Alternatively, the installer or binaries can be downloaded directly from GitHub. 或者,可以直接从 GitHub 下载安装程序或二进制文件。

See the reference documentation on the installer for details on customizing your uv installation. 有关自定义 uv 安装的详细信息,请参阅安装程序上的参考文档。

PyPI PyPI的

For convenience, uv is published to PyPI.

为方便起见,uv 发布到 PyPI。

If installing from PyPI, we recommend installing uv into an isolated environment, e.g., with pipx: 如果从 PyPI 安装,我们建议将 uv 安装到隔离环境中,例如使用 pipx:

\$ pipx install uv

However, pip can also be used: 但是,pip 也可以用于:

\$ pip install uv

Homebrew 自制

✓ Note 注意

uv ships with prebuilt distributions (wheels) for many platforms; if a wheel is not available for a given platform, uv will be built from source, which requires a Rust toolchain. See the contributing setup guide for details on building uv

from source. UV 附带了适用于许多平台的预构建发行版(轮子);如果给定的轮子不可用 平台,uv 将从源代码构建,这需要一个 Rust 工具链。请参阅 贡献设置指南 有关从源代码构建 UV 的详细信息。

uv 在核心 Homebrew 包中可用。

uv is available in the core Homebrew packages.

\$ winget install --id=astral-sh.uv -e

WinGet WinGet (温格)

uv is available via WinGet.

\$ brew install uv

uv 可通过 WinGet 获得。

Scoop 舀

uv is available via Scoop.

uv 可通过 Scoop 获得。

\$ scoop install main/uv

Docker 码头工人

uv provides a Docker image at ghcr.io/astral-sh/uv. uv 在 ghcr.io/astral-sh/uv。

See our guide on using uv in Docker for more details. 有关更多详细信息,请参阅我们在 Docker 中使用 uv 的指南。

GitHub Releases GitHub 发布 uv release artifacts can be downloaded directly from GitHub Releases.

UV 释放伪影可直接从 GitHub 发布。

the standalone installer via github.com instead of astral.sh.

每个发布页面都包含所有受支持平台的二进制文件,以及通过 github.com 而不是 astral.sh 使 用独立安装程序的说明。

Each release page includes binaries for all supported platforms as well as instructions for using

Cargo 负责

uv is available via Cargo, but must be built from Git rather than crates.io due to its dependency on

unpublished crates. uv 可通过 Cargo 获得,但由于它依赖于未发布的 crate,因此必须从 Git 而不是 crates.io 构建。

✓ Note 注意

\$ cargo install --git https://github.com/astral-sh/uv uv

This method builds uv from source, which requires a compatible Rust toolchain.

此方法从源代码构建 uv,这需要兼容的 Rust 工具链。

当 uv 通过独立安装程序安装时,它可以按需更新:

Upgrading uv 升级紫外线

\$ uv self update

UV_NO_MODIFY_PATH=1.

★ Tip 提示 Updating uv will re-run the installer and can modify your shell profiles. To disable this behavior, set

When uv is installed via the standalone installer, it can update itself on-demand:

When another installation method is used, self-updates are disabled. Use the package manager's upgrade method instead. For example, with pip:

更新 uv 将重新运行安装程序,并可以修改您的 shell 配置文件。若要禁用此行为,请设置 UV_NO_MODIFY_PATH=1。

使用其他安装方法时,将禁用自我更新。请改用包管理器的升级方法。例如,使用 pip: \$ pip install --upgrade uv

Shell autocompletion Shell 自动补全 ◆ Tip 提示

You can run echo \$SHELL to help you determine your shell. 您可以运行 echo \$SHELL 来帮助您确定 shell。

To enable shell autocompletion for uv commands, run one of the following: 要为 uv 命令启用 shell 自动完成,请运行以下命令之一:

PowerShell / pwsh Zsh fish 鱼 Elvish 精灵 Bash 猛击 echo 'uv generate-shell-completion fish | source' > ~/.config/fish/completions/uv.

To enable shell autocompletion for uvx, run one of the following: 要为 uvx 启用 shell 自动完成功能,请运行以下作之一:

Zsh fish 鱼 Elvish 精灵 PowerShell / pwsh Bash 猛击 echo 'uvx --generate-shell-completion fish | source' > ~/.config/fish/completions/

Then restart the shell or source the shell config file. 然后重新启动 shell 或获取 shell 配置文件。

Uninstallation 卸载 If you need to remove uv from your system, follow these steps:

1. Clean up stored data (optional):

如果您需要从系统中去除紫外线,请按照下列步骤作:

\$ uv cache clean \$ rm -r "\$(uv python dir)"

\$ rm -r "\$(uv tool dir)"

清理存储的数据(可选):

🔥 Tip 提示 Before removing the binaries, you may want to remove any data that uv has stored.

在删除二进制文件之前,您可能希望删除 uv 存储的任何数据。

2. Remove the uv and uvx binaries:

删除 uv 和 uvx 二进制文件:

\$ rm ~/.local/bin/uv ~/.local/bin/uvx

macOS and Linux macOS 和 Linux Windows 窗户

Prior to 0.5.0, uv was installed into ~/.cargo/bin. The binaries can be removed from there to uninstall.

✓ Note 注意

Upgrading from an older version will not automatically remove the binaries from ~/.cargo/bin. 在 0.5.0 之前, uv 被安装到 ~/.cargo/bin 中。二进制文件可以从那里删除,以 卸载。从旧版本升级不会自动从 ~/.cargo/bin 中。

Next steps 后续步骤

See the first steps or jump straight to the guides to start using uv. 请参阅第一步或直接跳转到指南以开始使用 uv。

Made with Material for MkDocs Insiders

Previous 以前