

W3WAVE
W3SRCE (one sea point)
Fortran ST4 + DIA
W3KOKKOSMD (bind C)
part_flags.cpp
C++ shims
Kokkos kernel, device VA
NOAA WW3 at 03adda91
CALL W3SRCE, w3wavemd.F90 : 2311 (loop : 2246)
W3SIN4 : 1239, W3SNL1 : 1260, W3SDS4 : 1303
S_in, S_nl, S_ds
VA(:, JSEA) updated
Fork at 769c44f0, phase 1 (one point per call)
W3KOKKOS_SETUP asks WW_KOKKOS_PART flags
on or off (unset means off)
CALL W3SRCE, w3wavemd.F90 : 2500 (loop : 2417)
alt
[flag off]
W3SIN4 : 1244, W3SNL1 : 1544, W3SDS4 : 1622
same Fortran as NOAA
[flag on]
W3KOKKOS_SIN4 : 1240, WW_SNL1 : 1535, W3KOKKOS_SDS4 : 1619
ww_sin4, ww_snl1, ww_sds4
copy one point in
kernel, fence, copy out
VSNL, VDNL, last error
opt
[WW_KOKKOS_SRCE: whole W3SRCE for one point]
W3KOKKOS_SRCE, w3wavemd.F90 : 2486
VA(:, JSEA), fluxes
Fork, —kokkos resident (opt-in parts)
W3KOKKOS_SRCE_BATCH, w3wavemd.F90 : 2408
ww_srce_batch_va, all sea points
batched source terms on device VA
UST, TAUW, WHITECAP unpacked on host
W3KOKKOS_OUTG, w3wavemd.F90 : 2699 (NOAA : W3OUTG : 2490)
ww_outg_va on device VA
gridded fields, no VA copy
W3KOKKOS_VA_HOST_READ before a host reader
ww_va_host_read
VA copied back if the device copy is newer
W3WAVE
W3SRCE (one sea point)
Fortran ST4 + DIA
W3KOKKOSMD (bind C)
part_flags.cpp
C++ shims
Kokkos kernel, device VA