Launch Control XL 3 — Track 011 — the set: 007 → 010 → 009 → 008 (one controller)

One continuous set through four tracks: 007 ambient (70 BPM) → 010 ambient house (120) → 009 cool house (122) → 008 groove techno (140, here in A). Every column keeps its role; the sounds behind it change with the track.

Jonas' column 8 button 2 switches the Fog knob between Fog and the set position. In set mode, turning it moves through the set: each track has a plateau, between two plateaus a slow transformation: column by column the old sound turns into the new one (hits move to their new place, pitch, decay and filters glide; what has no partner thins out or fades). Air and pad first, then the low end, drums, melodies last. Leave it anywhere: a halfway position is its own sound.

Chapter, the buttons and the LC view belong to the track in focus (the nearer one in a transition). Chapters change at the next 8-bar phrase (007, 008: 4 bars). No Break / Drop in the set.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Shaker / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Pulse / Kick	2 Rumble / Noise	3 Sub	4 Bassline	5 Backbeat	6 Hats	7 Percussion	8 Global
Row 1 Brightness	CC 13 **Brightness** dull thump ↔ clicky attack. Never fully closed.	CC 14 **Brightness** deep rumble ↔ airy hiss.	CC 15 **Brightness** pure sine ↔ a little buzz on top.	CC 16 **Brightness** round and dark ↔ buzzing, squelchy.	CC 17 **Brightness** soft and far ↔ sharp crack.	CC 18 **Brightness** soft hiss ↔ crisp and sharp.	CC 19 **Brightness** woody ↔ metallic.	CC 20 **Fog / Set** Fog: 0 = clear, up = everything muffled. Set mode (button 2): the set position, 007 → 010 → 009 → 008.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 22 **Space** dry ↔ far away.	CC 23 **Space** dry ↔ far away.	CC 24 **Space** dry ↔ far away.	CC 25 **Space** dry ↔ far away.	CC 26 **Space** dry ↔ far away.	CC 27 **Space** dry ↔ far away.	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Softness** 0 = soft and round (the default) ↔ a deep, soft thump. Punch comes from row 1 (click). 007: Drive · 009/008: Punch.	CC 30 **Sea ↔ Wind / Motion** still ↔ rolling waves / sweeps.	CC 31 **Beating / Length** long held tones ↔ short blips.	CC 32 **Groove / Sound** few notes ↔ busy, bouncing line.	CC 33 **Ghost notes** 0 = plain backbeat ↔ extra quiet hits in between.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little rolls. 009: Hats ↔ Shaker.	CC 35 **Density** steady pattern ↔ + ghost notes and rolls.	CC 36 **Tension** build-up: echo grows, filters open (in the set at most 75 %). Back to 0 = release.
Fader Level	CC 5 **Level** 007 Pulse · 010 Kick · 009 Kick · 008 Kick.	CC 6 **Level** 007 Sea / Wind · 010 Atmo Pump · 009 Noise Pump · 008 Rumble.	CC 7 **Level** 007 Drone · 010 Sub · 009 Sub · 008 Sub.	CC 8 **Level** 007 Bass · 010 Bassline · 009 Bass · 008 Bassline.	CC 9 **Level** 007 Rim · 010 Clap / Rim · 009 Clap · 008 Clap.	CC 10 **Level** 007 Ticks · 010 Hats · 009 Hats / Shaker · 008 Hats.	CC 11 **Level** 007 Wood / Drops · 010 Congas · 009 Congas · 008 Percussion.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change / Double time** next of at most 3 patterns, at the next bar.	CC 38 **Change** next of at most 3 patterns.	CC 39 **Change** next of at most 3 patterns.	CC 40 **Change** next of at most 3 patterns.	CC 41 **Change** next of at most 3 patterns.	CC 42 **Change** next of at most 3 patterns.	CC 43 **Change** next of at most 3 patterns.	CC 44 **Chapter** next chords of the track in focus, at the next phrase.

Button 2 Moment	CC 45 **Drop out / Drop** kick pauses while held.	CC 46 **Riser** noise rises while held.	CC 47 **Slide** notes glide into each other while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll / Swell** snare roll while held.	CC 50 **Open / Long** hats ring long while held.	CC 51 **Fill** a fill while held.	CC 52 **Set mode** Fog knob: Fog ↔ set position.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Chords	3 Arp	4 Lead	5 Answer	6 Sparkle	7 FX / Risers	8 Global + Set
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy.	CC 62 **Brightness** warm ↔ bright, glassy.	CC 63 **Brightness** soft plucks ↔ sharp, sparkling.	CC 64 **Brightness** soft and round ↔ biting (acid squelch).	CC 65 **Brightness** hushed ↔ clear.	CC 66 **Brightness** soft glow ↔ glittering.	CC 67 **Brightness** dark whoosh ↔ bright shimmer.	CC 20 **Fog / Set** Fog: 0 = clear, up = everything muffled. Set mode (button 2): the set position, 007 → 010 → 009 → 008.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 70 **Space** dry ↔ far away.	CC 71 **Space / Soft** dry ↔ far away.	CC 72 **Space** dry ↔ far away.	CC 73 **Space** dry ↔ far away.	CC 74 **Space** dry ↔ far away.	CC 75 **Space** dry ↔ far away.	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell / Strings ↔ B3** still ↔ slowly breathing in and out.	CC 78 **Rhythm** long held chords ↔ short, choppy stabs. 007: Complexity · 009: Length · 008: Pump.	CC 79 **Complexity / Range** few slow notes ↔ fast and wide.	CC 80 **Glide** plain notes ↔ notes slide into each other. 007: Complexity · 009: Playful · 008: Variation.	CC 81 **Voices / Complexity** one voice ↔ two-, three-part harmony.	CC 82 **Density / Build-up** a sparkle now and then ↔ a rain of notes.	CC 83 **Amount / Complexity** subtle ↔ wild.	CC 36 **Tension** build-up: echo grows, filters open (in the set at most 75 %). Back to 0 = release.
Fader Level	CC 53 **Level** 007 Pad · 010 Pad · 009 Harmony · 008 Pad.	CC 54 **Level** 007 Eno Bowed · 010 Deep Chords · 009 Keys · 008 Techno Pad.	CC 55 **Level** 007 Marimba · 010 Pluck Arp · 009 Vibraphone · 008 Sequence.	CC 56 **Level** 007 Toms · 010 Lead · 009 Flute · 008 Stab.	CC 57 **Level** 007 Choir · 010 Marimba · 009 Brass · 008 Answer.	CC 58 **Level** 007 Glitter · 010 Glockenspiel · 009 Strings · 008 Dark Perc.	CC 59 **Level** 007 Shimmer · 010 Birds · 009 Guitar · 008 FX / Breath.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change / Progression** next pattern / melody, at the next bar.	CC 86 **Change** next pattern / melody.	CC 87 **Change / Phrase** next pattern / melody.	CC 88 **Change / Motif** next pattern / melody.	CC 89 **Change / Figure** next pattern / melody.	CC 90 **Change / Figure** next pattern / melody.	CC 91 **Change / Line** next pattern / melody.	CC 44 **Chapter** next chords of the track in focus, at the next phrase.
Button 2 Moment	CC 93 **Freeze / Echo throw** holds the current chord while held.	CC 94 **Stab** one accent chord, now. 007/008: Echo throw · 009: Sound.	CC 95 **Echo throw / Octave** one octave up while held.	CC 96 **Echo throw** the last note echoes away.	CC 97 **Answer** plays one phrase, now. 007: Full choir · 009: Lift.	CC 98 **Burst** one quick run of sparkles. 007/010: Run · 009: Lift · 008: Roll.	CC 99 **Hit** one FX hit / impact. 007: Rise · 010: Flock · 009: Lift · 008: Open.	CC 52 **Set mode** Fog knob: Fog ↔ set position.

Guide

The journey

007 → 010 → 009 → 008: from a floating heartbeat to techno. The Fog knob in set mode is the map: a full turn is the whole set, each track sits on a plateau where small moves change nothing.

A transition takes as long as you turn: slowly, over 16–32 bars, is best. Even a fast spin glides over at least 5 seconds. The tempo moves with it: 70 → 60 (007 slows a little, then 010 doubles it to 120), 120 → 122, 122 → 140.

Faders stay where they are: the same column has the same job in the next track. Bring the faders of a new track's extra sounds up only after the transition.

Less is more

One change at a time, every 8 bars at most. Let a loop run before it changes again. Chapters wait for the next phrase on purpose.

Fog and Room hide a transition: muffle or drown everything a little, move the set on, then clear up again.

Status box

The status box at the bottom right of the Strudel page shows the set position, chapter and each stem's pattern. Its button "als Fenster" opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.