Launch Control XL 3 — Arp Cascade (sounds/parts)

One 12-step dorian arpeggio in ten registers at once, plus kick and tom-bass. All knobs at 0 and all faders up = the original sound from tutorial.str.

The knobs are set to 0 on load. Button row 1 steps on with every press (re-evaluating starts over). Density: 4 = straight, 3 = floating, 2 = half-time, 6 = driving; kick 4 + tom 3 = 3-against-4 polyrhythm. Each arp column has its own motif, so they can play against each other.

Knob Fader Button unused

Mode 16 — Arp Cascade

	1 High (+24, +15)	2 Mid (+12, +3)	3 Root (0)	4 Low (–12, –24)	5 Sub (–31 … –48)	6 Kick	7 Tom-Bass	8 Global
Row 1 HPF	CC 13 **HPF** 20–2000 Hz: takes the body out of the layer; fully open only the chirp is left.	CC 14 **HPF** as 1 High (+24, +15)	CC 15 **HPF** as 1 High (+24, +15)	CC 16 **HPF** as 1 High (+24, +15)	CC 17 **HPF** as 1 High (+24, +15)	CC 18 **HPF** 20–2000 Hz: fully open only the click is left.	CC 19 **HPF** 20–2000 Hz.	CC 20 **Global HPF** 0–1000 Hz, added to every column's HPF: everything thinner, for breaks.
Row 2 Acid / LPF	CC 21 **Acid** 0 = original, up = the filter opens up to 3× further per note: brighter, more squelchy.	CC 22 **Acid** as 1 High (+24, +15)	CC 23 **Acid** as 1 High (+24, +15)	CC 24 **Acid** as 1 High (+24, +15)	CC 25 **Acid** as 1 High (+24, +15)	CC 26 **LPF** 0 = original (200 Hz, muffled), up = up to 6.4 kHz: the attack comes through.	CC 27 **LPF** 0 = original (300/200 Hz, just boom), up = up to 32× brighter: becomes a tom.	CC 28 **Noise** 0–0.3: brown noise as a bed underneath (0.1 in the original).
Row 3 Character	CC 29 **Decay** 0 = original (0.12 s), up = up to 0.7 s: the filter closes slower, “wah” instead of “blip”.	CC 30 **Decay** as 1 High (+24, +15)	CC 31 **Decay** as 1 High (+24, +15)	CC 32 **Decay** as 1 High (+24, +15)	CC 33 **Decay** as 1 High (+24, +15)	CC 34 **Drive** 0 = original, up = more saturation: harder, sounds louder.	CC 35 **Length** 0 = original (1.8 s tail), up = shorter, down to 0.2 s: from drone to dab.	CC 36 —
Fader Level	CC 5 **Level** 0–1, top = original level of the layers.	CC 6 **Level** as 1 High (+24, +15)	CC 7 **Level** as 1 High (+24, +15)	CC 8 **Level** as 1 High (+24, +15)	CC 9 **Level** as 1 High (+24, +15)	CC 10 **Level** 0–1.	CC 11 **Level** 0–1.	CC 12 **Master** 0–1, overall volume.
Button 1 Pattern	CC 37 **Motif** full → gaps → short.	CC 38 **Motif** as 1 High (+24, +15)	CC 39 **Motif** as 1 High (+24, +15)	CC 40 **Motif** as 1 High (+24, +15)	CC 41 **Motif** as 1 High (+24, +15)	CC 42 **Density** 4 → 3 → 2 → 6 per bar.	CC 43 **Density** 4 → 3 → 6 → 2. 1 press = 3 against 4.	CC 44 —
Buttons 2	CC 45 —	CC 46 —	CC 47 —	CC 48 —	CC 49 —	CC 50 —	CC 51 —	CC 52 —