Launch Control XL 3 — Track 008 — groove techno (one controller)

Groove techno on F, 140 BPM. Jojo plays the foundation (kick, bass, drums), Jonas the colour (pads, dub chords, melodies) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Jonas' pad button 1 changes the chords, and Jojo's sub and bassline follow.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Rumble	3 Sub	4 Bassline	5 Clap	6 Hats	7 Percussion	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round but clear ↔ clicky attack (lpf 900–9000 Hz).	CC 14 **Brightness** 0 = warm rumble ↔ more of the kick's body in the tail (lpf 250–1800 Hz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** 0 = round ↔ raw and buzzing (lpf 400–3000 Hz).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.5–12 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** woody ↔ metallic (FM and lpf 600–12000 Hz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** short rumble ↔ a long dark cloud (reverb never fully off: the reverb is the sound).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** 0 = really soft thump, middle = round kick, 1 = hard and punchy.	CC 30 **Motion** still ↔ the filter breathes and the rumble echoes in 16ths.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** off-beats only ↔ extra 16th notes bouncing in between.	CC 33 **Ghost notes** plain ↔ a quiet clap before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + little rolls.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Kick on every beat, tuned to C (fifth of F).	CC 6 **Level** rumble under the kick, same pitch (C).	CC 7 **Level** pumping sub, follows Jonas' chords.	CC 8 **Level** off-beat bass, follows Jonas' chords.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** hats. Keep playing in the break.	CC 11 **Level** bongos and rimshot. Keep playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** straight → ghost kick before the 1 → gap every 4th bar.	CC 38 **Change** 3rd + 4th 16th → 2nd–4th → only the 3rd.	CC 39 **Change** pump → fifth on beat 4 → syncopated.	CC 40 **Change** off-beat → 3-3-2 → dub.	CC 41 **Change** plain → pickup → double clap.	CC 42 **Change** off-beat → plain 16ths → driving.	CC 43 **Change** pillow → gallop → 3-3-2.	CC 44 **Chapter** mood: warm → dark → tense, at the next bar.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on the off-beats while held.	CC 51 **Fill** a bongo run down over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Dub Chords	3 Sequence	4 Lead	5 Answer	6 Pings	7 FX / Breath	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 250–6000 Hz).	CC 62 **Brightness** warm and muffled ↔ bright, raw (lpf 400–7000 Hz).	CC 63 **Brightness** soft wooden mallet ↔ sharp, glassy (lpf 1.5–12 kHz, more FM).	CC 64 **Brightness** soft and warm ↔ open, a little reedy (lpf 600–6000 Hz).	CC 65 **Brightness** soft ↔ clear and bright (lpf 2–12 kHz).	CC 66 **Brightness** soft glow ↔ ringing, bright (lpf 4–16 kHz).	CC 67 **Brightness** dark whoosh ↔ bright hiss (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 70 **Space** dry ↔ the echoes repeat far into the distance.	CC 71 **Space** a little room ↔ far away (reverb + dub echo).	CC 72 **Space** a little room ↔ far away (reverb + echo).	CC 73 **Space** some room and echo ↔ far away in space.	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** some room ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Swell** 0 = held chords. Up = the chord is re-struck on every half bar and breathes in and out.	CC 78 **Length** long ringing chords ↔ short, choppy stabs.	CC 79 **Range** few notes of the loop ↔ every step, plus the 9th and 7th in between.	CC 80 **Glide** plain notes ↔ notes bend gently into their pitch (at most a semitone).	CC 81 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part blips.	CC 82 **Density** a few pings per bar ↔ a rain of pings (~70 % of the 16ths).	CC 83 **Amount** 0 = only the breathing noise. Up = the chord pulses along in 8ths, at 1 also a 16th shimmer an octave up.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** dark pad.	CC 54 **Level** dub chord stabs (same chords as the pad).	CC 55 **Level** hypnotic loop on the chord.	CC 56 **Level** lead line on the chord.	CC 57 **Level** counter blips, a short phrase every second bar.	CC 58 **Level** glockenspiel pings.	CC 59 **Level** slow breathing.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** next of 8 chord progressions, for all.	CC 86 **Change** next of 8 stab rhythms.	CC 87 **Change** next of 8 loops (3, 5 or 7 steps).	CC 88 **Change** next of 8 lines.	CC 89 **Change** next of 8 phrase rhythms (new notes too).	CC 90 **Change** next of 8 random ping patterns.	CC 91 **Change** one breath per 2 → 4 → 8 → 1 bar(s).	CC 44 **Chapter** mood: warm → dark → tense, at the next bar.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Stab** a chord on every off-beat while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the line while held.	CC 97 **Answer** the phrase plays in every bar while held.	CC 98 **Run** runs up and down the chord, denser and louder the longer it is held (full after 2 bars).	CC 99 **Open** the breath opens fully while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: kick first, rumble right next to it, then sub and hats, then clap, bassline and the groove (percussion, ride).

Jonas colours it: pad or dub chords first (all knobs at 0 is a good start), then the sequence. Lead, answer and pings are for the peaks, the breathing FX for long transitions.

The pad's button 1 changes the chords for both players: Jojo's sub and bassline move with it. Pad button 2 (freeze) holds the chord for everybody.

Break: one press takes out kick, rumble, sub, bassline and clap at the next bar; hats, percussion, ride and all of Jonas' sounds keep going. Turn Tension up during the break, press again: everything is back on the one. Then let Tension go.

Every position sounds good

No filter closes completely. Sequence, answer and FX keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.