Launch Control XL 3 — Track 009 — happy house (one controller)

Happy house in A major, 124 BPM. Jojo plays the foundation (kick, bass, drums, congas), Jonas the colour (strings, piano, hook, chops) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) changes the chords for everybody at the next 4-bar phrase.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Shaker / Tamb.) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Noise Pump	3 Sub	4 Bassline	5 Clap + Snare	6 Hats	7 Congas	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round but clear ↔ clicky attack (lpf 900–9000 Hz).	CC 14 **Brightness** dull whoosh ↔ airy hiss (lpf 2–14 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** 0 = round and woody ↔ buzzing, squelchy (lpf 300–2500 Hz + envelope).	CC 17 **Brightness** soft and far ↔ sharp crack (lpf 1.5–12 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 600–12000 Hz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Softness** 0 = round 909 kick ↔ 1 = very soft, deep thump without click.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ extra 16th notes bouncing in between.	CC 33 **Ghost notes** plain ↔ a quiet clap before beat 3 ↔ + small double taps.	CC 34 **Density** the pattern as it is ↔ + quiet 16ths ↔ + little 32nd rolls.	CC 35 **Density** steady pattern ↔ + fingertip ghost notes ↔ + agogo bells.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Four-on-the-floor kick, tuned to E (fifth of A).	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the chord root, follows the chapter.	CC 8 **Level** bouncy bass, follows the chapter.	CC 9 **Level** clap + snare on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat open hat. Keeps playing in the break.	CC 11 **Level** congas and bongos. Keep playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** straight → pickup before the 1 → gap every 4th bar.	CC 38 **Change** pump → off-beat → swoosh (2 bars).	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** octave bounce → off-beat → disco.	CC 41 **Change** plain → pickup → double clap.	CC 42 **Change** off-beat → + 16ths → disco (swelling 16ths).	CC 43 **Change** pillow → gallop → latin.	CC 44 **Chapter** next chord progression for all, at the next 4-bar phrase.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one, with a crash.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Strings	2 Piano	3 Arp	4 Vocal Hook	5 Answer	6 Bells	7 Vocal Chops	8 Global
Row 1 Brightness	CC 61 **Brightness** muffled ↔ open and airy (lpf 400–6000 Hz).	CC 62 **Brightness** warm and muffled ↔ bright, ringing (lpf 600–10000 Hz).	CC 63 **Brightness** soft plucks ↔ sharp, sparkling (lpf 1.2–10 kHz).	CC 64 **Brightness** soft and hushed ↔ open, bright voice (lpf 600–6000 Hz).	CC 65 **Brightness** soft ↔ clear and bright (lpf 1.5–10 kHz).	CC 66 **Brightness** soft glow ↔ glittering (lpf 3–16 kHz).	CC 67 **Brightness** muffled ↔ bright, crisp syllables (lpf 1.2–10 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 69 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 70 **Space** dry ↔ the echoes repeat far into the room.	CC 71 **Space** a little room ↔ far away (reverb + echo).	CC 72 **Space** a little room ↔ far away (reverb + echo).	CC 73 **Space** some room and echo ↔ far away.	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** a little room ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Pump** 0 = held strings. Up = they pump with the kick (re-struck every beat, like a sidechain).	CC 78 **Rhythm** long ringing chords ↔ short, choppy stabs.	CC 79 **Range** few notes of the arp ↔ every 16th, plus the 9th and 6th in between.	CC 80 **Glide** plain notes ↔ notes bend gently into their pitch (at most a semitone).	CC 81 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part organ.	CC 82 **Density** a few bells per bar ↔ a rain of bells (~70 % of the 16ths).	CC 83 **Amount** subtle (the rhythm only) ↔ wild: extra chops an octave up, with echo.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** warm strings on the chapter's chords.	CC 54 **Level** piano chords on the chapter's chords.	CC 55 **Level** bright arp on the chord.	CC 56 **Level** the vocal hook on the chord.	CC 57 **Level** answer phrase, every second bar.	CC 58 **Level** bells on the chord.	CC 59 **Level** vocal chops on the chord.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** voicing: warm → bright → wide.	CC 86 **Change** next of 8 piano rhythms.	CC 87 **Change** next of 8 arp shapes.	CC 88 **Change** next of 8 hooks.	CC 89 **Change** next of 8 phrase rhythms (new notes too).	CC 90 **Change** next of 8 random bell patterns.	CC 91 **Change** next of 8 chop rhythms (new syllables too).	CC 44 **Chapter** next chord progression for all, at the next 4-bar phrase.
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Stab** a chord on every off-beat while held.	CC 95 **Octave** one octave up while held.	CC 96 **Echo throw** long echo on the hook while held.	CC 97 **Answer** the phrase plays in every bar while held.	CC 98 **Burst** a quick rain of bells while held.	CC 99 **Stutter** the chop stutters on every 16th while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one, with a crash.

Guide

Playing together

Jojo builds the floor: kick first, then sub and the off-beat hats, then clap, bassline and the groove (congas, shaker). The noise pump glues to the kick.

Jonas colours it: strings or piano first (all knobs at 0 is a good start), then arp and bells. Vocal hook and chops are for the peaks.

Chapter changes the chords for both players at the next 4-bar phrase: sub, bassline and every melody follow. Strings button 2 (freeze) holds the chord for everybody.

Build-up and drop: Jonas turns Tension up (echo, open filters, snare roll), presses Break at the top: the beat goes out, strings and piano float. Jojo holds the noise riser, Jonas presses Break again: everything is back on the one, with a crash. Then let Tension go.

Every position sounds good

No filter closes completely. Arp, hook and chops keep a little room even at space 0.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.