# Launch Control XL 3 — Track 007 (ambient moods, two controllers)

Dreamy ambient on D, about 70 BPM. Three moods on the global button 2, switching at the next bar: lydian (floating, bright), dorian (melancholic, misty), whole tone (strange, no key).

Every column: HPF, LPF, character, level, button 1 = next random variation (8 per stem). Column 1, knob 1 = level of a soft heartbeat thump on D, independent of the drone fader (pulse without drone works).

LPF knobs at 0 are almost closed: open row 2 first. The global knobs at 0 are neutral (dry, clear, no echo).

Two controllers: A plays the ambient stems and the global column, B (second LC XL 3, same Mode 16) plays the bass on column 1.

The status box at the bottom right of the Strudel page shows mood, pulse rhythm and each stem's variation. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | unused

## Controller A, Mode 16 — Ambient

| | 1 Drone + Pulse | 2 Pad | 3 Glitter | 4 Sea / Wind | 5 Whale | 6 Choir | 7 Music Box | 8 Global |
|---|---|---|---|---|---|---|---|---|
| **Row 1 HPF** | CC 13 **Pulse** level of a soft kick on D, 0 = off. Plays without the drone fader too. | CC 14 **HPF** 40–1500 Hz | CC 15 **HPF** 200–4000 Hz | CC 16 **HPF** 20–2000 Hz | CC 17 **HPF** 20–800 Hz | CC 18 **HPF** 80–2000 Hz | CC 19 **HPF** 100–3000 Hz | CC 20 **Space** 0 = each stem's own reverb, 1 = everything drowns in reverb. |
| **Row 2 LPF** | CC 21 **LPF** 80–4000 Hz | CC 22 **LPF** 150–8000 Hz | CC 23 **LPF** 1–16 kHz | CC 24 **LPF** 200–12000 Hz (moves with the waves) | CC 25 **LPF** 150–6000 Hz | CC 26 **LPF** 300–10000 Hz | CC 27 **LPF** 1–14 kHz | CC 28 **Fog** 0 = clear, 1 = every stem's LPF pulled down to ~6 %: distant, under water. |
| **Row 3 Character** | CC 29 **Beating** 0 = pure sines. Up = a detuned saw copy fades in, the two beat against each other (slow “wah-wah”). | CC 30 **Shimmer** 0 = only the soft chord swells. Up = the chord an octave higher pings in a 3-in-8 rhythm with echoes. | CC 31 **Density** 0 = a drop now and then (~1 per bar), 1 = a sparkling rain (~70 % of the 16ths). | CC 32 **Sea ↔ Wind** 0 = brown-noise waves rolling in, 0.5 = both, 1 = only whistling wind gusts. | CC 33 **Glide** how far each call slides into its note: 0 = ±2 semitones, 1 = ±12 (deep, eerie bends). | CC 34 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part harmony. | CC 35 **Density** 0 = a few notes of the tune, 1 = every 8th plays. | CC 36 **Dream** 0–0.5: echo on all stems (not pulse, bass). 0.5–1: + a slow, gentle wobble on drone, pad, choir. |
| **Fader Level** | CC 5 **Level** drone, 0–1 (not the pulse) | CC 6 **Level** 0–1 | CC 7 **Level** 0–1 | CC 8 **Level** 0–1 | CC 9 **Level** 0–1 | CC 10 **Level** 0–1 | CC 11 **Level** 0–1 | CC 12 **Master Level** volume of everything. |
| **Button 1 Variation** | CC 37 **Variation** next of 8 drone chords per mood (D-A, D-A-E, …). | CC 38 **Variation** next of 8 random chord progressions. | CC 39 **Variation** next of 8 random drop patterns. | CC 40 **Variation** next of 8 random wave / gust patterns. | CC 41 **Variation** next of 8 random call sequences. | CC 42 **Variation** next of 8 random melodies. | CC 43 **Variation** next of 8 random note choices and octave leaps. | CC 44 **Re-roll all** all stems: next variation at once. |
| **Button 2 Pulse / Mood** | CC 45 **Pulse rhythm** heartbeat → quarters → half notes. | CC 46 **Pulse softness** soft → medium → hard (all rhythms). Starts soft. | CC 47 — | CC 48 — | CC 49 — | CC 50 — | CC 51 — | CC 52 **Mood** lydian → dorian → whole tone, at the next bar. |

## Controller B, Mode 16 — Bass

| | 1 Bass | 2 Test clap | 3 | 4 | 5 | 6 | 7 | 8 |
|---|---|---|---|---|---|---|---|---|
| **Row 1 HPF** | CC 13<br>**HPF**<br>20–300 Hz. Up = thinner, less sub. | CC 14<br>— | CC 15<br>— | CC 16<br>— | CC 17<br>— | CC 18<br>— | CC 19<br>— | CC 20<br>— |
| **Row 2 LPF** | CC 21<br>**LPF**<br>60–2000 Hz. Low = round and dark, up = the saw's buzz comes through. | CC 22<br>— | CC 23<br>— | CC 24<br>— | CC 25<br>— | CC 26<br>— | CC 27<br>— | CC 28<br>— |
| **Row 3 Rhythm** | CC 29<br>**Rhythm**<br>0 = a soft swell every bar. Up to 0.5 a 3-3-2 pulse fades in, at 1 only the pulse. | CC 30<br>— | CC 31<br>— | CC 32<br>— | CC 33<br>— | CC 34<br>— | CC 35<br>— | CC 36<br>— |
| **Fader Level** | CC 5<br>**Level**<br>0–1 | CC 6<br>**Test clap**<br>909 clap on 2 and 4, 0–1. Not affected by the master. To check controller B. | CC 7<br>— | CC 8<br>— | CC 9<br>— | CC 10<br>— | CC 11<br>— | CC 12<br>— |
| **Button 1 Variation** | CC 37<br>**Variation**<br>next of 8 random bass lines (a note every 2 bars). | CC 38<br>— | CC 39<br>— | CC 40<br>— | CC 41<br>— | CC 42<br>— | CC 43<br>— | CC 44<br>— |
| **Buttons 2** | CC 45<br>— | CC 46<br>— | CC 47<br>— | CC 48<br>— | CC 49<br>— | CC 50<br>— | CC 51<br>— | CC 52<br>— |