Launch Control XL 3 — Low-End Width Lab (lab/bass)

Kick, sub and bassline of 008, each from mono to very wide. Turn up width (knob 1) on one sound, then press mono check (column 8, button 1): does the sound keep its power?

Button 1 of a column switches the method: detune → Haas delay → auto-pan. Knob 3 keeps everything below the crossover mono: the safe way to be wide.

The status box at the bottom right shows every value with units.

Knob Fader Button unused

Mode 16 — Low-End Width Lab

	1 Kick	2 Sub	3 Bassline	4	5	6	7	8 Master + mono check
Row 1	CC 13 **Width** 0 = mono in the middle ↔ 1 = copies hard left and right.	CC 14 **Width** 0 = mono in the middle ↔ 1 = copies hard left and right.	CC 15 **Width** 0 = mono in the middle ↔ 1 = copies hard left and right.	CC 16 —	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2	CC 21 **Amount** detune 0–25 cents, Haas 0–20 ms, or auto-pan 0.25–4 sweeps per bar.	CC 22 **Amount** detune 0–25 cents, Haas 0–20 ms, or auto-pan 0.25–4 sweeps per bar.	CC 23 **Amount** detune 0–25 cents, Haas 0–20 ms, or auto-pan 0.25–4 sweeps per bar.	CC 24 —	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3	CC 29 **Crossover** 0 = whole sound wide; up = mono below 40–300 Hz, wide above.	CC 30 **Crossover** 0 = whole sound wide; up = mono below 40–300 Hz, wide above.	CC 31 **Crossover** 0 = whole sound wide; up = mono below 40–300 Hz, wide above.	CC 32 —	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 008's kick: sine on C2 + 909, on every beat.	CC 6 **Level** 008's sub: pumping sine + triangle on F1 / D♭1, a 16th after each kick.	CC 7 **Level** 008's rolling bassline on F2, detuned saws through a snapping filter.	CC 8 —	CC 9 —	CC 10 —	CC 11 —	CC 12 **Master** volume of the whole board.
Buttons 1	CC 37 **Method** detune → Haas → auto-pan.	CC 38 **Method** detune → Haas → auto-pan.	CC 39 **Method** detune → Haas → auto-pan.	CC 40 —	CC 41 —	CC 42 —	CC 43 —	CC 44 **Mono check** on: everything in the middle, as a club system sums it (copies stay, so you hear what cancels).
Buttons 2	CC 45 **Solo** only the kick; press again = all.	CC 46 **Solo** only the sub; press again = all.	CC 47 **Solo** only the bassline; press again = all.	CC 48 —	CC 49 —	CC 50 —	CC 51 —	CC 52 **Bypass** on: no width at all, one mono copy each: the reference.

Guide

Three ways to make a sound wide

Detune: two copies, left a little lower, right a little higher; they beat against each other. Haas: the right copy comes a few milliseconds later. Auto-pan: one copy that wanders from left to right.

What mono does

A club system adds left and right. A Haas copy then hollows out some frequencies (comb filter): on the sub at 10 ms almost half a wave late, so it nearly cancels. Detuned copies swell and fade in a slow pulse, but 008's sub notes are short and restart in step, so detune costs little there (and gives little width). Auto-pan changes the level a little.

What to listen for

Headphones first: which width do you like? Then mono check: is the sub still there on every note, and still as loud? A phone speaker is a good second test.

Crossover

Knob 3 splits the sound: below the crossover one mono copy, above it the wide copies. The sub (a sine at 35–44 Hz) has almost nothing above 100 Hz, so with the crossover up only its triangle overtones go wide.