Launch Control XL 3 — Track 009 — dry house (one controller)

Dry, happy oldschool house in A minor, 124 BPM: short sounds, one piano hook on the off-beats. Jojo plays the rhythm (kick, bass, drums, percussion), Jonas the melody (keys, trumpet stabs, sax, vocal chops, pluck, marimba, pad) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) switches between one chord (Vamp) and two chords (Wechsel) at the next 4-bar phrase.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Tamb / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Noise Pump	3 Sub	4 Bass	5 Clap	6 Hats / Shaker	7 Congas	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = round and tight ↔ extra click on top (lpf 4–16 kHz).	CC 14 **Brightness** soft whoosh ↔ airy hiss (lpf 2–14 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** round ↔ a clear, buzzing edge (lpf 700–5000 Hz).	CC 17 **Brightness** natural ↔ sharp crack (lpf 3.5–14 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 4–16 kHz).	CC 19 **Brightness** soft and woody ↔ crisp slap (lpf 1–12 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Punch** 0 = tight 909 kick ↔ harder: bigger pitch drop, more body.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Groove** the line as it is ↔ random ghost notes (root, fifth, seventh) rolling in between.	CC 33 **Ghost notes** plain ↔ a quiet rim before beat 3 ↔ + small double taps.	CC 34 **Hats ↔ Shaker** 0 = 909 hats ↔ middle = both ↔ 1 = shaker (same rhythm).	CC 35 **Density** steady pattern ↔ + fingertip ghost notes.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Four on the floor, tuned to A.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the root, follows the chapter.	CC 8 **Level** bass line, follows the chapter.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat hat + swung 16ths.	CC 11 **Level** congas and bongos, in the background.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** 4/4 → a gap every 4th bar → a gap every 8th bar.	CC 38 **Change** pump → off-beat → 16ths.	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** syncopated → two-bar melody → off-beat.	CC 41 **Change** 2 + 4 → with a pickup → a fill every 4th bar.	CC 42 **Change** off-beat → + swung 16ths → driving 16ths.	CC 43 **Change** pillow → rolling → latin.	CC 44 **Chapter** Vamp ↔ Wechsel, at the next phrase.
Button 2 Moment	CC 45 **Drop** kick, noise pump and sub pause while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a conga run over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Keys	2 Horns	3 Sax	4 Vocal Chops	5 Pluck	6 Marimba	7 Pad	8 Global
Row 1 Brightness	CC 61 **Brightness** soft ↔ glassy and bright (lpf 3–18 kHz).	CC 62 **Brightness** soft ↔ brassy and sharp (lpf 2–16 kHz).	CC 63 **Brightness** breathy and soft ↔ bright, reedy (lpf 1.5–12 kHz).	CC 64 **Brightness** hushed ↔ clear (lpf 1.5–12 kHz).	CC 65 **Brightness** round ↔ sharp and glassy (lpf 1.5–14 kHz).	CC 66 **Brightness** woody ↔ bright (lpf 1.5–12 kHz).	CC 67 **Brightness** soft ↔ open and bright (lpf 1.2–9 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 69 **Space** dry ↔ the echoes repeat into the room.	CC 70 **Space** dry ↔ far away (reverb + echo).	CC 71 **Space** dry ↔ far away (reverb + echo).	CC 72 **Space** dry ↔ far away (reverb + echo).	CC 73 **Space** dry ↔ the echoes repeat into the room.	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** dry ↔ a big hall (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Sound** 0 = M1 house piano ↔ grand ↔ Rhodes ↔ 1 = organ (crossfade).	CC 78 **Play** 0 = the riff repeats every 2 bars ↔ up = beats break out: new, busier, wider.	CC 79 **Play** 0 = the phrase repeats every 4 bars ↔ up = it improvises: new notes, busier, higher.	CC 80 **Play** 0 = the chops repeat every 2 bars ↔ up = they stutter and jump around.	CC 81 **Play** 0 = the figure repeats every 2 bars ↔ up = it wanders: new notes, wider jumps.	CC 82 **Play** 0 = the figure repeats every 2 bars ↔ up = it plays freely, busier.	CC 83 **Motion** 0 = still ↔ the filter breathes slowly over 4 bars.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** the chords: the only chord instrument.	CC 54 **Level** trumpet stabs, a syncopated riff on the chord tones.	CC 55 **Level** tenor sax phrases.	CC 56 **Level** “ah” chops, sparse.	CC 57 **Level** the pluck arp.	CC 58 **Level** marimba figures.	CC 59 **Level** pad on the chapter's chord. Keeps playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** 3-3-2 → push → gospel → call.	CC 86 **Change** the next riff (8 riffs, at the next bar).	CC 87 **Change** the next phrase (8 phrases, at the next bar).	CC 88 **Change** the next chop pattern (8 patterns, at the next bar).	CC 89 **Change** the next figure (8 figures, at the next bar).	CC 90 **Change** the next figure (8 figures, at the next bar).	CC 91 **Change** full chord → only the top (thin, high) → low and wide.	CC 44 **Chapter** Vamp ↔ Wechsel, at the next phrase.
Button 2 Moment	CC 93 **Echo** a short echo on the chords while held.	CC 94 **Shout** stabs on every off-beat 8th while held.	CC 95 **Echo throw** long echo on the sax while held.	CC 96 **Shout** a rave shout on the one of every bar while held.	CC 97 **Octave** one octave up while held.	CC 98 **Echo throw** long echo on the marimba while held.	CC 99 **Freeze** holds the current chord while held, for everybody.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Building it up

One layer after the other, not all at once: drums (kick, hats, clap), then bass and sub, then the keys, then one or two top voices, then percussion (congas, tambourine). Start in Vamp.

Keys and top voices

Keys are the only chords: row 3 changes the sound (piano → Rhodes → organ), not the part. Horns, sax, vocal, pluck and marimba each play a riff that repeats; button 1 = the next riff, Play (row 3) lets it improvise. Two top voices at a time, answering each other, is plenty.

Break and drop

Jonas presses Break: the whole rhythm goes out at the next bar, only keys or pad keep playing (pull the rest down). Jojo holds the riser (noise pump, button 2). Jonas switches Chapter to Wechsel and presses Break again: everything is back on the one, now with two chords.

Every position sounds good

All knobs at 0 is dry, close and clear, as the track is meant to be. Space adds room, it does not repair. Every column has its own fader: each layer can be muted on its own.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.