STANDARD OPERATING PROCEDURE · BY ROLE

How to LIVE and TEST: switching, logins and scanners

For: Admins, and anyone who uses the TEST system · Full Harvest Inventory

TEST is the app deployed a second time with its own database: the place to try new code, new settings or a practice count on real guns without touching the live stock. **LIVE** is the home: it keeps the logins, decides who may use which system, and registers the scanners. People and scanners switch between the two from inside the app — one sign-in, one scanner link.

Printed October 20, 2026

Contents

1 — In one minute 3

2 — Set TEST up (once) 4

3 — Who may use TEST 6

4 — Logins someone made on TEST: copy them to LIVE 7

5 — Switching in the office 8

6 — Scanners 9

7 — When something is not right 10

1 — In one minute

- **Logins are made on LIVE only.** Nobody needs a login on TEST: switching takes the person over with their role and pages.
- **Scanners are registered on LIVE only.** A gun switches to TEST under its own name and link.
- **Which one am I on?** The logo and site name sit in a ring of the system's color with its name — green **LIVE**, orange **TEST** — on the office pages and on the gun. Every TEST page also has an orange *TEST — not the live system* bar with **Back to LIVE**.
- **Nothing mixes.** TEST has its own counts, lists, crew, settings and backups.

2 — Set TEST up (once)


In Railway, on the TEST service (deployed from the same branch as LIVE, with its **own volume**), set three variables and redeploy:

VARIABLE	VALUE
`SYSTEM_NAME`	`TEST`
`SYSTEM_HOME_URL`	LIVE's address, nothing after it — `https://full-harvest-inv-prod.up.railway.app`
`SYSTEM_LINK_KEY`	LIVE's link key: on LIVE, **Settings → Site & systems → Systems → The link key → Copy**. Paste it with no spaces or quotes

LIVE has **no** `SYSTEM_HOME_URL` — that is what makes it the home.

On LIVE, *Settings → Site & systems → Systems*:


1. **Add a system**: name **TEST**, TEST's Railway address, a color (orange).
2. Under **On the scanners**, choose where the guns count: back until you choose again (a training day on the real guns, say).
   - **LIVE and TEST** — the gun's sign-on screen has *System* to switch;
   - **LIVE only** — no *System* row; a gun left on TEST comes back to LIVE by itself;
   - **TEST only** — every gun goes to TEST by itself, once its counts have sent, and has no way
3. **Save**.
4. Press **Check the link** on the TEST row. It asks TEST, server to server, and says what to fix if anything is wrong: TEST cannot be reached, runs an older version, thinks it is a home, has the wrong home address, is called something else, or holds another key. All green, and it works.



LIVE's Systems card: TEST, its address, its color, whether the scanners may switch, and Check the link.

3 — Who may use TEST

Settings → Logins → Supervisor logins, the **Systems** column:




LIVE is ticked for everyone; tick TEST for each login that should have it. Admins always have both.

- Tick **TEST** for a login and it may switch; untick it and it may not (within twelve hours — a switched sign-in lasts a shift).
- **Add login** has *may also switch to TEST*, to give it as the login is made.
- The same ticks are on the Systems card as *Who may use each system*; the two are one list.

4 — Logins someone made on TEST: copy them to LIVE

If people were set up on TEST before it was linked, bring them over instead of making them again.

1. On LIVE: **Settings → Logins → Copy logins from TEST**.
2. LIVE asks TEST (signed with the link key) for its logins and lists them first — nothing is copied by looking:




Copy logins from TEST: what would happen to each.

IT SAYS	IT MEANS
copied here, same password (ticked)	New to LIVE. Comes over with its name, email, role, pages and password, and TEST ticked
already a login here — left as it is	LIVE has that username; the LIVE login is never changed
never chose a password	An invite nobody took up on TEST: add them on LIVE and invite them
TEST's superadmin (not ticked)	TEST's own setup login. Tick it only if it should be on LIVE too


1. Untick anyone who should not come over and press **Copy the ticked logins**. They sign in on LIVE with the password they use on TEST. The log records who was copied.

People who only ever switched over from LIVE are not listed — they are LIVE's already.

5 — Switching in the office




LIVE — the green ring, and *Switch to...* at the bottom of the sidebar




TEST — the orange ring, and the *TEST — not the live system* bar with **Back to LIVE**

- **Sign in on LIVE.** Its sign-in box has **Sign in to: LIVE / TEST** — pick TEST to land there.
- **Switch to… TEST** at the bottom of the sidebar opens TEST on the same page, signed in as you, with the same role and pages.
- **Back to LIVE** on TEST's bar (or *Switch to... LIVE*) goes home, still signed in.
- On TEST, *Settings → Scanners* registers nothing, and TEST's own sign-in box says to sign in on LIVE.

6 — Scanners




On LIVE: green band and ring, *System: LIVE · TEST*



On TEST: orange band and ring, *Back to LIVE*

1. **Register every gun on LIVE** — *Settings → Scanners → Scanner setup*, print its setup card, open its link on the gun — as always.
2. With *On the scanners* at **LIVE and TEST**, the gun's sign-on screen shows **System: LIVE | TEST**. One tap takes it to TEST under its own name and link.
3. **Back to LIVE** on TEST's sign-on screen brings it home.
4. A gun with **counts still waiting to send** may not switch until they have gone — they belong to the system they were counted in.

On TEST, **Scanner setup** has no *Add scanner*, setup cards, *Copy* or *Reset link* — just the guns that have come over, and a note pointing to LIVE:



TEST's Scanner setup: the guns that came over from LIVE.

Reset or remove a gun on LIVE. Removing one from TEST is harmless: it comes back the next time it switches.

7 — When something is not right

YOU SEE	WHAT IT MEANS	WHAT TO DO
Back to LIVE does nothing, or says *this system's own address*	TEST's `SYSTEM_HOME_URL` holds TEST's address	Set it to LIVE's address on the TEST service and redeploy TEST
Switching to TEST fails	The link is not set up right	On LIVE, **Check the link** on the TEST row and do what it says
…refuses a hand-off… link key	The two hold different keys	Copy LIVE's key into TEST's `SYSTEM_LINK_KEY` (no spaces, no quotes), redeploy
calls itself DEV, but it is listed here as TEST	The names differ	Set `SYSTEM_NAME=TEST` on TEST, or rename the row on LIVE
this login may not use TEST	TEST is not ticked for that login	Settings → Logins → Systems column
No *Switch to…* in the sidebar	No other system is listed, or this login has none ticked	Settings → Site & systems → Systems; Settings → Logins
The gun shows no *System* row	*On the scanners* is LIVE only, or TEST only	Choose **LIVE and TEST** on LIVE's Systems card and save
A gun goes to TEST (or back to LIVE) by itself	*On the scanners* is one system only	As meant. Choose **LIVE and TEST** to let the guns switch
The gun says *the scanners are on TEST now* and will not sign on	TEST only is chosen, and its counts are still sending	Get it into Wi-Fi; it goes when they have sent
N counts are still on this scanner	Counts waiting to send	Let them send (Wi-Fi), then switch
scanners are registered on LIVE	Someone tried to add a gun on TEST	Add it on LIVE, then switch it to TEST from the gun