



Hazz Karaoke Hoster Complete Illustrated User Manual

Every screen button workflow and live show function for version 0.80

This manual explains the complete application in plain language. Labelled screenshots identify the controls you use during a show, diagrams show how information and media move through Hazz, and reference tables explain every visible button, menu command and setting.

The screenshot shows the Hazz Karaoke Hoster interface. At the top, there's a header with 'KARAOKE HOSTER' and 'v0.80.22'. Below it, there are tabs for 'SEARCH', 'KARAOKE', and 'MUSIC'. The main area is divided into three sections: 'DECK 1' on the left, 'KARAOKE DECK' in the center, and 'DECK 2' on the right. Each deck has a 'No track loaded' status and a 'DECK READY' indicator. The 'KARAOKE DECK' section includes a 'KARAOKE SINGERS LIST' and a 'KARAOKE PREVIEW' section at the bottom. Numbered callouts identify the following features:

- 1: Menus for Library, Import, Display and Show
- 2: Search mode and search text
- 3: Music Deck 1 controls
- 4: Karaoke Deck and transitions
- 5: Music Deck 2 controls
- 6: Deck 1 playlist
- 7: Singer rotation and requests
- 8: Deck 2 playlist
- 9: Private host preview

Figure 1 The complete live console and its nine working areas

Windows x64 | Visual Studio 2026 | September 2026

How to use this manual

Read the first three sections before your first show. During a show, use the labelled figures to find a control quickly and the tables to confirm what it changes. The final sections cover imports, recovery and troubleshooting.

The safest operating rule

Keep the host console on Display 1. Send only the audience window to Display 2. Press TV before the show and confirm that the singer screen appears on the correct display. Hazz deliberately avoids placing one-click fullscreen output on Display 1.



Figure 2 Button colours stay consistent across the console

Contents

Control or function	What it does
1 First show setup	Connect displays and sound, import libraries, and test one karaoke and one music track.
2 Live console map	Understand the three main columns and the top search area.
3 Menus	Use every Library, Import, Display and Show command.
4 Search	Find karaoke or music and route the results.
5 Music decks	Play, pause, seek, crossfade and manage playlists.
6 Karaoke deck	Load singers, play karaoke, change key, fix sync and Fade Stop.
7 Singer rotation	Add singers, requests, history, hold, skip and reorder.
8 Single Deck mode	Use Deck 2 as a staging side list.
9 Audience display	Set Display 2, backgrounds, GIFs, video, logo and scroller.
10 Libraries and imports	Browse, rescan, back up and migrate data from other software.
11 Supporting windows	Use song history, archive, playlist and import dialogs.
12 Live workflows	Follow complete show, interval music and VJ sequences.
13 Recovery	Protect a long show and recover after interruption.
14 Shortcuts and troubleshooting	Use keyboard controls and fix common problems.
15 Visual Studio build	Produce the one-file Release output.

1 First show setup




Figure 3 The recommended order for a live show

Before guests arrive

1. Connect the host computer to the sound system and Windows Display 2.
2. In Windows display settings choose Extend these displays.
3. Open Hazz and choose Import, Import Karaoke Folders. Select the folders that contain karaoke files.
4. Choose Import, Import Music or Video Folders. Select background music and music-video folders.
5. Search for one karaoke track and one music track. Play both briefly to confirm codecs, sound routing and file access.
6. Press TV. Confirm that only the audience display appears on Display 2 and that the host console remains visible on Display 1.
7. Choose Show, New Show when you are ready to clear the working rotation and begin the event.

Recommended live-show checks

- Use mains power and disable Windows sleep for the duration of the event.
- Keep media drives connected until Hazz has closed.
- Keep a recent database backup.
- Test the persistent logo and background slideshow before guests can see the screen.
- Leave enough free disk space for the database, logs and temporary extracted ZIP karaoke files.

2 Live console map




Figure 4 Labelled map of the host console

Control or function	What it does
1 Main menus	Library manages indexed media and backups. Import adds media and migrates other programs. Display controls the audience output. Show changes the working layout.
2 Search bar	Choose Karaoke or Music, then type artist, title, manufacturer, disc ID or folder text.
3 and 5 Music decks	Independent background-music players with LED title displays, queues, seek controls and volume.
4 Karaoke Deck	The singer performance player, key and graphics timing controls, music transition controls and silence tools.
6 and 8 Music playlists	The remaining order for each deck. Drag rows to reorder and use the footer buttons to save, remove or load lists.
7 Singer list	The live rotation, request counts, key and sync values. Drag rows to reorder.
9 Karaoke preview	A private host preview. Hide it when you want more room for the singer rotation.

Automatic scaling

The entire console scales to the available window and display. Buttons remain accessible at small resolutions. If you resize the window during a show, allow the layout a moment to settle before dragging tracks.

3 Main menus

Library menu

Control or function	What it does
Browse Library	Opens the paged library browser for the complete indexed karaoke or music collection.
Music History or Lists	Opens played music history and saved playlists. Load selected items or a complete list into a music deck.
Database Open Database Folder	Opens the folder that contains the Hazz SQLite database and related data files.
Database Backup Database	Copies the database to a location you choose. Back up before a large import.
Rescan Watched Folders	Checks configured library folders for added, changed or removed files.
Auto watch New Files ON	Shows that Hazz is watching imported library folders for new media.

Import menu

Control or function	What it does
Import Karaoke Folders	Adds folders as karaoke sources and scans supported ZIP, CDG, audio and video karaoke.
Import Music or Video Folders	Adds interval music and music-video folders. A detected video can play on the singer display through VJ output.
Import BPM Studio	Migrates supported BPM Studio library data using its dedicated importer.
Smart Import Import Singer History	Imports singers and performance history from CSV, TSV, JSON, XML, SQLite, MDB, ACCDB or KDB data.
Smart Import Detect from File	Select an export, playlist or database. Hazz detects supported software and shows a preview.
Smart Import Detect from Application Folder	Select another program folder when its data is spread across several files.
Smart Import VirtualDJ database xml	Imports a VirtualDJ XML database directly.
Import Karma Singers or History	Imports Karma singer and history information.
Import Karma Complete Karaoke Library	Imports the supported Karma karaoke catalogue.
Supported Applications	Informational entries listing the recognised programs and playlist formats.

Display menu

Control or function	What it does
Open Audience Display	Opens the singer screen as a movable window for checking.
Send Full Screen To	Lets you choose a specific connected display.
Send Windowed To Preferred Display	Moves the audience window to the selected display without fullscreen.
Full Screen On Preferred Display	Makes the audience window borderless on the selected display.
Windowed or Move and Resize	Returns the audience window to a normal movable window.
Overlay or Next Singer Settings	Opens the complete audience information, background, logo and Kamikaze settings panel.

Show menu

Control or function	What it does
New Show	Clears the current working show after confirmation and begins a clean session.
Karaoke Only Mode	Hides both music decks and expands the karaoke and singer workspace.
Single Deck and Side List Mode	Keeps Deck 1 as the only music player and converts Deck 2 into a staging list.
Toggle Karaoke Preview	Shows or hides the private preview and gives the singer list more vertical room.

4 Search and drag and drop




Figure 5 Search results can be routed without covering their destination

Control or function	What it does
Karaoke	Searches CDG, ZIP, audio karaoke and video karaoke together.
Music	Searches ordinary music and music videos. The result panel opens over the centre so both music playlists remain reachable.
Music Video	Searches only video files imported into the music library. It supports the same multi-select and deck actions as Music search.
Search box	Searches artist, title, manufacturer, disc ID and indexed folder text as you type.

Control or function	What it does
Select All	In Music search, selects every visible result.
Add to Deck 1	Adds the selected music result or selected batch to Deck 1.
Add to Deck 2	Adds the selected batch to Deck 2, or to the side list in Single Deck mode.
Close	Closes the results panel without changing queued tracks.
Cancel Import	Appears during an active import and asks the importer to stop safely.

Mouse selection

- Click selects one row.
- Shift click selects a continuous range in Music search.
- Ctrl click adds or removes individual Music rows.
- Ctrl A selects all visible Music results.
- Drag a karaoke result onto a singer row to add a request.
- Drag a karaoke result directly onto the Karaoke Deck to load it without starting playback.
- Drag Music results to Deck 1, Deck 2 or the side list. The selected order is preserved.

Space bar quick play

While Music or Music Video search has focus, press Space to play the highlighted result immediately without adding it to a deck. A quick-played video is also sent to the audience display. Press Space again to stop quick play.

Broken media

If a file is missing or Windows cannot decode it, Hazz marks it as broken, stores the failure reason and colour-codes its row. Fix or replace the file before the show. Healthy recycled rows are cleared so a broken colour does not spread to other tracks.

5 Music decks




Figure 6 Music Deck 1 controls. Deck 2 uses the same controls in normal mode

Control or function	What it does
LED display	Scrolls the state, artist and title. READY means no track is loaded, NOW PLAYING means audible, PAUSED means position is retained and CUED means loaded at zero volume.
Add Files	Adds supported audio or video files directly to that deck queue.
Play	Starts the selected or next scheduled track. If paused, Play resumes from the exact stored position.
Pause or Resume	First press pauses at the exact position and changes the label to Resume. The next press continues from that position.
Stop	Stops the deck and removes the already-played entry from the live queue.
Shuffle	Randomises remaining tracks. A currently playing row stays at position 1.
Seek timeline	Drag or click to move to an exact time. While dragging, Hazz shows the target time. Arrow, Page, Home and End keys also seek.
Time display	Shows elapsed, remaining and total duration when Windows reports a duration.
Volume	Sets that deck level. Crossfades multiply this value rather than replacing it.
Save Playlist	Saves the remaining unplayed order under a name.
Remove Selected	Removes selected unplayed rows without deleting media files or library records.
Load Playlist or History	Loads a saved Hazz playlist, imported playlist or played music history into the deck.

Playlist behaviour

Each playlist is a live queue. When a track starts, it becomes row 1. Drag unplayed rows to change the future order. The active row is protected. Hazz records played music so the history can be reused later.

Automatic crossfade

When Auto Crossfade is enabled, Hazz starts the other deck near the end of the current track and fades between them using the selected time. Fade Now starts that transition immediately. Automatic crossfade never advances a deck that you deliberately paused.

6 Karaoke Deck




Figure 7 Labelled Karaoke Deck and music-transition controls

Control or function	What it does
Load Next Singer	Loads the first singer and their next queued request.
Load File	Opens a file picker for a karaoke package or supported karaoke media file.
TV	One-click command that sends the audience and karaoke output fullscreen to Display 2. It does not fall back to Display 1.
Play	Starts the loaded karaoke track and activates karaoke presentation on the audience screen.
Pause or Resume	Pauses the karaoke track and audience video at the same position. Press again to resume.
Fade Stop	Fades karaoke audio down over 1.5 seconds, ends the performance, then fades the scheduled music back in over 1.5 seconds.
Find Alternative	Loads the next matching version with the same artist and title when another manufacturer or disc version exists.
Kamikaze	Randomly assigns a karaoke-library song to the next singer. Press again before playback for another random choice.
Key minus and plus	Changes the singer key from minus 5 to plus 5 semitones. Use only when requested.

Control or function	What it does
Key Reset	Returns the key to zero.
CDG minus 0.25 seconds	Shows CDG graphics earlier in quarter-second steps.
CDG plus 0.25 seconds	Shows CDG graphics later in quarter-second steps.
CDG Reset	Returns the graphics timing offset to zero.
Auto Crossfade	Enables the two music decks to alternate between tracks.
Crossfade Time	Sets the normal music crossfade from 0.5 to 12 seconds.
Fade Now	Immediately begins a music-deck crossfade when both decks have material.
Play Music	Stops karaoke if needed and resumes the interval-music plan.
Crossfade indicator	Shows the live balance between Deck 1 and Deck 2. It is an indicator rather than a manual fader.
Skip Silent Intro	Automatically jumps past leading silence at the start of karaoke. It does not skip quiet sections inside the song.
Skip Silence Now	Finds the next audible point when the current playback position is in silence.
Pre roll	Keeps the selected amount before the detected audio so the first lyric is not clipped.

Supported karaoke drops

You can drop a karaoke search result or supported ZIP, CDG, audio or video file directly onto the Karaoke Deck. Hazz loads it for checking and does not start it automatically. A drop cannot interrupt a song already playing; press Fade Stop first.

7 Singer rotation and requests




Figure 8 Singer list controls and live rotation

Control or function	What it does
Singer search box	Type part of a name to search every saved singer. Opening the arrow shows about 100 recent singers immediately instead of rendering thousands.
Add Singer	Adds the typed or selected singer to the current show. Existing history is preserved.
Singer row	Shows status, singer name, request and performance counts, queued songs, preferred key and graphics sync.
Move Up or Move Down	Moves the selected singer one place while preserving their requests.
Set As Next	Moves the selected singer to the first playable position.
Remove	Removes the singer from this show after confirmation. Saved singer history remains in the database.
Hide Preview	Hides the private karaoke preview and enlarges the rotation list.

Singer right-click menu

Control or function	What it does
Add Song or Search	Opens song selection for that singer.
Open Songs and History	Shows queued requests and previous performances.
Hold Singer	Temporarily prevents automatic Load Next Singer selection while keeping the singer visible.
Skip Once	Moves the singer to the bottom once, then restores normal rotation behaviour.
Set As Next	Moves this singer to the next position.
Move Up, Down or Top	Changes the rotation order.
Kamikaze for This Singer	Assigns a random library song to the chosen singer.
Clear Queued Songs	Removes current requests while keeping the singer and history.
Edit Name or Notes	Changes the display name or private notes.
Remove From Show	Removes the singer from the current show only.

Selecting a previous singer

The picker initially returns the most recently used singers. Type a name to search the full database asynchronously. Search is debounced and cancelled when the text changes, and results are capped at about 100, sorted by recent use then name. Selecting a singer still loads their complete song and history information.

8 Single Deck and Side List mode




Figure 9 Normal two-deck operation and Single Deck mode

Choose Show, Single Deck and Side List Mode when you want only one music player. Deck 2 loses its LED, transport, seek and volume controls and becomes a staging list. Automatic display scaling cannot make those hidden player controls reappear.

Control or function	What it does
Add Files	Adds music or video files to the side list.
Load List	Loads a saved playlist or music-history list into the side list.
Save List	Stores the current side-list order.
Select All	Selects every track in the side list.
Move Up or Move Down	Moves the selected row or selected block one position while preserving order.

Control or function	What it does
Send to Deck 1	Moves selected tracks to the end of Deck 1 in their current order.
Shuffle List	Randomises the side-list order.
Remove Selected	Removes selected rows without deleting their files.
Clear List	Confirms and removes every side-list row without deleting files or library records.
Drag to Deck 1	Moves selected side-list tracks to Deck 1 by drag and drop.

9 Audience and singer display




Figure 10 Every audience-display settings group

Opening and placing the audience window

1. Choose Display, Open Audience Display for a movable preview.
2. Use Send Full Screen To when you want to choose a particular monitor.
3. Use TV for the usual one-click Display 2 fullscreen command.
4. Use Windowed or Move and Resize when checking projector overscan or cabling.

Next singer and colours

Control or function	What it does
Show next 4 singers	Shows up to four upcoming singers between songs.
Show songs	Adds each upcoming request when available.
Singer font, size and position	Controls the typeface, text size and one of six screen positions.
Heading	Chooses the Next Singers heading colour.
Position number	Chooses the rotation-number colour.
Singer	Chooses singer-name colour.
Song or Artist	Chooses request text colour.
Rotation	Chooses the full rotation colour in the moving scroller.
Venue Message	Chooses the optional venue-message colour.

Scroller

Control or function	What it does
Full singer rotation scroller	Enables the complete numbered rotation ticker.
Scroller text	Appends an optional venue message after the rotation.
Font and size	Choose a typeface and readable audience-screen size.
Speed	Sets movement from 40 to 250 pixels per second.
Position	Moves the scroller to the top or bottom. Next-singer information leaves room automatically.

Background image GIF and video slideshow

Control or function	What it does
Singer-view background	Enables the selected background between karaoke songs.
Image GIF or Video	Selects one still image, animated GIF or muted video.
Choose Folder	Uses all supported images, GIFs and videos in a folder as a slideshow. Each receives a one-minute slot.
Clear	Removes the selected background source.
Fit	Shows the entire image or video with unused space if aspect ratios differ.
Fill crop	Fills the screen and crops edges where necessary.
Stretch	Fills the entire screen without preserving the original aspect ratio.
Center	Shows the source at its original size in the centre.
GIF speed	Adjusts animated GIF playback from 0.25 times to 4 times. The slideshow slot remains one minute.

Persistent logo and Kamikaze message

Control or function	What it does
Persistent audience logo	Keeps an enabled transparent logo above backgrounds, CDG and video karaoke.
Choose Logo	Selects a PNG or supported image.
Logo position	Places it in a corner, edge centre or screen centre.
Logo width	Changes its displayed width from 60 to 800 pixels.
Kamikaze text	Changes the message shown after a random assignment.
Kamikaze font size and colour	Controls the message appearance.
Close	Closes the settings panel. Changes are already applied live.

10 VJ music video output




Figure 11 How music-video picture and audio are routed

Import music-video folders through Import, Import Music or Video Folders. Use the Music Video button at the top to search only video files. When Deck 1, Deck 2 or Space-bar quick play starts a video, Hazz mirrors its picture to the audience display. The audience copy is muted, while the player supplies the normal show audio.

While a music video is visible, the next-singer list, rotation scroller, venue message, background media and persistent logo are hidden. They return automatically when the video ends, so the picture remains unobstructed.

Control or function	What it does
Play	Starts both the audible music deck and muted audience picture.
Pause or Resume	Pauses and resumes both copies at the same position.
Seek	Moves both copies to the selected time. Periodic synchronization corrects visible drift.
Stop	Clears the audience music video.
Crossfade	An incoming video becomes the audience picture as its deck starts.
Karaoke starts	Karaoke picture takes priority and the music video pauses.
Karaoke ends	The music video returns when interval music resumes.
Audience display closed	Music audio can continue; reopening the audience display restores the current video state.

11 Libraries and imports




Figure 12 Safe read-only Smart Import sequence

Supported smart-import sources

Hazz recognises common exports and databases from MediaMonkey, CompuHost, Lyrx, KaraFun, Siglos and PowerKaraoke, VirtualDJ, OpenKJ, Karma, BPM Studio, PCDJ DEX, rekordbox, iTunes, SongBookDB, kJams, JustKaraoke, Sax and Dottys, TriKaraoke, Serato, Mixxx, ZipDJ, Winamp, WPL, XSPF, ASX, M3U and CSV or JSON data where supported fields can be identified.

Smart import preview controls

Control or function	What it does
Media mode	Chooses how imported rows are classified when the source is ambiguous.
Verify files exist	Checks every path during import. Enable it when accuracy matters more than speed.
Preview	Shows the detected program, source format, record count and sample records before writing to Hazz.
Import Into Hazz	Copies recognised records into the Hazz database.
Cancel	Closes the preview without importing.

MediaMonkey notes

Close MediaMonkey before reading its database. Hazz registers the private MediaMonkey collation needed for read-only queries and avoids its unsupported mm tokenizer. Drive-relative paths are combined with MediaMonkey drive information. Large imports reuse prepared database commands and batch progress updates for speed.

Singer history import

Singer history import previews detected columns and sample performances. It preserves available dates, key changes and times-sung counts, links matching songs from the Hazz library, retains unmatched historical descriptions and avoids duplicating the same imported records on repeat import.

12 Library Browser and supporting windows

Library Browser

HAZZ LIBRARY BROWSER — VIRTUAL FOLDERS

Folders contain links. Your original music and karaoke files never move.




Figure 14 Virtual folders: organise library links without moving media files

Control or function	What it does
Karaoke or Music	Switches the browser between indexed media types.
Filter	Filters artist, title, manufacturer or disc ID. Leave blank to browse everything.
Sort	Chooses the active sort field.
Descending	Reverses the selected sort order.
First and Previous	Moves backward through paged results.
Page and Go	Jumps directly to a page number.
Next and Last	Moves forward through results.
Add to Selected Singer	Adds a selected karaoke item as a request.

Control or function	What it does
Add to Deck 1 or Deck 2	Adds selected Music items to a deck.

Virtual folders: the basic idea

Virtual folders are named collections of links to tracks already in the Hazz library. They work like crates or categories: 80s, Rock, Jingles, Requests or any structure you choose. Adding, removing, emptying or deleting a virtual folder never moves or deletes the original audio, video, ZIP or CDG files. One track can belong to several virtual folders.

Create folders and subfolders

1. Choose Library, Browse Library. The window opens maximised so every folder control is visible.
2. Press New Folder to create a top-level folder such as 80s or Jingles.
3. To create a nested folder, select its intended parent and press New Subfolder. Enter a name such as Rock.
4. Use Rename to change only the selected folder name. The links and media files remain unchanged.

Add one track or many tracks

1. Select All Library Tracks or the source virtual folder. Choose Karaoke or Music and use the search and sort controls if required.
2. Click one row, Ctrl-click separate rows, Shift-click the first and last rows of a continuous range, or press Ctrl+A to select all visible results.
3. Press Add Selected to Folder. Choose the destination by its full nested path, then press Add Tracks. You may also drag the selected rows directly onto a folder in the left tree.
4. Open the destination folder to check the result. Adding the same track twice does not create a duplicate link.

Use and maintain a virtual folder

Control or function	What it does
All Library Tracks	Returns to the whole indexed library and clears the virtual-folder filter.
Folder tree	Selects the active folder. A parent shows its own directly assigned tracks; open a child to see that child collection.
Add Selected to Folder	Opens a destination picker. This is the clearest method for moving a large multi-selection into a nested folder.
Remove from Folder	Removes selected links from the open folder. The library entries and files remain.
Empty	Removes every direct track link from the selected folder after confirmation. Subfolders remain.
Delete Selected Folder	Deletes the selected folder, its child folders and their virtual links after confirmation. Media files remain.
Folder count	Shows the number of directly linked tracks. The visible Karaoke or Music count can be lower when that media filter is active.

Import BPM Studio virtual folders

1. Close BPM Studio so its archive files are stable.
2. In Hazz choose Import, Import BPM Studio and select the BPM Studio data or archive folder.
3. Review the preview counts and confirm the fast read-only import.

4. Hazz imports playlists and history, reads recoverable .GRP and .PLG archive groups, and creates them below a BPM Studio virtual folder. Physical subdirectories become nested Hazz folders.

5. Open Library, Browse Library and expand BPM Studio to check the imported groups. Unreadable proprietary group files are listed in the completion report; source data is never changed.

Import VirtualDJ and other program folders

1. Close the other program so its files are stable.
2. Choose Import, Smart Import, Detect from Application Folder.
3. Select the complete application data/export folder. For VirtualDJ, select the home folder containing database.xml plus MyLists or Playlists.
4. Review the detected program and sample, then confirm the read-only import.
5. Open Library, Browse Library and expand the folder named after the detected application. VirtualDJ My Lists, Rekordbox playlist trees and nested M3U, PLS, XSPF or WPL exports retain their folder structure.

Virtual-folder examples

Control or function	What it does
80s / Rock	Create 80s, select it, create Rock as a subfolder, then add the chosen tracks to 80s / Rock.
Jingles / Station IDs	Keep short show elements separate from ordinary music while leaving the actual files in the original jingle folder.
Party / Floor Fillers	Add a track here and also to 80s or Rock; Hazz stores separate links to the same library item.
BPM Studio / ...	Created by BPM Studio import from recoverable archive groups. You can browse and use these like folders created in Hazz.

Virtual-folder troubleshooting

- If Hazz asks you to choose a folder, use Add Selected to Folder and select the destination in the picker.
- If the folder is empty, confirm the correct Karaoke or Music tab is active and clear the search box.
- If a parent appears empty, open its child folder; parent and child collections are deliberately separate.
- If controls are clipped, maximise the Library Browser. v0.80 also changes the folder panel width for smaller displays.
- If an imported BPM group is missing, check the completion report. Some proprietary group files contain no recoverable media paths.

Music History and Lists

Control or function	What it does
Refresh	Reloads played history and saved playlists.
Load Selected or Playlist to Deck 1 or 2	Loads the selected history row or complete saved playlist.
Load Full History to Deck 1 or 2	Loads every playable track currently shown, newest first.
Close	Closes the archive window.

Singer Songs and History

Control or function	What it does
Song Up or Song Down	Changes request order for this singer.
Key minus plus and Reset	Stores a preferred key for the selected request.
Sync minus 0.25 plus 0.25 and Reset	Stores the CDG graphics timing correction for the selected request.
Remove Song	Removes the selected current request.
History Search	Filters the singer previous performances.
Clear	Clears the history filter text.
Close	Closes the singer detail window.

Folder and import progress windows

Control or function	What it does
Add Folder	Adds another source folder to the pending import.
Remove Selected	Removes the selected pending folder.
Clear	Clears the pending folder list.
Import All	Starts scanning every listed folder.
Cancel	Cancels the folder selection or requests cancellation of a running import.
Playlist name Save	Stores a playlist under the typed name.
Singer edit Save	Stores the singer name and private notes.

13 Complete live workflows

Add a singer and play their request

1. Type the singer name in the singer search box. Select an existing singer or type a new name.
2. Press Add Singer.
3. Choose Karaoke search and type the artist or title.
4. Drag the result onto the singer row. Add more requests in the required order.
5. Press Load Next Singer. Confirm the singer, song and preview.
6. Press Play.
7. At the end press Fade Stop. Hazz fades karaoke down, ends the performance and fades interval music in.

Run interval music on two decks

1. Choose Music search.
2. Shift click a range or Ctrl click individual tracks.
3. Drag or add the selection to Deck 1 or Deck 2.
4. Press Play on one deck.
5. Enable Auto Crossfade and choose a transition time if you want the decks to alternate.
6. Use Pause when you need to retain an exact position. Use the timeline to seek.

7. Starting karaoke preserves the music plan. Play Music resumes it later.

Run interval music with one player

1. Choose Show, Single Deck and Side List Mode.
2. Add the immediate queue to Deck 1.
3. Add later choices to the right side list.
4. Select tracks and use Send to Deck 1, or drag them into Deck 1.
5. Deck 1 advances through its queue automatically.

Use a music video

1. Import its folder as Music or Video.
2. Open the audience display and send it to Display 2.
3. Press Music Video at the top and search for the artist or title.
4. Add the video to a music deck and press Play, or press Space for quick play.
5. Confirm its picture appears on Display 2 with no singer lists or scrollers covering it.
6. Use Pause, seek and Stop normally. Karaoke automatically replaces it when a singer begins.

14 Long show stability and recovery




Figure 13 Recovery after an unexpected interruption

Protection built into Hazz

- Timer and display-update faults are isolated so one failed refresh does not end the show.
- The live singer rotation and music queues are checkpointed every two minutes.
- SQLite uses write-ahead logging and contention handling for searches, imports and history writes.
- Library watcher and slideshow work is bounded to protect memory.
- Media resources are explicitly released when windows close.
- Diagnostic logs are size-limited and old logs are removed.

If Hazz closes unexpectedly

1. Restart Hazz.
2. Accept restoration of the previous rotation and unplayed music queues when offered.
3. Check which track was active before continuing.
4. Press TV and confirm the audience output is on Display 2.
5. Load or resume the next correct item.

Normal shutdown

Close the main window and answer Yes to the shutdown confirmation. Wait for Hazz to close before disconnecting media drives or shutting down Windows.

15 Keyboard and mouse shortcuts

Control or function	What it does
Space in Music or Music Video search	Quick-plays the highlighted result; press again to stop.
Shift click	Selects a continuous range of Music search results.
Ctrl click	Selects or deselects individual Music results.
Ctrl A	Selects all visible Music results.
Delete in music playlist	Removes selected unplayed rows.
Drag music rows	Reorders a queue or moves selected tracks between valid lists.
Drag karaoke result	Adds it to a singer or loads it on the Karaoke Deck.
Seek slider arrows	Moves the music position in small steps.
Seek slider Page Up or Page Down	Moves the music position in larger steps.
Seek slider Home or End	Jumps to the beginning or end.
Singer right click	Opens hold, skip, history, order, notes and Kamikaze actions.
Window resize	Causes the console to rescale so controls remain visible.

16 Troubleshooting

Control or function	What it does
No audience picture	Open Display, Open Audience Display. Verify Windows Extend mode, then use TV or Send Full Screen To and choose Display 2.
Audience screen covers host controls	Return it to Windowed mode and explicitly send it to Display 2. Do not mirror Windows displays.
A track will not play	Read the broken-file reason. Confirm the path, drive connection and installed Windows codec. Repair or replace the file.
MediaMonkey import fails	Close MediaMonkey, select its real database, and use Smart Import. Hazz does not use the unsupported mm tokenizer.
MediaMonkey path points into AppData	Reimport using the current importer so drive-relative paths are reconstructed from MediaMonkey drive data.
Music Pause appears to stop	Press the same Pause button, now labelled Resume, or press Play. It should continue from the stored position.
CDG lyrics early or late	Use quarter-second CDG timing buttons. Save a per-song correction in singer history when appropriate.
Karaoke starts before lyrics	Enable Skip Silent Intro or press Skip Silence Now, then adjust pre-roll.
Previous singer arrow was slow	Use the current picker. It loads a capped recent list and searches the full database asynchronously.
Controls are missing	Maximise or resize the host window. Hazz rescales the console. Confirm Karaoke Only or Single Deck mode is not enabled unintentionally.
Visual Studio makes many files	Use Release and x64, then Rebuild Solution. Run the packaged EXE from the top-level RELEASE folder rather than the normal bin folder.

17 Visual Studio 2026 build

Required build

1. Open HazzKaraokeHoster.sln in Visual Studio 2026.
2. Select Release and x64.
3. Choose Build, Rebuild Solution.
4. Wait for the release packaging project to finish.
5. Open RELEASE, HazzKaraokeHoster.
6. Run Hazz Karaoke Hoster.exe. That folder should contain exactly one executable.

If the release folder is missing

Close any running Hazz copy and rebuild. If Visual Studio reports a child-node or publishing failure, use BUILD-EXE.cmd from the source root. Review the first publish error rather than the later MSBuild shutdown messages. The normal bin folder contains framework build files and is not the packaged release.

Release verification

- Confirm the file version is 0.80.0.0.
- Confirm the release folder contains one EXE.
- Open the application and test Display 2 before using the build live.
- Keep the SHA-256 checksum file with downloaded release packages.

18 One page show checklist

Control or function	What it does
Before doors	Power connected; Windows sleep disabled; Display 2 extended; sound tested; drives connected; database backed up.
Audience	TV tested; background and scroller readable; logo correct; no host controls on Display 2.
Libraries	Karaoke search works; Music search works; one CDG and one video tested; broken rows reviewed.
Music	Queues loaded; volume set; Auto Crossfade and time checked; Single Deck mode set as intended.
Singers	New Show started; first singers added; requests loaded; key and sync values checked.
During show	Use Load Next Singer; confirm preview; Play; Fade Stop; avoid disconnecting drives.
After show	Save any required playlists; close Hazz normally; wait for shutdown; then disconnect drives.

Keep this checklist near the host computer until the setup and shutdown sequence becomes routine.

BPM Studio large archive import

Version 0.80 improves the dedicated BPM Studio importer for very large libraries. BPM source files remain read-only, and the import window shows the work that remains.

Duplicate and repeat group files

1. Select the BPM Studio data or archive folder once. Hazz searches it recursively for supported playlist, history, GRP and PLG files.
2. When several GRP or PLG files have the same filename, Hazz imports only the newest modified copy. If dates match, the larger copy is selected.
3. Hazz remembers a processed group by its full path, size and modified time. Repeat imports skip unchanged groups and read changed groups again.

Large import progress

The progress window moves through Reading, Indexing, Linking, Saving and Finalizing database. Song search data is indexed in bounded batches, and virtual-folder links are saved in 5,000-track batches. Wait for Import complete before starting another import or closing Hazz.

Cancel requests are checked between batches. If cancellation is requested during a database operation, allow Hazz to finish the current safe unit and roll back the unfinished transaction.