


Hazz Karaoke Hoster Dummy Guide

A simple step by step guide for running your first show

Windows x64 | Version 0.17.22 | September 2026



Hazz Karaoke Hoster

Read this first

This guide gives you the shortest safe route from opening Hazz to playing singers. Follow the steps in order during your first practice session. The Complete Manual explains every option in more detail.

The three rules

- Keep the Hazz controls on Display 1 and the audience picture on Display 2.
- Load and check the next singer before pressing Play.
- Do not disconnect karaoke or music drives while Hazz is open.

The ten minute setup

1. Connect your second screen or projector and set Windows to Extend these displays.
2. Open Hazz Karaoke Hoster.exe.
3. Choose Import, Import Karaoke Folders and select your karaoke folder.
4. Choose Import, Import Music Folders if you want interval music.
5. Press TV. The audience picture should appear full screen on Display 2.
6. Choose Show, New Show when you are ready to start a fresh night.

Add the first singer

7. Click the singer-name box in the centre.
8. Type the singer's name.
9. Press Add Singer.
10. Search in Karaoke mode for the requested artist or song.
11. Drag the result onto the singer's row.

Play the singer

12. Press Load Next Singer.
13. Read the singer and song shown in the Karaoke Deck.
14. Press the green Play button.
15. Use yellow Pause if needed.
16. Use red Fade Stop to lower karaoke for 1.5 seconds; returning music then fades in for 1.5 seconds.
17. To load without a singer assignment, drag a Karaoke search result or karaoke file directly onto the Karaoke Deck, check it, then press Play.

Keep the queue fair

18. Drag a singer to change the order, or use Move Up and Move Down.
19. Set As Next puts the selected singer first.
20. Right-click and choose Hold when a singer has gone outside.
21. Use Skip Once if they should be passed over only this time.

Use a previous singer

22. Open the singer-name dropdown. It opens with recent singers instead of loading thousands at once.

23. Type part of the name to search all saved singers.
24. Select the name and add them to tonight's rotation.
25. Open Songs and History to reuse one of their old songs.

Run interval music

26. Drag Music search results to Deck 1 or Deck 2.
27. Shift-click a range or Ctrl-click individual tracks, then drag the selection or use a deck button.
28. Press Select All or Ctrl+A to queue every visible result from a folder search.
29. Press the green Play button on a deck.
30. Pause keeps the exact position; press Pause or Play to resume. Drag the timeline to seek.
31. Import a music-video folder through Import, Import Music / Video Folders. Video tracks automatically appear full-screen and muted on the singer display while deck audio plays normally.
32. Enable Auto Crossfade if you want the decks to alternate.
33. For one-player operation, choose Show, Single Deck + Side List Mode. The right panel becomes a proper side list with Add, Load, Save, Select, Move, Send to Deck 1, Shuffle, Remove and Clear controls.
34. Starting karaoke pauses the music plan; Play Music resumes the next scheduled track.
35. In Music search, Space quickly plays the highlighted result and Space again stops it.

Make the audience screen look good

36. Open Display, Overlay and Next Singer Settings.
37. Choose whether to show the next four singers and their songs.
38. Choose a background image, GIF or silent video, or choose a whole slideshow folder.
39. Use Fit for the whole image, Fill for edge-to-edge cropping, or Stretch to fill everything.
40. Move the singer scroller to the top if it blocks artwork at the bottom.

If something goes wrong

41. No second-screen picture: press TV again and confirm Windows sees Display 2.
42. Missing file: reconnect the drive, then rescan the watched folder.
43. Red or broken song: choose another version; Hazz has marked the failed file so you can repair it later.
44. Lyrics early or late: use the CDG minus or plus 0.25-second buttons.
45. Wrong pitch: use Key minus or plus, then Reset when needed.
46. Cramped controls: maximise Hazz or hide the preview.

Finish safely

47. Let the current media stop.
48. Close Hazz from the main window.
49. Answer Yes to the shutdown question.
50. Wait until Hazz closes before disconnecting a library drive or shutting down Windows.

Quick control reference

Colour	Meaning
Green	Play or confirm
Red	Stop remove or clear
Yellow	Pause timing or reset
Blue	Load or navigate
Teal	Add or save
Purple	Special action shuffle fade or alternative

One page show checklist

- Display 2 tested
- Sound output tested
- Karaoke search returns songs
- Music decks tested
- Audience background and scroller checked
- Database backup current
- New Show started
- First singer and song loaded