

NVIDIA OptiX 7.5 – Programming Guide	
Copyright Information	
© 2022 NVIDIA Corporation. All rights reserved.	D
	Document build number 359426

Contents

	Preface	1
	Terms used in this document	1
1	Overview	3
2	Basic concepts and definitions	5
	2.1 Program	5
	2.2 Program and data model	5
	2.2.1 Shader binding table	6
	2.2.2 Ray payload	6
	2.2.3 Primitive attributes	7
	2.2.4 Buffer	7
	2.3 Acceleration structures	7
	2.4 Traversing the scene graph	7
	2.5 Ray tracing with NVIDIA OptiX 7	9
3	Implementation principles	. 11
	3.1 Error handling	. 11
	3.2 Thread safety	. 11
	3.3 Stateless model	. 11
	3.4 Asynchronous execution	. 11
	3.5 Opaque types	. 11
	3.6 Function table and entry function	. 11
4	Context	. 15
	4.1 Sending messages with a callback function	. 16
	4.2 Compilation caching	
	4.3 Validation mode	. 18
5	Acceleration structures	. 19
	5.1 Primitive build inputs	. 21
	5.2 Curve build inputs	. 24
	5.3 Sphere build inputs	. 25
	5.4 Instance build inputs	. 25
	5.5 Build flags	. 27
	5.6 Dynamic updates	. 27
	5.7 Relocation	. 28
	5.8 Compacting acceleration structures	. 30
	5.9 Traversable objects	. 32
	5.9.1 Traversal of a single geometry acceleration structure	. 32
5	5.10 Motion blur	. 33
	5.10.1 Basics	. 33
	5.10.2 Motion geometry acceleration structure	. 35
	5.10.3 Motion instance acceleration structure	. 35
	5.10.4 Motion matrix transform	. 37
	5.10.5 Motion scale/rotate/translate transform	. 37
	5.10.6 Transforms trade-offs	. 39

6	Pro	gram pipeline creation	41
	6.1	Program input	42
	6.2	Programming model	43
	6.3	Module creation	44
	6.4	Pipeline launch parameter	45
	6	5.4.1 Parameter specialization	46
	6.5	Program group creation	48
	6.6	Pipeline linking	51
	6.7	Pipeline stack size	52
	6	5.7.1 Constructing a path tracer	54
	6.8	Compilation cache	55
7	Sha	nder binding table	57
	7.1	Records	57
		Layout	
		Acceleration structures	
	7	7.3.1 SBT instance offset	59
		7.3.2 SBT geometry-AS index	
		7.3.3 SBT trace offset	
		7.3.4 SBT trace stride	
		7.3.5 Example SBT for a scene	
		SBT record access on device	
8		rves and spheres	
_		Differences between curves, spheres, and triangles	
		Splitting curve segments	
		Curves and the hit program	
		Spheres and the hit program	
	8.5	Interpolating curve endpoints	
	8.6	Back-face culling	
		Limitations	
9		y generation launches	
	-	nits	
		vice-side functions	
		Launch index	
	11.1	Trace	
		Payload access	
		Reporting intersections and attribute access	
	11.4		
		Undefined values	
	11.7	SBT record data	
	11.8		
		Vertex random access	
	1.10	Geometry acceleration structure motion options	
1	1.11	Transform list	85

11.12 Instance random access	. 87
11.13 Terminating or ignoring traversal	. 88
11.14 Exceptions	. 88
12 Payload	. 93
13 Callables	. 97
14 NVIDIA AI Denoiser	. 99
14.1 Functions and data structures for denoising	100
14.1.1 Structure and use of image buffers	102
14.1.2 Temporal denoising modes	103
14.1.3 Allocating denoiser memory	104
14.1.4 Using the denoiser	105
14.1.5 Calculating the HDR average color of the AOV model	108
14.1.6 Calculating the HDR intensity parameter	108
14.2 Using image tiles with the denoiser	109
15 Demand-loaded sparse textures	113
15.1 Motivation	113
15.2 Background	114
15.2.1 Sparse textures	114
15.3 Library overview	116
15.4 Texture fetch	116
15.5 Page request processing	118
15.6 Host-side library	
15.7 Implementation	120

Preface

DirectX Raytracing (DXR),¹ Vulkan² (through the VK_NV_ray_tracing extension) and the NVIDIA OptiXTM API³ employ a similar programming model to support ray tracing capabilities. DXR and Vulkan enable ray tracing effects in raster-based gaming and visualization applications. NVIDIA OptiX 7 is intended for ray tracing applications that use NVIDIA[®] CUDA[®] technology, such as:

- Film and television visual effects
- Computer-aided design for engineering and manufacturing
- Light maps generated by path tracing
- High-performance computing
- LIDAR simulation

NVIDIA OptiX 7 also includes support for motion blur and multi-level transforms, features required by ray-tracing applications designed for production-quality rendering.

Terms used in this document

This document and the OptiX API use abbreviations for the software components of OptiX.

The nine types of user-defined ray interactions, called *programs*, are abbreviated as follows:

Program type	Abbreviation
Ray generation	RG
Intersection	IS
Any-hit	AH
Closest-hit	СН
Miss	MS
Exception	EX
Direct callable	DC
Continuation callable	CC

The NVIDIA OptiX 7 program types resemble shaders in traditional rendering systems; the term "shader" is sometimes used in the names of API elements.

^{1.} https://microsoft.github.io/DirectX-Specs/d3d/Raytracing.html

^{2.} https://www.khronos.org/vulkan/

^{3.} https://developer.nvidia.com/optix/

The geometry of the scene to be rendered is optimized for ray tracing through *acceleration structures*:

Acceleration structure type	Abbreviation in this document	Abbreviation in the API
Geometry acceleration structure	geometry-AS	GAS
Instance acceleration structure	instance-AS	IAS
Acceleration structures in general		AS
Bottom-level acceleration structure (DXR and Vulkan)	BLAS	
Top-level acceleration structure (DXR and Vulkan)	TLAS	

The relationship of NVIDIA OptiX 7 programs and the elements of the acceleration structures with which they interact are defined in the *shader binding table*, abbreviated as "SBT". (Note that "shader" in this context refers to an NVIDIA OptiX 7 "program.") No other terms associated with the shader binding table are abbreviated.

Other abbreviations in the document include:

Term	Abbreviation
application programming interface	API
axis-aligned bounding box	AABB
graphics processing unit	GPU
high dynamic range	HDR
just-in-time	JIT
low dynamic range	LDR
multiple instruction, multiple data	MIMD
parallel thread execution	PTX
scaling, rotation, translation	SRT
streaming assembly [language]	SASS
streaming multiprocessor	SM

In this document and in the names of API elements, the "host" is the processor that begins execution of an application. The "device" is the GPU with which the host interacts. A "build" is the creation of an acceleration structure on the device as initiated by the host.

1 Overview

The NVIDIA OptiX 7 API is a CUDA-centric API that is invoked by a CUDA-based application. The API is designed to be stateless, multi-threaded and asynchronous, providing explicit control over performance-sensitive operations like memory management and shader compilation.

It supports a lightweight representation for scenes that can represent instancing, vertex- and transform-based motion blur, with built-in triangles, built-in swept curves, built-in spheres, and user-defined primitives. The API also includes highly-tuned kernels and neural networks for machine-learning-based denoising.

An NVIDIA OptiX 7 context controls a single GPU. The context does not hold bulk CPU allocations, but like CUDA, may allocate resources on the device necessary to invoke the launch. It can hold a small number of handle objects that are used to manage expensive host-based state. These handle objects are automatically released when the context is destroyed. Handle objects, where they do exist, consume a small amount of host memory (typically less than 100 kilobytes) and are independent of the size of the GPU resources being used. For exceptions to this rule, see "Program pipeline creation" (page 41).

The application invokes the creation of acceleration structures (called *builds*), compilation, and host-device memory transfers. All API functions employ CUDA streams and invoke GPU functions asynchronously, where applicable. If more than one stream is used, the application must ensure that required dependencies are satisfied by using CUDA events to avoid race conditions on the GPU.

Applications can specify multi-GPU capabilities with a few different recipes. Multi-GPU features such as efficient load balancing or the sharing of GPU memory via NVLINK must be handled by the application developer.

For efficiency and coherence, the NVIDIA OptiX 7 runtime—unlike CUDA kernels—allows the execution of one task, such as a single ray, to be moved at any point in time to a different lane, warp or streaming multiprocessor (SM). (See section "Kernel Focus"⁴ in the CUDA Toolkit Documentation.⁵) Consequently, applications cannot use shared memory, synchronization, barriers, or other SM-thread-specific programming constructs in their programs supplied to OptiX.

The NVIDIA OptiX 7 programming model provides an API that future-proofs applications: as new NVIDIA hardware features are released, existing programs can use them. For example, software-based ray tracing algorithms can be mapped to hardware when support is added or mapped to software when the underlying algorithms or hardware support such changes.

^{4.} https://docs.nvidia.com/cuda/cuda-gdb/index.html#kernel-focus

^{5.} https://docs.nvidia.com/cuda/

2 Basic concepts and definitions

2.1 Program

In NVIDIA OptiX 7, a *program* is a block of executable code on the GPU that represents a particular shading operation. This is called a *shader* in DXR and Vulkan. For consistency with prior versions of NVIDIA OptiX 7, the term *program* is used in the current documentation. This term also serves as a reminder that these blocks of executable code are programmable components in the system that can do more than shading. See "Program input" (page 42).

2.2 Program and data model

NVIDIA OptiX 7 implements a single-ray programming model with ray generation, any-hit, closest-hit, miss and intersection programs.

The ray tracing pipeline provided by NVIDIA OptiX 7 is implemented by eight types of programs:

Ray generation

The entry point into the ray tracing pipeline, invoked by the system in parallel for each pixel, sample, or other user-defined work assignment. See "Ray generation launches" (page 71).

Intersection

Implements a ray-primitive intersection test, invoked during traversal. See "Traversing the scene graph" (page 7) and "Ray information" (page 81).

Any-hit

Called when a traced ray finds a new, potentially closest, intersection point, such as for shadow computation. See "Ray information" (page 81).

Closest-hit

Called when a traced ray finds the closest intersection point, such as for material shading. See "Constructing a path tracer" (page 54).

Miss

Called when a traced ray misses all scene geometry. See "Constructing a path tracer" (page 54).

Exception

Exception handler, invoked for conditions such as stack overflow and other errors. See "Exceptions" (page 88).

Direct callables

Similar to a regular CUDA function call, direct callables are called immediately. See "Callables" (page 97).

Continuation callables

Unlike direct callables, continuation callables are executed by the scheduler. See "Callables" (page 97).

The ray-tracing "pipeline" is based on the interconnected calling structure of the eight programs and their relationship to the search through the geometric data in the scene, called a *traversal*. Figure 2.1 is a diagram of these relationships:




Fig. 2.1 – Relationship of NVIDIA OptiX 7 programs. Green represents fixed functions; gray represents user programs.

In Figure 2.1, green represents fixed-function, hardware-accelerated operations, while gray represents user programs. The built-in or user-provided exception program may be called from any program or scene traversal in case of an exception if exceptions are enabled.

2.2.1 Shader binding table

The *shader binding table* connects geometric data to programs and their parameters. A *record* is a component of the shader binding table that is selected during execution by using offsets specified when acceleration structures are created and at runtime. A record contains two data regions, *header* and *data*.

Record header

- Opaque to the application, filled in by optixSbtRecordPackHeader
- Used by NVIDIA OptiX 7 to identify programmatic behavior. For example, a primitive would identify the intersection, any-hit, and closest-hit behavior for that primitive in the header.

Record data

- Opaque to NVIDIA OptiX 7
- User data associated with the primitive or programs referenced in the headers can be stored here, for example, program parameter values.

2.2.2 Ray payload

The ray payload is used to pass data between optixTrace and the programs invoked during ray traversal. Payload values are passed to and returned from optixTrace, and follow a copy-in/copy-out semantic. There is a limited number of payload values, but one or more of these values can also be a pointer to stack-based local memory, or application-managed global memory. See "Payload" (page 93).

2.2.3 Primitive attributes

Attributes are used to pass data from intersection programs to the any-hit and closest-hit programs. Triangle intersection provides two predefined attributes for the barycentric coordinates (U,V). User-defined intersections can define a limited number of other attributes that are specific to those primitives.

2.2.4 Buffer

NVIDIA OptiX 7 represents GPU information with a pointer to GPU memory. References to the term "buffer" in this document refer to this GPU memory pointer and the associated memory contents. Unlike NVIDIA OptiX 6, the allocation and transfer of buffers is explicitly controlled by user code.

2.3 Acceleration structures

NVIDIA OptiX 7 acceleration structures are opaque data structures built on the device. Typically, they are based on the *bounding volume hierarchy*⁶ model, but implementations and the data layout of these structures may vary from one GPU architecture to another.

NVIDIA OptiX 7 provides two basic types of acceleration structures:

Geometry acceleration structures

• Built over primitives (triangles, curves, spheres, or user-defined primitives)

Instance acceleration structures

- Built over other objects such as acceleration structures (either type) or motion transform nodes
- Allow for instancing with a per-instance static transform

2.4 Traversing the scene graph

To determine the intersection of geometric data by a ray, NVIDIA OptiX 7 searches a graph of nodes composed of acceleration structures and transformations. This search is called a *traversal*; the nodes in the graph are called *traversable objects* or *traversables*.

The following types of traversable objects exist:

- An instance acceleration structure
- A geometry acceleration structure (as a root for graph with a single geometry acceleration structure (see Traversal of a single geometry acceleration structure (page 32))
- Static transform
- Matrix motion transform
- Scaling, rotation, translation (SRT) motion transform

For transformation traversables, the corresponding transformation applies to all descendant child traversables (the sub graph spanned by the child of the transformation traversable). The

^{6.} https://en.wikipedia.org/wiki/Bounding_volume_hierarchy

transformation traversables should only be used in case of motion as applying transformations to geometry is order dependent and motion transformations are time dependent. Static transformations are available as they cannot be merged with any motion transformation due to time-dependency, but should be merged with instance transformations (if desired as the child of an instance) or any other static transformation (i.e., there should be at most one static transformation following a motion transformation). For example, Figure 2.2 combines both types:




Fig. 2.2 – Example graph of traversables for a scene containing static as well as dynamic motion-transform driven objects

OptiX uses handles as references to traversable objects. These *traversable handles* are 64-bit opaque values that are generated from device memory pointers for the graph nodes. The handles identify the connectivity of these objects. All calls to optixTrace begin at a traversable handle.

Note: DXR and VulkanRT use the terms *top-level acceleration structure* and *bottom-level acceleration structure*. A bottom-level acceleration structure is the same as a geometry acceleration structure; a top-level acceleration structure is similar to an instance acceleration structure. Traversing against a single geometry acceleration structure, motion transform nodes, or nested instance acceleration structures (multi-level instancing) are not supported in DXR or VulkanRT. In NVIDIA OptiX 7, the terms were changed due to the additional possible configurations of scene graphs beyond the strict two-level, top-bottom configurations supported by DXR and VulkanRT. (See DirectX Raytracing (DXR) Functional Spec.⁷)

^{7.} https://microsoft.github.io/DirectX-Specs/d3d/Raytracing.html#geometry-and-acceleration-structures

2.5 Ray tracing with NVIDIA OptiX 7

A functional ray tracing system is implemented by combining four components as described in the following steps:

- 1. Create one or more acceleration structures over one or many geometry meshes and instances of these meshes in the scene. See "Acceleration structures" (page 19).
- 2. Create a pipeline of programs that contains all programs that will be invoked during a ray tracing launch. See "Program pipeline creation" (page 41).
- 3. Create a shader binding table that includes references to these programs and their parameters and choose a data layout that matches the implicit shader binding table record selection of the instances and geometries in the acceleration structures. See "Shader binding table" (page 57).
- 4. Launch a device-side kernel that will invoke a ray generation program with a multitude of threads calling optixTrace to begin traversal and the execution of the other programs. See "Ray generation launches" (page 71). Device-side functionality is described in "Device-side functions" (page 75).

Ray tracing work can be interleaved with other CUDA work to generate data, move data to and from the device, and move data to other graphics APIs. It is the application's responsibility to coordinate all work on the GPU. NVIDIA OptiX 7 does not synchronize with any other work.

3 Implementation principles

3.1 Error handling

Errors are reported using enumerated return codes. An optional log callback can be registered with the device context to receive any additional logging information.

Functions that compile can optionally take a string character buffer to report additional messaging for errors, warnings and resource use.

3.2 Thread safety

Almost all host functions are thread-safe. Exceptions to this rule are identified in the API documentation. A general requirement for thread-safety is that output buffers and any temporary or state buffers are unique. For example, you can create more than one acceleration structure concurrently from the same input geometry, as long as the temporary and output device memory are disjoint. Temporary and state buffers are always part of the parameter list if they are needed to execute the method.

3.3 Stateless model

Given the same input, the same output should be generated. GPU state is not held by NVIDIA OptiX 7 internally.

In NVIDIA OptiX 7 functions, a CUstream is associated with the CUcontext used to create the OptixDeviceContext. Some API functions take a CUstream as an argument. These functions incur work on the device and require that the CUcontext associated with the OptixDeviceContext is the current context when they are called. Applications can expect the CUcontext to remain the same after invoking NVIDIA OptiX 7 functions.

3.4 Asynchronous execution

Work performed on the device is issued on an application-supplied CUstream using asynchronous CUDA methods. The host function blocks execution until all work has been issued on the stream, but does not do any synchronization or blocking on the stream itself.

3.5 Opaque types

The API employs several opaque types, such as OptixModule and OptixPipeline. Such values should be treated like pointers, insofar as copying these does not create new objects.

3.6 Function table and entry function

The NVIDIA OptiX 7 library uses a function table approach to assist in the introduction of new features in future releases while maintaining backward compatibility. To that end, it defines a struct OptixFunctionTable that holds pointers to all functions of the host API for a particular version. The current version is specified in the OPTIX_ABI_VERSION macro definition.

The NVIDIA OptiX 7 driver library exports the symbol optixQueryFunctionTable. This function is used to obtain pointers to the actual API functions:

```
Listing 3.2

OptixQueryFunctionTable_t* optixQueryFunctionTable;

... OS-specific code to load the library and to assign the address of OptixQueryFunctionTable to optixQueryFunctionTable omitted

OptixFunctionTable optixFunctionTable = {};
OptixResult result = optixQueryFunctionTable(
    OPTIX_ABI_VERSION, 0, 0, 0, &optixFunctionTable, sizeof(OptixFunctionTable));

... Error check omitted
```

Note that the three "0" arguments in the example above allow for future extensions of the entry function without changing its signature and are currently unused. A complete example implementation of this functionality including code specific to the operating system is provided as source code in optixInit() found in the header file optix_stubs.h.

After a successful call to optixQueryFunctionTable, the function table can be used as follows, for example, for context creation:

```
Listing 3.3

CUcontext fromContext = nullptr;
... fromContext initialization omitted

OptixDeviceContextOptions options = {};
... options initialization omitted

OptixResult result = optixFunctionTable.optixDeviceContextCreate(
    fromContext, &options, &context);

... Error check omitted
```

Since the explicit call qualifications with the function table instance can be inconvenient, optional stubs that wrap the addresses in the function table into C functions are provided.

These stubs are made available by including the header file optix_stubs.h. With these stubs the previous example can be simplified as follows:

```
Listing 3.4

CUcontext fromContext = nullptr;
... fromContext initialization omitted

OptixDeviceContextOptions options = {};
... options initialization omitted

OptixResult result = optixDeviceContextCreate(
    fromContext, &options, &context);

... Error check omitted
```

Using these stubs is purely optional and applications are free to implement their own solution to make the addresses in the function table more easily available.

4 Context

The API functions described in this section are:

```
optixDeviceContextCreate
optixDeviceContextDestroy
optixDeviceContextGetProperty
optixDeviceContextSetLogCallback
optixDeviceContextSetCacheEnabled
optixDeviceContextSetCacheLocation
optixDeviceContextSetCacheDatabaseSizes
optixDeviceContextGetCacheEnabled
optixDeviceContextGetCacheLocation
optixDeviceContextGetCacheLocation
optixDeviceContextGetCacheDatabaseSizes
```

A *context* is created by optixDeviceContextCreate and is used to manage a single GPU. The NVIDIA OptiX 7 device context is created by specifying the CUDA context associated with the device. For convenience, zero can be passed and NVIDIA OptiX 7 will use the current CUDA context.

```
Listing 4.1

OptixDeviceContext context = nullptr;

cudaFree(0); Initialize CUDA for this device on this thread

CUcontext cuCtx = 0; Zero means take the current context
optixDeviceContextCreate(cuCtx, 0, &context);
```

Additional creation time options can also be specified with OptixDeviceContextOptions, including parameters for specifying a callback function, log and data. (See "Sending messages with a callback function" (page 16).)

A small set of context properties exist for determining sizes and limits. These are queried using optixDeviceContextGetProperty. Such properties include maximum trace depth, maximum traversable graph depth, maximum primitives per build input, and maximum number of instances per acceleration structure.

The context may retain ownership of any GPU resources necessary to launch the ray tracing kernels. Some API objects will retain host memory. These are defined with create/destroy patterns in the API. The application must invoke optixDeviceContextDestroy to clean up any host or device resources associated with the context. If any other API objects associated with this context still exist when the context is destroyed, they are also destroyed.

A context can hold a decryption key. When specified, the context requires user code passed into the API to be encrypted using the appropriate session key. This minimizes exposure of the input code to security attacks.

4 Context 4.2 Compilation caching

Note: The context decryption feature is available upon request from NVIDIA.

An application may combine any mixture of supported GPUs as long as the data transfer and synchronization is handled appropriately. Some applications may choose to simplify multi-GPU handling by restricting the variety of these blends, for example, by mixing only GPUs of the same streaming multiprocessor version to simplify data sharing.

4.1 Sending messages with a callback function

A log callback and pointer to host memory can also be specified during context creation or later by using optixDeviceContextSetLogCallback. This callback will be used to communicate various messages. It must be thread-safe if multiple NVIDIA OptiX 7 functions are called concurrently.

This callback must be a pointer to a function of the following type:

```
Listing 4.2

typedef void (*OptixLogCallback)(
   unsigned int level,
   const char* tag,
   const char* message,
   void* cbdata);
```

The log level indicates the severity of the message. The tag is a terse message category description (for example, SCENE STAT). The message is a null-terminated log message (without a newline character at the end) and the value of cbdata, the pointer provided when setting the callback function.

The following log levels are supported:

disable

Disables all messages. The callback function is not called in this case.

fatal

A non-recoverable error. The context, as well as NVIDIA OptiX 7 itself, may no longer be in a usable state.

error

A recoverable error, for example, when passing invalid call parameters.

warning

Hints that the API might not behave exactly as expected by the application or that it may perform slower than expected.

print

Status and progress messages.

4.2 Compilation caching

Compilation of input programs will be cached to disk when creating OptixModule, OptixProgramGroup, and OptixPipeline objects if caching has been enabled. Subsequent

4.2 Compilation caching 4 Context

compilation can reuse the cached data to improve the time to create these objects. The cache can be shared between multiple <code>OptixDeviceContext</code> objects, and NVIDIA OptiX 7 will take care of ensuring correct multi-threaded access to the cache. If no sharing between <code>OptixDeviceContext</code> objects is desired, the path to the cache can be set differently for each <code>OptixDeviceContext</code>. Caching can be disabled entirely by setting the environment variable <code>OPTIX_CACHE_MAXSIZE</code> to 0. Disabling the cache via the environment variable will not affect existing cache files or their contents.

The disk cache can be controlled with:

optixDeviceContextSetCacheEnabled(..., int enabled)

When enabled has a value of 1, the disk cache is enabled; a value of 0 disables it. Note that no in-memory cache is used when caching is disabled.

The cache database is initialized when the device context is created and when enabled through this function call. If the database cannot be initialized when the device context is created, caching will be disabled; a message is reported to the log callback if caching is enabled. In this case, the call to optixDeviceContextCreate does not return an error. To ensure that cache initialization succeeded on context creation, the status can be queried using optixDeviceContextGetCacheEnabled. If caching is disabled, the cache can be reconfigured and then enabled using optixDeviceContextSetCacheEnabled. If the cache database cannot be initialized with optixDeviceContextSetCacheEnabled, an error is returned. Garbage collection is performed on the next write to the cache database, not when the cache is enabled.

optixDeviceContextSetCacheLocation(..., const char* location)

The disk cache is created in the directory specified by location. The value of location must be a NULL-terminated string. The directory is created if it does not exist.

The cache database is created immediately if the cache is currently enabled. Otherwise the cache database is created later when the cache is enabled. An error is returned if it is not possible to create the cache database file at the specified location for any reason (for example, if the path is invalid or if the directory is not writable) and caching will be disabled. If the disk cache is located on a network file share, behavior is undefined.

The location of the disk cache can be overridden with the environment variable OPTIX_CACHE_PATH. This environment variable takes precedence over the value passed to this function when the disk cache is enabled.

The default location of the cache depends on the operating system:

Operating system	Pathname
Windows	%LOCALAPPDATA%\NVIDIA\OptixCache
Linux	/var/tmp/OptixCache_username, or /tmp/OptixCache_username if the first choice is not usable. The underscore and username suffix are omitted if the username cannot be obtained.

optixDeviceContextSetCacheDatabaseSizes(

..., size_t lowWaterMark, size_t highWaterMark)

Parameters lowWaterMark and highWaterMark set the low and high water marks for disk cache garbage collection. Setting either limit to zero disables garbage collection. Garbage collection only happens when the cache database is written. It is triggered whenever the

4 Context 4.3 Validation mode

cache data size exceeds the high water mark and proceeding until the size reaches the low water mark. Garbage collection always frees enough space to allow the insertion of the new entry within the boundary of the low water mark. An error is returned if either limit is nonzero and the high water mark is lower than the low water mark. If more than one device context accesses the same cache database with different high and low water mark values, the device context uses its values when writing to the cache database.

The high water mark can be overridden with the environment variable OPTIX_CACHE_MAXSIZE. Setting OPTIX_CACHE_MAXSIZE to 0 will disable the cache. Negative and non-integer values will be ignored.

The value of OPTIX_CACHE_MAXSIZE takes precedence over the highWaterMark value passed to this function. The low water mark will be set to half the value of OPTIX_CACHE_MAXSIZE.

Corresponding get* functions are supplied to retrieve the current value of these cache properties.

4.3 Validation mode

The NVIDIA OptiX 7 *validation mode* can help uncover errors which might otherwise go undetected or which occur only intermittently and are difficult to locate. Validation mode enables additional tests and settings during application execution. This additional processing can reduce performance, so it should only be used during debugging or in the final testing phase of a completed application.

Validation mode is enabled by setting a field in the OptixDeviceContextOptions struct:

```
Listing 4.3

OptixDeviceContextOptions options = {};
options.validationMode = OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_ALL;
```

The error OPTIX_ERROR_VALIDATION_FAILURE is signaled if an error is caught when validation mode is enabled. Function optixLaunch will synchronize after the launch and report errors, if any.

Among other effects, validation mode implicitly enables all OptiX debug exceptions and provides an exception program if none is provided. The first non-user exception caught inside an exception program will therefore be reported and the launch terminated immediately. This will make exceptions more visible that otherwise might be overlooked.

5 Acceleration structures

The API functions described in this section are:

```
optixAccelComputeMemoryUsage
optixAccelBuild
optixAccelRelocate
optixConvertPointerToTraversableHandle
```

NVIDIA OptiX 7 provides *acceleration structures* to optimize the search for the intersection of rays with the geometric data in the scene. Acceleration structures can contain two types of data: geometric primitives (a *geometry-AS*) or instances (an *instance-AS*). Acceleration structures are created on the device using a set of functions. These functions enable overlapping and pipelining of acceleration structure creation, called a *build*. The functions use one or more OptixBuildInput structs to specify the geometry plus a set of parameters to control the build.

Acceleration structures have size limits, listed in "Limits" (page 73). For an instance acceleration structure, the number of instances has an upper limit. For a geometry acceleration structure, the number of geometric primitives is limited, specifically the total number of primitives in its build inputs, multiplied by the number of motion keys.

The following build input types are supported:

```
Instance acceleration structures

OPTIX_BUILD_INPUT_TYPE_INSTANCES
OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS

A geometry acceleration structure containing built-in triangles
OPTIX_BUILD_INPUT_TYPE_TRIANGLES

A geometry acceleration structure containing built-in curve primitives
OPTIX_BUILD_INPUT_TYPE_CURVES

A geometry acceleration structure containing built-in spheres
OPTIX_BUILD_INPUT_TYPE_SPHERES

A geometry acceleration structure containing custom primitives
OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES
```

For geometry-AS builds, each build input can specify a set of triangles, a set of curves, a set of spheres, or a set of user-defined primitives bounded by specified axis-aligned bounding boxes. Multiple build inputs can be passed as an array to optixAccelBuild to combine different meshes into a single acceleration structure. All build inputs for a single build must agree on the build input type.

Instance acceleration structures have a single build input and specify an array of instances. Each instance includes a ray transformation and an OptixTraversableHandle that refers to a geometry-AS, a transform node, or another instance acceleration structure.

To prepare for a build, the required memory sizes are queried by passing an initial set of build inputs and parameters to optixAccelComputeMemoryUsage. It returns three different sizes:

```
outputSizeInBytes
```

Size of the memory region where the resulting acceleration structure is placed. This size is an upper bound and may be substantially larger than the final acceleration structure. (See "Compacting acceleration structures" (page 30).)

tempSizeInBytes

Size of the memory region that is temporarily used during the build.

tempUpdateSizeInBytes

Size of the memory region that is temporarily required to update the acceleration structure.

Using these sizes, the application allocates memory for the output and temporary memory buffers on the device. The pointers to these buffers must be aligned to a 128-byte boundary. These buffers are actively used for the duration of the build. For this reason, they cannot be shared with other currently active build requests.

Note that optixAccelComputeMemoryUsage does not initiate any activity on the device; pointers to device memory or contents of input buffers are not required to point to allocated memory.

The function optixAccelBuild takes the same array of OptixBuildInput structs as optixAccelComputeMemoryUsage and builds a single acceleration structure from these inputs. This acceleration structure can contain either geometry or instances, depending on the inputs to the build.

The build operation is executed on the device in the specified CUDA stream and runs asynchronously on the device, similar to CUDA kernel launches. The application may choose to block the host-side thread or synchronize with other CUDA streams by using available CUDA synchronization functionality such as cudaStreamSynchronize or CUDA events. The traversable handle returned is computed on the host and is returned from the function immediately, without waiting for the build to finish. By producing handles at acceleration time, custom handles can also be generated based on input to the builder.

The acceleration structure constructed by optixAccelBuild does not reference any of the device buffers referenced in the build inputs. All relevant data is copied from these buffers into the acceleration output buffer, possibly in a different format.

The application is free to release this memory after the build without invalidating the acceleration structure. However, instance-AS builds will continue to refer to other instance-AS and geometry-AS instances and transform nodes.

The following example uses this sequence to build a single acceleration structure:

```
Listing 5.1

OptixAccelBuildOptions accelOptions = {};
OptixBuildInput buildInputs[2];

CUdeviceptr tempBuffer, outputBuffer;
size_t tempBufferSizeInBytes, outputBufferSizeInBytes;
```

```
memset(accelOptions, 0, sizeof(OptixAccelBuildOptions));
accelOptions.buildFlags = OPTIX_BUILD_FLAG_NONE;
accelOptions.operation = OPTIX_BUILD_OPERATION_BUILD;
accelOptions.motionOptions.numKeys = 0;
                                       A numKeys value of zero specifies no motion blur
Setup build inputs; see below.
OptixAccelBufferSizes bufferSizes = {};
optixAccelComputeMemoryUsage(optixContext, &accelOptions,
   buildInputs, 2, &bufferSizes);
void* d_output;
void* d_temp;
cudaMalloc(&d_output, bufferSizes.outputSizeInBytes);
cudaMalloc(&d_temp, bufferSizes.tempSizeInBytes);
OptixTraversableHandle outputHandle = 0;
OptixResult results = optixAccelBuild(optixContext, cuStream,
    &accelOptions, buildInputs, 2, d_temp,
    bufferSizes.tempSizeInBytes, d_output,
    bufferSizes.outputSizeInBytes, &outputHandle, nullptr, 0);
```

To ensure compatibility with future versions, the OptixBuildInput structure should be initialized with zeros before populating it with specific build inputs.

5.1 Primitive build inputs

A triangle build input references an array of triangle vertex buffers in device memory, one buffer per motion key (a single triangle vertex buffer if there is no motion). (See "Motion blur" (page 32).) Optionally, triangles can be indexed using an index buffer in device memory. Various vertex and index formats are supported as input, but may be transformed to an internal format (potentially of a different size than the input) that is more efficient.

```
Listing 5.2

OptixBuildInputTriangleArray& buildInput =
    buildInputs[0].triangleArray;
buildInput.type = OPTIX_BUILD_INPUT_TYPE_TRIANGLES;
buildInput.vertexBuffers = &d_vertexBuffer;
buildInput.numVertices = numVertices;
buildInput.vertexFormat = OPTIX_VERTEX_FORMAT_FLOAT3;
buildInput.vertexStrideInBytes = sizeof(float3);
buildInput.indexBuffer = d_indexBuffer;
```

```
buildInput.numIndexTriplets = numTriangles;
buildInput.indexFormat = OPTIX_INDICES_FORMAT_UNSIGNED_INT3;
buildInput.indexStrideInBytes = sizeof(int3);
buildInput.preTransform = 0;
```

The preTransform is an optional pointer to a 3x4 row-major transform matrix in device memory. The pointer needs to be aligned to 16 bytes; the matrix contains 12 floats. If specified, the transformation is applied to all vertices at build time with no runtime traversal overhead.

A curves build input or a spheres build input is similar to a triangle build input; see "Curve build inputs" (page 23), "Sphere build inputs" (page 25).

The acceleration structure build input for custom primitives uses the type <code>OptixBuildInputCustomPrimitiveArray</code>. Each custom primitive is represented by an <code>axis-aligned bounding box</code> (AABB), which is a rectangular solid defined by ranges of x, y, and z values, and which must completely enclose the primitive. The memory layout of an AABB is defined in the struct <code>OptixAabb</code>. The AABBs are organized in an array of buffers in device memory, with one buffer per motion key. The precise shape of each custom primitive will be depend on the intersection program in its SBT record.

```
Listing 5.3

OptixBuildInputCustomPrimitiveArray& buildInput =
    buildInputs[0].customPrimitiveArray;
buildInput.type = OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES;
buildInput.aabbBuffers = d_aabbBuffer;
buildInput.numPrimitives = numPrimitives;
```

The optixAccelBuild function accepts multiple build inputs per call, but they must be all triangle inputs, all curve inputs, all sphere inputs, or all AABB inputs. Mixing build input types in a single geometry-AS is not allowed.

Each build input maps to one or more consecutive records in the shader binding table (SBT), which controls program dispatch. (See "Shader binding table" (page 57).) If multiple records in the SBT are required, the application needs to provide a device buffer with per-primitive SBT record indices for that build input. If only a single SBT record is requested, all primitives reference this same unique SBT record. Note that there is a limit to the number of referenced SBT records per geometry-AS. (Limits are discussed in "Limits" (page 73).)

```
Listing 5.4

buildInput.numSbtRecords = 2;
buildInput.sbtIndexOffsetBuffer =
    d_sbtIndexOffsetBuffer;

buildInput.sbtIndexOffsetSizeInBytes = sizeof(int);
buildInput.sbtIndexOffsetSizeInBytes = sizeof(int);
buildInput.sbtIndexOffsetStrideInBytes = sizeof(int);
1-4 byte unsigned integer offsets allowed
```

Each build input also specifies an array of OptixGeometryFlags, one for each SBT record. The flags for one record apply to all primitives mapped to this SBT record.

For example:

```
Listing 5.5

unsigned int flagsPerSBTRecord[2];
flagsPerSBTRecord[0] = OPTIX_GEOMETRY_FLAG_NONE;
flagsPerSBTRecord[1] = OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT;
...
buildInput.flags = flagsPerSBTRecord;
```

The following flags are supported:

```
OPTIX_GEOMETRY_FLAG_NONE
```

Applies the default behavior when calling the any-hit program, possibly multiple times, allowing the acceleration-structure builder to apply all optimizations.

```
OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL
```

Disables some optimizations specific to acceleration-structure builders. By default, traversal may call the any-hit program more than once for each intersected primitive. Setting the flag ensures that the any-hit program is called only once for a hit with a primitive. However, setting this flag may change traversal performance. The usage of this flag may be required for correctness of some rendering algorithms; for example, in cases where opacity or transparency information is accumulated in an any-hit program.

```
OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT
```

Indicates that traversal should not call the any-hit program for this primitive even if the corresponding SBT record contains an any-hit program. Setting this flag usually improves performance even if no any-hit program is present in the SBT.

Primitives inside a build input are indexed starting from zero. This primitive index is accessible inside the intersection, any-hit, and closest-hit programs. If the application chooses to offset this index for all primitives in a build input, there is no overhead at runtime. This can be particularly useful when data for consecutive build inputs is stored consecutively in device memory. The primitiveIndexOffset value is only used when reporting the intersection primitive.

```
Listing 5.6

buildInput[0].aabbBuffers = d_aabbBuffer;
buildInput[0].numPrimitives = ...;
buildInput[0].primitiveIndexOffset = 0;

buildInput[1].aabbBuffers = d_aabbBuffer +
    buildInput[0].numPrimitives * sizeof(float) * 6;
buildInput[1].numPrimitives = ...;
buildInput[1].primitiveIndexOffset = buildInput[0].numPrimitives;
```

5 Acceleration structures 5.2 Curve build inputs

5.2 Curve build inputs

In addition to triangles and custom primitives, NVIDIA OptiX 7 supports curves and spheres as geometric primitives. Curves are used to represent long thin strands, such as for hair, fur, and carpet fibers. Scenes may contain thousands or millions of curves, and they will often be no wider than a couple of pixels in the final image.

Each curve is a swept surface defined by a three-dimensional series of vertices, called *control points*, and a possibly varying radius. The NVIDIA OptiX 7 API provides curves with these characteristics:

- The cross-section of the curve primitive is a circle.
- Curve geometry is defined by a cubic uniform B-spline curve, a quadratic uniform B-spline curve, a Catmull-Rom spline curve, or a series of linear segments.
- A radius is specified at each control point. The radius is interpolated along the curve using the same spline basis as position.
- Linear curves have spherical end caps, with spherical "elbows" for smooth joints between segments. By default, the ends of cubic and quadratic splines are open and do not have end caps. Flat end caps for cubic and quadratic splines can be enabled by setting <code>OptixBuildInputCurveArray::endcapFlags to OPTIX_CURVE_ENDCAP_ON.</code>

Spline curves are composed of a series of polynomial segments. Each segment is defined by two, three, or four control points, depending on the curve type:

Curve type	Control points per segment
Piecewise linear	2
Quadratic	3
Cubic	4
Catmull-Rom	4

NVIDIA OptiX 7 considers each polynomial segment to be a primitive, with its own primitive ID.

A curve build input (OptixBuildInputCurveArray) references an array of vertex buffers in device memory, one buffer per motion key (a single vertex buffer if there is no motion). (See "Motion blur" (page 32).) Parallel to this, there is an array of radius buffers in device memory, one buffer per motion key, providing a radius value at each control vertex at each motion key. There is also a (required) index buffer in device memory.

The B-spline control points of each curve strand will appear sequentially in the vertex buffer. The index array contains one index per segment, namely, the index of the segment's first control point. For example, a cubic curve with three segments will have six vertices. The index array might contain {10, 11, 12}, in which case the 3 segments will have control points: {v[10], v[11], v[12], v[13]}, {v[11], v[12], v[13]}, and {v[12], v[13], v[14], v[15]}.

End caps appear at the ends of strands. NVIDIA OptiX 7 detects the strands by checking the overlap of segment control points. Within a B-spline strand, adjacent segments overlap all but one of their control points. In other words, unless indexArray[N+1] is equal to

indexArray[N]+1, segment N is the end of one strand and segment N+1 is the beginning of another.

See also "Differences between curves, spheres, and triangles" (page 65).

5.3 Sphere build inputs

Similar to curves, NVIDIA OptiX 7 supports spheres as geometric primitives. Spheres can be used in different applications to represent, for example, molecules, spray, or smoke.

Each sphere is defined by a three-dimensional center point and a radius.

A sphere build input (OptixBuildInputSphereArray) references an array of vertex buffers in device memory storing the center points, one buffer per motion key (a single vertex buffer if there is no motion). (See "Motion blur" (page 32).) Parallel to this, there is an array of radius buffers in device memory, one buffer per motion key, providing a radius value at each vertex at each motion key. If all spheres have the same radius per motion key, a single radius per radius buffer is sufficient if the singleRadius flag is set.

See also "Differences between curves, spheres, and triangles" (page 65).

5.4 Instance build inputs

An instance build input specifies a buffer of OptixInstance structs in device memory. These structs can be specified as an array of consecutive structs or an array of pointers to those structs. Each instance description references:

- A child traversable handle
- A static 3x4 row-major object-to-world matrix transform
- A user ID
- An SBT offset
- A visibility mask
- Instance flags

Unlike the triangle and AABB inputs, optixAccelBuild only accepts a single instance build input per build call. There are upper limits to the possible number of instances (the size of the buffer of the OptixInstance structs), the SBT offset, the visibility mask, as well as the user ID. (These limits are discussed in "Limits" (page 73).)

An example of this sequence:

```
Listing 5.7

OptixInstance instance = {};
float transform[12] = {1,0,0,3,0,1,0,0,0,0,1,0};
memcpy(instance.transform, transform, sizeof(float)*12);
instance.instanceId = 0;
instance.visibilityMask = 255;
instance.sbtOffset = 0;
instance.flags = OPTIX_INSTANCE_FLAG_NONE;
instance.traversableHandle = gasTraversable;

void* d_instance;
```

```
cudaMalloc(&d_instance, sizeof(OptixInstance));

cudaMemcpy(d_instance, &instance,
    sizeof(OptixInstance),
    cudaMemcpyHostToDevice);

OptixBuildInputInstanceArray* buildInput =
    &buildInputs[0].instanceArray;
buildInput->type = OPTIX_BUILD_INPUT_TYPE_INSTANCES;
buildInput->instances = d_instance;
buildInput->numInstances = 1;
```

The OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS build input is a variation on the OPTIX_BUILD_INPUT_TYPE_INSTANCES build input where instanceDescs references a device memory array of pointers to OptixInstance data structures in device memory.

Instance flags are applied to primitives encountered while traversing the geometry-AS connected to an instance. The flags override any instance flags set during the traversal of parent instance-ASs.

```
OPTIX_INSTANCE_FLAG_DISABLE_TRIANGLE_FACE_CULLING
```

Disables face culling for triangles. Overrides any culling ray flag passed to optixTrace.

```
OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING
```

Flips the triangle orientation during intersection. Also affects any culling of front and back faces.

```
OPTIX INSTANCE FLAG DISABLE ANYHIT
```

Disables any-hit calls for primitive intersections. Can be overridden by ray flags.

```
OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT
```

Forces any-hit calls for primitive intersections. Can be overridden by ray flags.

The visibility mask is combined with the ray mask to determine visibility for this instance. If the condition rayMask & instance.mask == 0 is true, the instance is culled. The visibility flags may be interpreted as assigning rays and instances to one of eight groups. Instances are traversed only when the instance and ray have at least one group in common. (See "Trace" (page 77).)

The sbtOffset is an offset into the SBT for hit groups (intersection, any-hit, closest-hit) specified with the hitgroupRecordBase parameter of OptixShaderBindingTable. It is used as a simple additive offset into the SBT to select the hit group programs run in case of an intersection of a primitive part of this instance. See "Acceleration structures" (page 59) for more detail. If the child of the instance is a transform object — an OptixStaticTransform, OptixMatrixMotionTransform, or OptixSRTMotionTransform traversable object instead of a geometry-AS — the instance's sbtOffset value still applies when hitting a primitive of the geometry-AS at the end of the chain of transforms. However, if the instance or the last transform (in case of a chain of transform traversables) references an instance-AS, the sbtOffset must be set to zero. Therefore, the sbtOffset does not stack for multi-level scene graphs.

5.5 Build flags 5 Acceleration structures

5.5 Build flags

An acceleration structure build can be controlled using the values of the OptixBuildFlags enum. To enable random vertex access on an acceleration structure, use OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS. (See "Vertex random access" (page 83).) To steer trade-offs between build performance, runtime traversal performance and acceleration structure memory usage, use OPTIX_BUILD_FLAG_PREFER_FAST_TRACE and OPTIX_BUILD_FLAG_PREFER_FAST_BUILD. For curve primitives in particular, these flags control splitting; see "Splitting curve segments" (page 66).

The flags OPTIX_BUILD_FLAG_PREFER_FAST_TRACE and OPTIX_BUILD_FLAG_PREFER_FAST_BUILD are mutually exclusive. To combine multiple flags that are not mutually exclusive, use the logical "or" operator.

5.6 Dynamic updates

Building an acceleration structure can be computationally costly. Applications may choose to update an existing acceleration structure using modified vertex data or bounding boxes. Updating an existing acceleration structure is generally much faster than rebuilding. However, the quality of the acceleration structure may degrade if the data changes too much with an update, for example, through explosions or other chaotic transitions — even if for only parts of the mesh. The degraded acceleration structure may result in slower traversal performance as compared to an acceleration structure built from scratch from the modified input data.

To allow for future updates of an acceleration structure, set OPTIX_BUILD_FLAG_ALLOW_UPDATE in the build flags when building the acceleration structure initially.

For example:

```
Listing 5.8
accelOptions.buildFlags = OPTIX_BUILD_FLAG_ALLOW_UPDATE;
accelOptions.operation = OPTIX_BUILD_OPERATION_BUILD;
```

To update the previously built acceleration structure, set the operation to OPTIX_BUILD_OPERATION_UPDATE and then call optixAccelBuild on the same output data. All other options are required to be identical to the original build. The update is done in-place on the output data.

```
Listing 5.9
accelOptions.buildFlags = OPTIX_BUILD_FLAG_ALLOW_UPDATE;
accelOptions.operation = OPTIX_BUILD_OPERATION_UPDATE;

void* d_tempUpdate;
cudaMalloc(&d_tempUpdate, bufferSizes.tempUpdateSizeInBytes);

optixAccelBuild(optixContext, cuStream, &accelOptions,
    buildInputs, 2, d_tempUpdate,
```

5 Acceleration structures 5.7 Relocation

```
bufferSizes.tempUpdateSizeInBytes, d_output,
bufferSizes.outputSizeInBytes, &outputHandle, nullptr, 0);
```

Updating an acceleration structure usually requires a different amount of temporary memory than the original build.

When updating an existing acceleration structure, only the device pointers and/or their buffer content may be changed. You cannot change the number of build inputs, the build input types, build flags, traversable handles for instances (for an instance-AS), or the number of vertices, indices, AABBs, instances, SBT records or motion keys. Changes to any of these things may result in undefined behavior, including GPU faults.

Note, however, that in the following two cases it is more efficient to re-build the geometry-AS and/or the instance-AS, or to use the respective masking and flags:

- When using indices, changing the connectivity or, in general, using shuffled vertex positions will work, but the quality of the acceleration structure will likely degrade substantially.
- During an animation operation, geometry that should be invisible to the camera should not be "removed" from the scene, either by moving it very far away or by converting it into a degenerate form. Such changes to the geometry will also degrade the acceleration structure.

Setting the acceleration structure flag OPTIX_BUILD_FLAG_ALLOW_UPDATE may also degrade the performance of the acceleration structure when processing curve primitives.

Updating an acceleration structure requires that any other acceleration structure that is using this acceleration structure as a child directly or indirectly also needs to be updated or rebuild.

5.7 Relocation

Geometry acceleration structures can be copied and moved, however they may not be used until optixAccelRelocate has been called to update the copied acceleration structure and generate the new traversable handle. Any acceleration structure may be relocated, including compacted acceleration structures.

The copy does not need to be on the original device. This enables the copying of acceleration structure data to compatible devices without rebuilding the acceleration structure.

To relocate an acceleration structure, an OptixAccelRelocationInfo object is filled using optixAccelGetRelocationInfo and the traversable handle of the source acceleration structure. This object can then be used to determine if relocation to a device (as specified with an OptixDeviceContext) is possible. This is done using optixAccelCheckRelocationCompatibility. If the target device is compatible, the source acceleration structure may be copied to that device with a subsequent call of optixAccelRelocate.

If an acceleration structure with instances is relocated, the traversable handles for the instances should be specified by optixAccelRelocate with the instanceTraversableHandles and numInstanceTraversableHandles parameters. The geometric bounds of the acceleration structure are not updated, so instanceTraversableHandles should correspond to either the same instances as the source (when relocating the instance-AS without relocating the

5.7 Relocation 5 Acceleration structures

geometry-AS) or the corresponding relocated instances (if relocating both types of acceleration structures).

The following example relocates the geometry and instance acceleration structure to new CUDA allocations on the same device:

```
Listing 5.10
OptixAccelRelocationInfo gasInfo = {};
optixAccelGetRelocationInfo(context, gasHandle, &gasInfo);
int compatible = 0;
optixAccelCheckRelocationCompatibility(
       context, &gasInfo, &compatible);
                                                           This is unnecessary
if (compatible != 1) {
                                                           because the copy
                                                           operation's source and
       fprintf(stderr,
                                                           destination are on the
        "Device isn't compatible for relocation "
                                                           same device, but is here to
               "of geometry acceleration structures.");
                                                           illustrate the API.
       exit(2);
}
// Copy and relocate the geometry acceleration structure
CUdeviceptr d_relocatedGas = 0;
cudaMalloc((void**)&d_relocatedGas,
   gasBufferSizes.outputSizeInBytes);
cudaMemcpy((void*)d_relocatedGas, (void*)d_gasOutputBuffer,
   gasBufferSizes.outputSizeInBytes,
   cudaMemcpyDeviceToDevice);
OptixTraversableHandle relocatedGasHandle = 0;
optixAccelRelocate(
   context, 0,
   &gasInfo,
   0, 0,
   d_relocatedGas,
   gasBufferSizes.outputSizeInBytes,
   &relocatedGasHandle);
// Copy and relocate the instance acceleration structure
CUdeviceptr d_relocatedIas = 0;
cudaMalloc((void**)&d_relocatedIas,
    iasBufferSizes.outputSizeInBytes);
cudaMemcpy((void*)d_relocatedIas, (void*)d_iasOutputBuffer,
    iasBufferSizes.outputSizeInBytes,
   cudaMemcpyDeviceToDevice);
OptixAccelRelocationInfo iasInfo = {};
optixAccelGetRelocationInfo(
   context, iasHandle, &iasInfo);
OptixTraversableHandle relocatedIasHandle = 0;
```

```
std::vector<OptixTraversableHandle>
   instanceHandles(g_instances.size());
CUdeviceptr d_instanceTravHandles = 0;
cudaMalloc(
   (void**)&d_instanceTravHandles,
   sizeof(OptixTraversableHandle) * instanceHandles.size());
for (unsigned int i = 0; i < g_instances.size(); ++i)
   instanceHandles[i] = relocatedGasHandle;
cudaMemcpy((void*)d_instanceTravHandles, instanceHandles.data(),
   sizeof(OptixTraversableHandle) * instanceHandles.size(),
   cudaMemcpyHostToDevice);
optixAccelRelocate(
   context, 0,
   &iasInfo,
   d_instanceTravHandles,
   instanceHandles.size(),
   d_relocatedIas,
   iasBufferSizes.outputSizeInBytes,
   &relocatedIasHandle);
```

5.8 Compacting acceleration structures

A post-process can compact an acceleration structure after construction. This process can significantly reduce memory usage, but it requires an additional pass. The build and compact operations are best performed in batches to ensure that device synchronization does not degrade performance. The compacted size depends on the acceleration structure type and its properties and on the device architecture.

To compact the acceleration structure as a post-process, do the following:

- Build flag OPTIX_BUILD_FLAG_ALLOW_COMPACTION must be set in the OptixAccelBuildOptions as passed to optixAccelBuild.
- 2. The emit property OPTIX_PROPERTY_TYPE_COMPACTED_SIZE must be set in the OptixAccelEmitDesc as passed to optixAccelBuild. This property is generated on the device and it must be copied back to the host if it is required for allocating the new output buffer. The application may then choose to compact the acceleration structure using optixAccelCompact.
- 3. The optixAccelCompact call should be guarded by an if (compactedSize < outputSize) (or similar) to avoid the compacting pass in cases where it is not beneficial. Note that this check requires a copy of the compacted size (as queried by optixAccelBuild) from the device memory to host memory.

Just like an uncompacted acceleration structure, it is possible to traverse, update, or relocate a compacted acceleration structure.

```
Listing 5.11
size_t *d_compactedSize;
OptixAccelEmitDesc property = {};
property.type = OPTIX_PROPERTY_TYPE_COMPACTED_SIZE;
property.result = d_compactedSize;
OptixTraversableHandle accelHandle = 0;
OptixTraversableHandle compactedAccelHandle = 0;
accelOptions.buildFlags = OPTIX_BUILD_FLAG_ALLOW_COMPACTION;
optixAccelBuild(optixContext, cuStream, &accelOptions,
   buildInputs, 2, d_tempUpdate, bufferSizes.tempSizeInBytes,
   d_output, bufferSizes.outputSizeInBytes, &accelHandle,
   &property, 1);
size_t compactedSize;
cudaMemcpy(&compactedSize, d_compactedSize,
   sizeof(size_t),
   cudaMemcpyDeviceToHost);
void *d_compactedOutputBuffer;
cudaMalloc(&d_compactedOutputBuffer, compactedSize);
if (compactedSize < bufferSizes.outputSizeInBytes) {</pre>
   optixAccelCompact(
       optixContext, stream,
       accelHandle,
       d_compactedOutputBuffer, compactedSize,
       &compactedAccelHandle);
}
```

A compacted acceleration structure does not reference the uncompacted input data. The application is free to reuse the memory of the uncompacted acceleration structure without invalidating the compacted acceleration structure. However, the memory for the compacted acceleration structure must not overlap memory of the uncompacted acceleration structure as the compaction operation does not work in-place.

A compacted acceleration structure supports dynamic updates only if the uncompacted source acceleration structure was built with the OPTIX_BUILD_FLAG_ALLOW_UPDATE build flag. (See "Dynamic updates" (page 27).) The amount of temporary memory required for a dynamic update is the same for the uncompacted acceleration structure and compacted acceleration structure. Note that using the following build flags will lead to less memory savings when enabling the compacting post-process:

```
• OPTIX_BUILD_FLAG_ALLOW_UPDATE
```

OPTIX_BUILD_FLAG_PREFER_FAST_BUILD

5.9 Traversable objects

The instances in an instance-AS may reference transform traversables, as well as geometry-ASs. Transform traversables are fully managed by the application. The application needs to create these traversables manually in device memory in a specific form. The function optixConvertPointerToTraversableHandle converts a raw pointer into a traversable handle of the specified type. The traversable handle can then be used to link traversables together.

In device memory, all traversable objects need to be 64-byte aligned. Note that moving a traversable to another location in memory invalidates the traversable handle. The application is responsible for constructing a new traversable handle and updating any other traversables referencing the invalidated traversable handle.

The traversable handle is considered opaque and the application should not rely on any particular mapping of a pointer to the traversable handle.

For example:

```
Listing 5.12

OptixMatrixMotionTransform transform = {};

... Setup motion transform

cudaMemcpy(d_transform, &transform,
    sizeof(OptixMatrixMotionTransform),
    cudaMemcpyHostToDevice);

OptixTraversableHandle transformHandle = 0;
optixConvertPointerToTraversableHandle(
    optixContext, d_transform,
    OPTIX_TRAVERSABLE_TYPE_MATRIX_MOTION_TRANSFORM,
    &transformHandle);

OptixInstance instance = {};
instance.traversableHandle = transformHandle;

... Setup instance description
```

5.9.1 Traversal of a single geometry acceleration structure

The traversable handle passed to optixTrace can be a traversable handle created from a geometry-AS. This can be useful for scenes where single geometry-AS objects represent the root of the scene graph.

If the modules and pipeline only need to support single geometry-AS traversables, it is beneficial to change the OptixPipelineCompileOptions::traversableGraphFlags from OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY to OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_GAS.

This signals to NVIDIA OptiX 7 that no other traversable types require support during traversal.

5.10 Motion blur 5 Acceleration structures

5.10 Motion blur

Motion support in OptiX targets the rendering of images with motion blur using a stochastic sampling of time. OptiX supports two types of motion as part of the scene: transform motion and vertex motion, often called deformation motion. When setting up the scene traversal graph and building the acceleration structures, motion options can be specified per acceleration structure as well as per motion transform traversable. At run time, a time parameter is passed to the trace call to perform the intersection of a ray against the scene at the selected point in time.

The general design of the motion feature in OptiX tries to strike a balance between providing many parameters to offer a high degree of freedom combined with a simple mapping of scene descriptions to these parameters but also delivering high traversal performance at the same time. As such OptiX supports the following key features:

- Vertex and transformation motion
- Matrix as well as SRT (scale rotation translation) transformations
- Arbitrary time ranges (ranges not limited to [0,1]) and flags to specify behavior outside the time range
- Arbitrary concatenations of transformations (for example, a matrix transformation on top of a SRT transformation)
- Per-ray timestamps

Scene descriptions with motion need to map easily to traversable objects and their motion options as offered by OptiX. As such, the idea is that the motion options are directly derived by the scene description, delivering high traversal performance without the need for any performance-driven adjustments. However, due to the complexity of the subject, there are a few exceptions that are discussed in this section.

This section details the usage of the motion options on the different traversable types and how to map scene options best to avoid potential performance pitfalls.

5.10.1 Basics

Motion is supported by <code>OptixMatrixMotionTransform</code>, <code>OptixSRTMotionTransform</code> and acceleration structure traversables. The general motion characteristics are specified per traversable as motion options: the number of motion keys, flags, and the beginning and ending motion times corresponding to the first and last key. The remaining motion keys are evenly spaced between the beginning and ending times. The motion keys are the data at specific points in time and the data is interpolated in between neighboring keys. The motion options are specified in the <code>OptixMotionOptions</code> struct.

The motion options are always specified per traversable (acceleration structure or motion transform). There is no dependency between the motion options of traversables; given an instance referencing a geometry acceleration structure with motion, it is not required to build an instance acceleration structure with motion. The same goes for motion transforms. Even if an instance references a motion transform as child traversable, the instance acceleration structure itself may or may not have motion.

Motion transforms must specify at least two motion keys. Acceleration structures, however, also accept OptixAccelBuildOptions with field OptixMotionOptions set to zero. This

5 Acceleration structures 5.10 Motion blur

effectively disables motion for the acceleration structure and ignores the motion beginning and ending times, along with the motion flags.

OptiX also supports static transform traversables in addition to the static transform of an instance. Static transforms are intended for the case of motion transforms in the scene. Without any motion transforms (OptixMatrixMotionTransform or OptixSRTMotionTransform) in the traversable graph, any static transformation should be baked into the instance transform. However, if there is a motion transform, it may be required to apply a static transformation on a traversable (for example, on a geometry-AS) first before applying the motion transform. For example, a motion transform may be specified in world coordinates, but the geometry it applies to needs to be placed into the scene first (object-to-world transformation, which is usually done using the instance transform). In this case, a static transform pointing at the geometry acceleration structure can be used for the object-to-world transformation and the instance transform pointing to the motion transform has an identity matrix as transformation.

Motion boundary conditions are specified by using flags. By default, the behavior for any time outside the time range, is as if time was clamped to the range, meaning it appears static and visible. Alternatively, to remove the traversable before the beginning time, set OPTIX_MOTION_FLAG_START_VANISH; to remove it after the ending time, set OPTIX_MOTION_FLAG_END_VANISH.

For example:

```
Listing 5.13

OptixMotionOptions motionOptions = {};
motionOptions.numKeys = 3;
motionOptions.timeBegin = -1f;
motionOptions.timeEnd = 1.5f;
motionOptions.flags = OPTIX_MOTION_FLAG_NONE;
```

OptiX offers two types of motion transforms, SRTs (scale-rotation-translation) as well as 3x4 affine matrices, each specifying one transform (SRT or matrix) per motion key. The transformations are always specified as object-to-world transformation just like the instance transformation. During traversal OptiX performs a per-component linear interpolation of the two nearest keys. The rotation component (expressed as a quaternion) of the SRT is an exception, OptiX ensures that the interpolated quaternion of two SRTs is of unit length by using nlerp interpolation for performance reasons. This results in a smooth, scale-preserving rotation in Cartesian space though with non-constant velocity.

For vertex motion, OptiX applies a linear interpolation between the vertex data that are provided by the application. If intersection programs are used and AABBs are supplied for the custom primitives, the AABBs are also linearly interpolated for intersection. The AABBs at the motion keys must therefore be big enough to contain any motion path of the underlying custom primitive.

There are several device-side functions that take a time parameter such as optixTrace and respect the motion options as set at the traversables. The result of these device-side functions is always that of the specified point in time, e.g, the intersection of the ray with the scene at the selected point in time. Device-side functions are discussed in detail in "Device-side functions" (page 75).

5.10 Motion blur 5 Acceleration structures

5.10.2 Motion geometry acceleration structure

Use optixAccelBuild to build a motion acceleration structure. The motion options are part of the build options (OptixAccelBuildOptions) and apply to all build inputs. Build inputs must specify primitive vertex buffers (for OptixBuildInputTriangleArray, OptixBuildInputCurveArray, and OptixBuildInputSphereArray), radius buffers (for OptixBuildInputCurveArray and OptixBuildInputSphereArray), and AABB buffers (for OptixBuildInputCustomPrimitiveArray and OptixBuildInputInstanceArray) for all motion keys. These are interpolated during traversal to obtain the continuous motion vertices and AABBs between the begin and end time.

For example:

```
Listing 5.14

CUdeviceptr d_motionVertexBuffers[3];

OptixBuildInputTriangleArray buildInput = {};
buildInput.vertexBuffers = d_motionVertexBuffers;
buildInput.numVertices = numVertices;
```

The motion options are typically defined by the mesh data which should directly map to the motion options on the geometry acceleration structure. For example, if a triangle mesh has three per-vertex motion values, the geometry acceleration structure needs to have three motion keys. Just as for non-motion meshes, it is possible to combine meshes within a single geometry acceleration structure to potentially increase traversal performance (this is generally recommended if there is only a single instance of each mesh and the meshes overlap or are close together). However, these meshes need to share the same motion options (as they are specified per geometry acceleration structure). The usual trade-offs apply in case meshes need to be updated from one frame to another as in an interactive application. The entire geometry acceleration structure needs to be rebuilt or refitted if the vertices of at least one mesh change.

It is possible to use a custom intersection program to decouple the actual vertex data and the motion options of the geometry acceleration structure. Intersection programs allow any kind of intersection routine. For example, it is possible to implement a three-motion-key-triangle intersection, but build a static geometry acceleration structure over AABBs by passing AABBs to the geometry acceleration structure build that enclose the full motion path of the triangles. However, this is generally not recommended for two reasons: First, the AABBs tend to increase in size very quickly even with very little motion. Second, it prevents the use of hardware intersection routines. Both of these effects can have a tremendous impact on performance.

5.10.3 Motion instance acceleration structure

Just as for a geometry acceleration structure, the motion options for an instance acceleration structure are specified as part of the build options. The notable difference to a geometry acceleration structure is that the motion options for an instance acceleration structure almost only impact performance. Hence, whether or not to build a motion instance acceleration structure has no impact on the correctness of the rendering (determining which instances can be intersected), but impacts memory usage as well as traversal performance. The only exception to that are the vanish flags as these force any instance of the instance acceleration

5 Acceleration structures 5.10 Motion blur

structure to be non-intersectable for any ray time outside of the time range of the instance acceleration structure.

In the following, guidelines are provided on setting the motion options to achieve good performance and avoid pitfalls. We will focus on the number of motion keys, usually the main discriminator for traversal performance and the only factor for memory usage. The optimal number of motion keys used for the instance acceleration structure build depends on the amount and linearity of the motion of the traversables referenced by the instances. The time beginning and ending range are usually defined by what is required to render the current frame. The recommendations given here may change in the future.

The following advice should be considered a simplified heuristic. A more detailed derivation of whether or not to use motion is given below. For RTCores version 1.0 (Turing architecture), do not use motion for instance acceleration structure, but instead build a static instance acceleration structure that can leverage hardware-accelerated traversal. For any other device (devices without RTCores or RTCores version >= 2.0), build a motion instance acceleration structure if any of the instances references a motion transform or a motion acceleration structure as traversable child.

If a motion instance acceleration structure is built, it is often sufficient to use a low number of motion keys (two or three) to avoid high memory costs. Also, it is not required to use a large number of motion keys just because one of the referenced motion transforms has many motion keys (such as the maximum motion keys of any referenced traversable by any of the instances). The motion options have no dependency between traversable objects and a high number of motion keys on the instance acceleration structure causes a high memory overhead. Clearly, motion should not be used for an instance acceleration structure if the instances only reference static traversables.

Further considerations when using motion blur:

Is motion enabled?

An instance acceleration structure should be built with motion on (the number of motion keys larger than one) if the overall amount of motion of the instanced traversables is non-minimal. For a single instance this can be quantified by the amount of change of its AABB over time. Hence, in case of a simple translation (for example, due to a matrix motion transform), the metric is the amount of the translation in comparison to the size of the AABB. In case of a scaling, it is the ratio of the size of the AABB at different points in times. If sufficiently many instanced traversables exhibit a non-minimal amount of change of their AABB over time, build a motion instance acceleration structure. Inversely, a static instance acceleration structure can yield higher traversal performance if many instanced traversables have no motion at all or only very little. The latter can happen for rotations. A rotation around the center of an object causes a rather small difference in the AABB of the object. However, if the rotational pivot point is not the center, it is likely to cause a big difference in the AABB of the object.

As it is typically hard to actually quantify the amount of motion for the instances, switch to motion if sufficiently many instanced traversables have or are expected to have motion. Yet it is difficult to predict when exactly it pays off to use or not use motion on the instance acceleration structure.

If motion is enabled, how many keys should be defined?

A reasonable metric to determine the required number of motion keys for an instance acceleration structure is the linearity of the motion of the instanced traversables. If there

5.10 Motion blur 5 Acceleration structures

are motion transforms with many motion keys, rotations, or a hierarchical set of motion transforms, more motion keys on the instance acceleration structure may increase traversal performance. Transformations like a simple translation, rotation around the center of an object, a small scale, or even all of those together are usually handles well by a two-motion-key instance acceleration structure.

Finally, the quality of the instance acceleration structure is also affected by the number of motion keys of the referenced traversables of the instances. As such, it is desirable to have the motion options of the instance acceleration structure match the motion options of any referenced motion transform. For example, if all instances reference motion transforms with three keys, it is reasonable to also use three motion keys for the instance acceleration structure. Note that also in this case the statement from above still applies that using more motion keys only helps if the underlying transformation results in a non-linear motion.

5.10.4 Motion matrix transform

The motion matrix transform traversable (OptixMatrixMotionTransform) transforms the ray during traversal using a motion matrix. The traversable provides a 3x4 row-major object-to-world transformation matrix for each motion key. The final motion matrix is constructed during traversal by interpolating the elements of the matrices at the nearest motion keys.

The OptixMatrixMotionTransform struct has a dynamic size, dependent on the number of motion keys. The struct specifies the header and the first two motion keys for convenience; when using more than than two keys, compute the size required for additional keys.

For example:

5.10.5 Motion scale/rotate/translate transform

The behavior of the motion transform OptixSRTMotionTransform is similar to the matrix motion transform OptixMatrixMotionTransform. In OptixSRTMotionTransform the

5 Acceleration structures 5.10 Motion blur

object-to-world transforms per motion key are specified as a scale, rotation and translation (SRT) decomposition instead of a single 3x4 matrix. Each motion key is a struct of type OptixSRTData, which consists of 16 floats:

```
Listing 5.16

typedef struct OptixSRTData {
   float sx, a, b, pvx, sy, c, pvy, sz, pvz, qx, qy, qz, qw, tx, ty, tz;
} OptixSRTData;
```

These 16 floats define the three components for scaling, rotation and translation whose product is the motion transformation:

• The scaling matrix *S*

$$S = \begin{bmatrix} sx & a & b & pvx \\ 0 & sy & c & pvy \\ 0 & 0 & sz & pvz \\ 0 & 0 & 0 & 1 \end{bmatrix}$$

defines an affine transformation that can include scale, shear, and a translation. The translation enables a pivot point to be defined for the scale, shear as well as the subsequent rotation.

• The quaternion *R*

$$R = \begin{bmatrix} qx & qy & qz & qw \end{bmatrix}$$

describes a rotation with angular component $qw = cos(\theta/2)$ and other components qx, qy and qz, where

$$\begin{bmatrix} qx & qy & qz \end{bmatrix} = sin(\theta/2) * \begin{bmatrix} ax & ay & az \end{bmatrix}$$

and where the axis $[ax \ ay \ az]$ is normalized.

• The translation *T*

$$T = \begin{bmatrix} 1 & 0 & 0 & tx \\ 0 & 1 & 0 & ty \\ 0 & 0 & 1 & tz \end{bmatrix}$$

defines another translation that is applied after the rotation. Typically, this translation includes the inverse translation from the matrix S to undo the pivot point transformation.

To obtain the effective transformation at time t, the elements of the components of S, R, and T are interpolated linearly and R is normalized afterwards. The components are then multiplied to obtain the combined transformation $C = T \times R \times S$. The transformation C is the effective object-to-world transformations at time t, and C^{-1} is the effective world-to-object transformation at time t.

5.10 Motion blur 5 Acceleration structures

Example 1 – Rotation about the origin

Use two motion keys. Set the first key to identity values. For the second key, define a quaternion from an axis and angle, for example, a 60-degree rotation about the z axis is given by:

$$Q = \begin{bmatrix} 0 & 0 & \sin(\pi/6) & \cos(\pi/6) \end{bmatrix}$$

Example 2 – Rotation about a pivot point

Use two motion keys. Set the first key to identity values. Represent the pivot point as a translation P, and define the second key as follows:

$$S' = P^{-1} \times S$$

$$T' = T \times P$$

$$C = T' \times R \times S'$$

Example 3 – Scaling about a pivot point

Use two motion keys. Set the first key to identity values. Represent the pivot as a translation $G = \begin{bmatrix} G_x & G_y & fG_z \end{bmatrix}$ and modify the pivot point described above:

$$P'_{x} = P_{x} + (-S_{x} * G_{x} + G_{x})$$

$$P'_{y} = P_{y} + (-S_{y} * G_{y} + G_{y})$$

$$P'_{z} = P_{z} + (-S_{z} * G_{z} + G_{z})$$

5.10.6 Transforms trade-offs

Several trade-offs must be considered when using transforms.

SRTs compared to matrix motion transforms

Use SRTs for any transformations containing a rotation. Only SRTs produce a smooth rotation without distortion. They also avoid any oversampling of matrix transforms to approximate a rotation. However, note that the maximum angle of rotation due to two neighboring SRT keys needs to be less than 180 degrees, hence, the dot product of the quaternions needs to be positive. This way the rotations are interpolated using the shortest path. If a rotation of 180 degrees or more is required, additional keys need to be specified such that the rotation between two keys is less than 180 degrees. OptiX uses nlerp to interpolate quaternion at runtime. While nlerp produces the best traversal performance, it causes non-constant velocity in the rotation. The variation of rotational velocity is directly dependent on the amount of the rotation. If near constant rotation velocity is required, more SRT keys can be used.

Due to the complexity of the rotation, instance acceleration structure builds with instances that reference SRT transforms can be relatively slow. For real-time or interactive applications, it can be advantageous to use matrix transforms to have fast rebuilds or refits of the instance acceleration structure.

Motion options for motion transforms

The motion options for motion transforms should be derived by the scene setup and used as needed. The number of keys is defined by the number of transformations

5 Acceleration structures 5.10 Motion blur

specified by the scene description. The beginning, ending times should be as needed for the frame or tighter if specified by the scene description.

Avoid duplicating instances of motion transforms to achieve a motion behavior that can also be expressed by a single motion transform but many motion keys. An example is the handling of irregular keys, which is discussed in the following section.

Dealing with irregular keys

OptiX only supports regular time intervals in its motion options. Irregular keys should be resampled to fit regular keys, potentially with a much higher number of keys if needed.

A practical example for this is a motion matrix transform that performs a rotation. Since the matrix elements are linearly interpolated between keys, the rotation is not an actual rotation, but a scale/shear/translation. To avoid visual artifacts, the rotation needs to be sampled with potentially many matrix motion keys. Such a sampling bounds the maximum error in the approximation of the rotation by the linear interpolation of matrices. The sampling should not try to minimize the number of motion keys by outputting irregular motion keys, but rather oversample the rotation with many keys.

Duplicate motion transforms should not be used as a workaround for irregular keys, where each key has varying motion beginning and ending times and vanish motion flags set. This duplication creates traversal overhead as all copies need to be intersected and their motion times compared to the ray's time.

6 Program pipeline creation

The following API functions are described in this section:

optixModuleCreateFromPTX optixModuleDestroy optixProgramGroupCreate optixProgramGroupGetStackSize optixPipelineCreate optixPipelineDestroy optixPipelineSetStackSize

Programs are first compiled into *modules* of type OptixModule. One or more modules are combined to create a *program group* of type OptixProgramGroup. Those program groups are then linked into an OptixPipeline on the GPU. This is similar to the compile and link process commonly found in software development. The program groups are also used to initialize the header of the SBT record associated with those programs.

The three create methods, optixModuleCreateFromPTX, optixProgramGroupCreate, and optixPipelineCreate take an optional log string. This string is used to report information about any compilation that may have occurred, such as compile errors or verbose information about the compilation result. To detect truncated output, the size of the log message is reported as an output parameter. It is not recommended that you call the function again to get the full output because this could result in unnecessary and lengthy work, or different output for cache hits. If an error occurred, the information that would be reported in the log string is also reported by the device context log callback (when provided).

Both mechanisms are provided for these create functions to allow a convenient mechanism for pulling out compilation errors from parallel creation operations without having to determine which output from the logger corresponds to which API invocation.

Symbols in OptixModule objects may be unresolved and contain extern references to variables and __device__ functions.

These symbols can be resolved during pipeline creation using the symbols defined in the pipeline modules. Duplicate symbols will trigger an error.

A *pipeline* contains all programs that are required for a particular ray-tracing launch. An application may use a different pipeline for each launch, or may combine multiple ray-generation programs into a single pipeline.

Most NVIDIA OptiX 7 API functions do not own any significant GPU state; Streaming Assembly (SASS) instructions, which define the executable binary programs in a pipeline, are an exception. The OptixPipeline owns the CUDA resource associated with the compiled SASS and it is held until the pipeline is destroyed. This allocation is proportional to the amount of compiled code in the pipeline, typically tens of kilobytes to a few megabytes. However, it is possible to create complex pipelines that require substantially more memory,

especially if large static initializers are used. Wherever possible, exercise caution in the number and size of the pipelines.

Module lifetimes need to extend to the lifetimes of program groups that reference them. After using modules to create an OptixPipeline through the OptixProgramGroup objects, modules may be destroyed with optixModuleDestroy.

6.1 Program input

NVIDIA OptiX 7 programs are encoded in either OptiX-IR, a proprietary intermediate representation, or PTX,⁸ an instruction set for parallel thread execution. OptiX-IR contains a richer representation of the code that enables symbolic debugging and provides opportunities for enhanced optimizations and future features. OptiX-IR is a binary format that can only be read by NVIDIA tools, unlike PTX, which is stored in plain-text format.

To create PTX programs, compile CUDA source files using the NVIDIA nvcc offline compiler or nvrtc JIT compiler. To create OptiX-IR programs, compile the CUDA source files with nvcc. OptiX device headers should be included in the source files to provide the device API for OptiX programs.

Transitioning from PTX to OptiX-IR input is recommended when using nvcc to generate code for OptiX. PTX will continue to be supported but may not provide all OptiX-IR features, such as symbolic debugging.

The following example uses nvcc to create an OptiX-IR program:

```
nvcc -optix-ir -Ipath-to-optix-sdk/include --use_fast_math myprogram.cu -o myprogram.optixir
```

The nvcc command-line options are explained in more detail as part of the usage description of the compiler options displayed with nvcc --help.

Note the following requirements for nvcc and nvrtc compilation:

- The streaming multiprocessor (SM) target of the input OptiX program must be less than or equal to the SM version of the GPU for which the module is compiled.
- To generate code for the minimum supported GPU (Maxwell), use architecture targets for SM 5.0, for example, --gpu-architecture=compute_50. Because OptiX rewrites the code internally, those targets will work on any newer GPU as well.
- CUDA Toolkits 10.2 and newer throw deprecation warnings for SM 5.0 targets. These can be suppressed with the compiler option -Wno-deprecated-gpu-targets.

If support for Maxwell GPUs is not required, you can use the next higher GPU architecture target SM 6.0 (Pascal) to suppress these warnings.

- Use --machine=64 (-m64). Only 64-bit code is supported in OptiX.
- Define the output type with --optix-ir or --ptx. Do not compile to obj or cubin.
- For debugging, use the debug flag -G. Symbolic debugging is currently only supported for OptiX-IR and not PTX, though PTX compiled with debug support can be used as input to OptiX.

^{8.} https://docs.nvidia.com/cuda/parallel-thread-execution/

^{9.} https://docs.nvidia.com/cuda/cuda-compiler-driver-nvcc/

^{10.} https://docs.nvidia.com/cuda/nvrtc/

- Enable --relocatable-device-code=true (-rdc). Command nvcc can also use the option --keep-device-functions, which is not supported by nvrtc. These flags prevent the CUDA compiler from eliminating direct or continuation callables as dead code.
- To get smaller and faster code, enable --use_fast_math. This flag enables .approx instructions for trigonometric functions and reciprocals, avoiding inadvertent use of slow double-precision floats. For performance reasons, it is recommended that you set this flag; the only exception is use cases that require more precision.
- To profile your code with Nsight Compute, 11 enable --generate-line-info and set debugLevel = OPTIX_COMPILE_DEBUG_LEVEL_MODERATE in both the OptixModuleCompileOptions and OptixPipelineLinkOptions in your application host code.

6.2 Programming model

The NVIDIA OptiX 7 programming model supports the *multiple instruction, multiple data* (MIMD) subset of CUDA. Execution must be independent of other threads. For this reason, shared memory usage and warp-wide or block-wide synchronization — such as barriers — are not allowed in the input PTX code. All other GPU instructions are allowed, including math, texture, atomic operations, control flow, and loading data to memory. Special warp-wide instructions like vote and ballot are allowed, but can yield unexpected results as the locality of threads is not guaranteed and neighboring threads can change during execution, unlike in the full CUDA programming model. Still, warp-wide instructions can be used safely when the algorithm in question is independent of locality by, for example, implementing warp-aggregated atomic adds.

The memory model is consistent only within the execution of a single launch index, which starts at the ray-generation invocation and only with subsequent programs reached from any optixTrace or callable program. This includes writes to stack allocated variables. Writes from other launch indices may not be available until after the launch is complete. If needed, atomic operations may be used to share data between launch indices, as long as an ordering between launch indices is not required. Memory fences are not supported.

The input PTX should include one or more NVIDIA OptiX 7 programs. The type of program affects how the program can be used during the execution of the pipeline. These program types are specified by prefixing the program's name with the following:

Program type	Function name prefix
Ray generation	raygen
Intersection	intersection
Any-hit	anyhit
Closest-hit	closesthit
Miss	miss
Direct callable	direct_callable
Continuation callable	continuation_callable
Exception	exception

 $^{11.\ \}texttt{https://developer.nvidia.com/nsight-compute}$

If a particular function needs to be used with more than one type, then multiple copies with corresponding program prefixes should be generated.

In addition, each program may call a specific set of device-side intrinsics that implement the actual ray-tracing-specific features. (See "Device-side functions" (page 75).)

6.3 Module creation

A module may include multiple programs of any program type. Two option structs control the parameters of the compilation process:

```
OptixPipelineCompileOptions
```

Must be identical for all modules used to create program groups linked in a single pipeline.

OptixModuleCompileOptions

May vary across the modules within the same pipeline.

These options control general compilation settings, for example, the level of optimization. OptixPipelineCompileOptions controls features of the API such as the usage of custom any-hit programs, curve primitives, sphere primitives, motion blur, exceptions, ray payload and primitive attributes. For example:

```
Listing 6.1
OptixModuleCompileOptions moduleCompileOptions = {};
moduleCompileOptions.maxRegisterCount =
   OPTIX_COMPILE_DEFAULT_MAX_REGISTER_COUNT;
moduleCompileOptions.optLevel =
   OPTIX_COMPILE_OPTIMIZATION_DEFAULT;
moduleCompileOptions.debugLevel =
   OPTIX_COMPILE_DEBUG_LEVEL_MINIMAL;
moduleCompileOptions.numPayloadTypes = 0;
moduleCompileOptions.payloadTypes = 0;
OptixPipelineCompileOptions pipelineCompileOptions = {};
pipelineCompileOptions.usesMotionBlur = false;
pipelineCompileOptions.traversableGraphFlags =
   OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_LEVEL_INSTANCING;
pipelineCompileOptions.numPayloadValues = 2;
pipelineCompileOptions.numAttributeValues = 2;
pipelineCompileOptions.exceptionFlags = OPTIX_EXCEPTION_FLAG_NONE;
pipelineCompileOptions.pipelineLaunchParamsVariableName = "params";
pipelineCompileOptions.usesPrimitiveTypeFlags = 0;
OptixModule module = nullptr;
char* ptxData = ...;
size_t logStringSize = sizeof(logString);
```

```
OptixResult res = optixModuleCreateFromPTX(
    optixContext,
    &moduleCompileOptions,
    &pipelineCompileOptions,
    ptxData, ptx.size(),
    logString, &logStringSize,
    &module);
```

The numAttributeValues field of OptixPipelineCompileOptions defines the number of 32-bit words that are reserved to store the attributes. This corresponds to the attribute definition in optixReportIntersection. See "Reporting intersections and attribute access" (page 80).

The numPayloadValues field of OptixPipelineCompileOptions defines the number of 32-bit words that are reserved to store the ray payload. Alternatively ray payload usage can be specified in more detail using the numPayloadTypes and payloadTypes fields in OptixModuleCompileOptions. See "Payload" (page 93).

Note: For best performance when your scene contains nothing but built-in triangles, set OptixPipelineCompileOptions::usesPrimitiveTypeFlags to just OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE.

6.4 Pipeline launch parameter

You specify launch-varying parameters or values that must be accessible from any module through a user-defined variable named in OptixPipelineCompileOptions. In each module that needs access, declare this variable with extern or extern "C" linkage and the __constant__ memory specifier. The size of the variable must match across all modules in a pipeline. Variables of equal size but differing types may trigger undefined behavior.

For example, the header file in Listing 6.2 defines the variable to shared, named params, as an instance of the Params struct:

```
Listing 6.2 - Struct defined in header file params.h

struct Params
{
    uchar4* image;
    unsigned int image_width;
};
extern "C" __constant__ Params params;
```

Listing 6.3 shows that by including header file params.h, programs can access and set the values of the shared params struct instance:

```
Listing 6.3 – Use of header file params.h in OptiX program

#include "params.h"

extern "C"

__global___ void draw_solid_color()
```

```
unsigned int image_index =
    launch_index.y * params.image_width + launch_index.x];
params.image[image_index] = make_uchar4(255, 0, 0);
}
```

6.4.1 Parameter specialization

In some cases it could be beneficial to specialize modules in a pipeline to toggle specific features on and off. For example, users may wish to compile support in their shaders for calculating shadow rays, but may wish to disable this support if the scene parameters do not require them. Users could support this with either multiple versions of the PTX program or by reading a value from the pipeline launch parameters to indicate whether shadows are supported. Multiple versions of the PTX program would allow for the best performance, but come at the cost of maintaining and storing all those program versions. NVIDIA OptiX 7 provides a mechanism for specializing values in the pipeline launch parameters.

During compilation of the module, NVIDIA OptiX 7 will attempt to find loads to the pipeline launch parameter struct that are specified by

OptixPipelineCompileOptions::pipelineLaunchParamsVariableName within a given range. These specified loads are then each replaced with a predefined value. Compiler optimization passes use those constant values.

The struct OptixModuleCompileBoundValueEntry in Listing 6.4 can specify an array of bytes that will replace a portion of the pipeline parameters:

```
Listing 6.4

struct OptixModuleCompileBoundValueEntry {
    size_t pipelineParamOffsetInBytes;
    size_t sizeInBytes;
    const void* boundValuePtr;

    const char* annotation; Optional string to display
};
```

Listing 6.5 shows how an array of OptixModuleCompileBoundValueEntry structs can be specified in OptixModuleCompileOptions during module compilation:

Listing 6.6 is an example of specializing a module to disable shadow rays:

```
Listing 6.6 - Device code that references the pipeline launch parameters to determine if shadows are enabled

struct LP {
    bool useShadows;
};

extern "C" {
    __constant__ LP params;
}

extern "C"
    __global__ void __closesthit__ch()
{
    float3 shadowColor = make_float3( 1.f, 1.f, 1.f );
    if ( params.useShadows ) {
        shadowColor = traceShadowRay(...);
    }
    ...
}
```

On the host side, Listing 6.7 shows the implementation of the launch parameters:

```
Listing 6.7 — Host code to specialize the pipeline launch parameters

LP launchParams = {};
launchParams.useShadows = false;

OptixModuleCompileBoundValueEntry useShadow = {};
useShadow.pipelineParamOffset = offsetof(LP, useShadows);
useShadow.sizeInBytes = sizeof(LP::useShadows);
useShadow.boundValuePtr = &launchParams.useShadows;

OptixModuleCompileOptions moduleCompileOptions = {};
moduleCompileOptions.boundValues = &useShadow;
moduleCompileOptions.numBoundValues = 1;
...
optixModuleCreateFromPTX(..., moduleCompileOptions, ...);
```

This pipeline launch parameter specialization makes the code of Listing 6.8 possible:

```
Listing 6.8

extern "C"
  __global__ void __closesthit__ch()
{
    float3 shadowColor = make_float3( 1.f, 1.f, 1.f );
    if ( false )
    {
        shadowColor = traceShadowRay(...);
    }
}
```

```
}
....
```

Subsequent optimization would remove unreachable code, producing Listing 6.9:

```
Listing 6.9

extern "C"
__global__ void __closesthit__ch()
{
   float3 shadowColor = make_float3( 1.f, 1.f, 1.f );
   ...
}
```

The bound values are intended to represent a constant value in the pipelineParams. NVIDIA OptiX 7 will attempt to locate all loads from the pipelineParams and correlate them to the appropriate bound value. However, there are cases where these loads and bound values cannot be safely or reliably correlated. For example, correlation is not possible if the pointer to the pipelineParams is passed as an argument to a non-inline function or if the offset of the load to the pipelineParams cannot be statically determined due to access in a loop. No module should rely on the value being specialized in order to work correctly. The values in the pipelineParams specified on optixLaunch should match the bound value. If validation mode is enabled on the context, NVIDIA OptiX 7 will verify that the bound values that are specified match the values in pipelineParams specified to optixLaunch.

If caching is enabled, changes in these values will result in newly compiled modules.

The pipelineParamOffset and sizeInBytes must be within the bounds of the pipelineParams variable or OPTIX_ERROR_INVALID_VALUE will be returned from optixModuleCreateFromPTX.

If more than one bound value overlaps or the size of a bound value is equal to 0, an OPTIX_ERROR_INVALID_VALUE will be returned from optixModuleCreateFromPTX.

The same set of bound values do not need to be used for all modules in a pipeline, but overlapping values between modules must have the same value. OPTIX_ERROR_INVALID_VALUE will be returned from optixPipelineCreate otherwise.

6.5 Program group creation

OptixProgramGroup objects are created from one to three OptixModule objects and are used to fill the header of the SBT records. (See "Shader binding table" (page 57).) There are five types of program groups.

```
OPTIX_PROGRAM_GROUP_KIND_RAYGEN
OPTIX_PROGRAM_GROUP_KIND_MISS
OPTIX_PROGRAM_GROUP_KIND_EXCEPTION
OPTIX_PROGRAM_GROUP_KIND_HITGROUP
OPTIX_PROGRAM_GROUP_KIND_CALLABLES
```

Modules can contain more than one program. The program in the module is designated by its entry function name as part of the OptixProgramGroupDesc struct passed to optixProgramGroupCreate. Four program groups can contain only a single program; only

OPTIX_PROGRAM_GROUP_KIND_HITGROUP can designate up to three programs for the closest-hit, any-hit, and intersection programs.

Programs from modules can be used in any number of OptixProgramGroup objects. The resulting program groups can be used to fill in any number of SBT records. Program groups can also be used across pipelines as long as the compilation options match.

The lifetime of a module must extend to the lifetime of any OptixProgramGroup that references that module.

A hit group specifies the intersection program used to test whether a ray intersects a primitive, together with the hit shaders to be executed when a ray does intersect the primitive. For built-in primitive types, a built-in intersection program should be obtained from optixBuiltinISModuleGet() and used in the hit group. As a special case, the intersection program is not required – and is ignored – for triangle primitives.

The following examples show how to construct a single hit-group program group:

```
Listing 6.10 – Construct hit-group for custom primitives
OptixModule shadingModule, intersectionModule;
             shadingModule and intersectionModule created here by optixModuleCreateFromPTX
OptixProgramGroupDesc pgDesc = {};
pgDesc.kind = OPTIX_PROGRAM_GROUP_KIND_HITGROUP;
pgDesc.hitgroup.moduleCH = shadingModule;
pgDesc.hitgroup.entryFunctionNameCH = "__closesthit__shadow";
pgDesc.hitgroup.moduleAH = shadingModule;
pgDesc.hitgroup.entryFunctionNameAH = "__anyhit__shadow";
pgDesc.hitgroup.moduleIS = intersectionModule;
pgDesc.hitgroup.entryFunctionNameIS = "__intersection__sphere";
OptixProgramGroupOptions pgOptions = {};
OptixProgramGroup sphereGroup = nullptr;
optixProgramGroupCreate(
   optixContext,
    &pgDesc,
               programDescriptions
         numProgramGroups
    &pgOptions,
                  programOptions
    logString, sizeof(logString),
    &sphereGroup);
                     programGroup
```

```
Listing 6.11 — Construct hit-group for built-in curves primitives

OptixModule shadingModule, intersectionModule;

shadingModule created here by optixModuleCreateFromPTX
```

```
OptixBuiltinISOptions builtinISOptions = {};
builtinISOptions.builtinISModuleType =
   OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BSPLINE;
OptixResult res = optixBuiltinISModuleGet(
   optixContext,
   &moduleCompileOptions,
   &pipelineCompileOptions,
   &builtinISOptions,
   &intersectionModule);
OptixProgramGroupDesc pgDesc= {};
pgDesc.kind = OPTIX_PROGRAM_GROUP_KIND_HITGROUP;
pgDesc.hitgroup.moduleCH = shadingModule;
pgDesc.hitgroup.entryFunctionNameCH = "__closesthit__curves";
pgDesc.hitgroup.moduleAH = nullptr; Any-hitshader is optional
pgDesc.hitgroup.entryFunctionNameAH = nullptr;
pgDesc.hitgroup.moduleIS = intersectionModule;
pgDesc.hitgroup.entryFunctionNameIS = nullptr;
                                                 No name for built-in IS
OptixProgramGroupOptions pgOptions = {};
OptixProgramGroup curvesGroup = nullptr;
optixProgramGroupCreate(
   optixContext,
   &pgDesc,
   1,
   &pgOptions,
   logString, sizeof(logString),
   &curvesGroup);
```

A hit-group construction for sphere primitives would be similar to the built-in curves example, replacing the module type OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BSPLINE by OPTIX_PRIMITIVE_TYPE_SPHERE.

Multiple program groups of varying kinds can be constructed with a single call to optixProgramGroupCreate. The following code demonstrates the construction of a ray-generation and miss program group.

```
OptixModule rg, miss;
Ray-generation and miss programs created here by optixModuleCreateFromPTX

OptixProgramGroupDesc pgDesc[2] = {};
pgDesc[0].kind = OPTIX_PROGRAM_GROUP_KIND_MISS;
pgDesc[0].miss.module = miss1;
pgDesc[0].miss.entryFunctionName = "__miss__radiance";
pgDesc[1].kind = OPTIX_PROGRAM_GROUP_KIND_RAYGEN;
pgDesc[1].raygen.module = rg;
pgDesc[1].raygen.entryFunctionName = "__raygen__pinhole_camera";
```

```
OptixProgramGroupOptions pgOptions = {};
OptixProgramGroup raygenMiss[2];
optixProgramGroupCreate(
   optixContext,
   &pgDesc, programDescriptions

2, numProgramGroups

&pgOptions, programOptions
logString, sizeof(logString),
   raygenMiss); programGroup
```

Options defined in OptixProgramGroupOptions may vary across program groups linked into a single pipeline, similar to OptixModuleCompileOptions.

6.6 Pipeline linking

After all program groups of a pipeline are defined, they must be linked into an OptixPipeline. The resulting OptixPipeline object is then used to invoke a ray-generation launch.

When the OptixPipeline is linked, some fixed function components may be selected based on OptixPipelineLinkOptions and OptixPipelineCompileOptions. These options were previously used to compile the modules in the pipeline. The link options consist of the maximum recursion depth setting for recursive ray tracing, along with pipeline level settings for debugging. However, the value for the maximum recursion depth has an upper limit that overrides an limit set by the link options. (See "Limits" (page 73).)

For example, the following code creates and links an OptixPipeline:

After calling optixPipelineCreate, the fully linked module is loaded into the driver.

NVIDIA OptiX 7 uses a small amount of GPU memory per pipeline. This memory is released when the pipeline or device context is destroyed.

6.7 Pipeline stack size

The programs in a module may consume two types of stack structure: a *direct stack* and a *continuation stack*. The resulting stack needed for launching a pipeline depends on the resulting call graph, so the pipeline must be configured with the appropriate stack size. These sizes can be determined by the compiler for each program group. A pipeline may be reused for different call graphs as long as the set of programs is the same. For this reason, the pipeline stack size is configured separately from the pipeline compilation options.

The direct stack requirements resulting from ray-generation, miss, exception, closest-hit, any-hit and intersection programs and the continuation stack requirements resulting from exception programs are calculated internally and do not need to be configured. The direct stack requirements resulting from direct-callable programs, as well as the continuation stack requirements resulting from ray-generation, miss, closest-hit, any-hit, intersection, and continuation-callable programs need to be configured. If these are not configured explicitly, an internal default implementation is used. When the maximum depth of call trees of continuation-callable and direct-callable programs is two or less, the default implementation is correct (but not necessarily optimal) Even in cases where the default implementation is correct, Users can always provide more precise stack requirements based on their knowledge of a particular call graph structure.

To query individual program groups for their stack requirements, use optixProgramGroupGetStackSize. Use this information to calculate the total required stack sizes for a particular call graph of NVIDIA OptiX 7 programs. To set the stack sizes for a particular pipeline, use optixPipelineSetStackSize. For other parameters, helper functions are available to implement these calculations. The following is an explanation about how to compute the stack size for optixPipelineSetStackSize, starting from a very conservative approach, and refining the estimates step by step.

Let cssRG denote the maximum continuation stack size of all ray-generation programs; similarly for miss, closest-hit, any-hit, intersection, and continuation-callable programs. Let dssDC denote the maximum direct stack size of all direct callable programs. Let maxTraceDepth denote the maximum trace depth (as in OptixPipelineLinkOptions::maxTraceDepth), and let maxCCDepth and maxDCDepth denote the

OptixPipelineLinkOptions::maxTraceDepth), and let maxCCDepth and maxDCDepth denote the maximum depth of call trees of continuation-callable and direct-callable programs, respectively. Then a simple, conservative approach to compute the three parameters of optixPipelineSetStackSize is:

```
cssCHOrMSPlusCCTree =
   max(cssCH, cssMS) + cssCCTree;

continuationStackSize =
   cssRG
   + cssCCTree
   + maxTraceDepth * cssCHOrMSPlusCCTree
   + cssIS
   + cssAH;
Upper bound on continuation stack used by closest-hit or miss programs, including the call tree of continuation-callable programs
```

This computation can be improved in several ways. For the computation of continuationStackSize, the stack sizes cssIS and cssAH are not used on top of the other summands, but can be offset against one level of cssCHOrMSPlusCCTree. This gives a more complex but better estimate:

```
Listing 6.15

continuationStackSize =
    cssRG
+ cssCCTree
+ max(1, maxTraceDepth) - 1) * cssCHOrMSPlusCCTree
+ min(maxTraceDepth, 1) * max(cssCHOrMSPlusCCTree, cssIS+cssAH);
```

The preceding formulas are implemented by the helper function optixUtilComputeStackSizes.

The computation of the first two terms can be improved if the call trees of direct callable programs are analyzed separately based on the semantic type of their call site. In this context, call sites in any-hit and intersection programs count as traversal, whereas call sites in ray-generation, miss, and closest-hit programs count as state.

```
Listing 6.16

directCallableStackSizeFromTraversal =
   maxDCDepthFromTraversal * dssDCFromTraversal;
directCallableStackSizeFromState =
   maxDCDepthFromState * dssDCFromState;
```

This improvement is implemented by the helper function optixUtilComputeStackSizesDCSplit.

Depending on the scenario, these estimates can be improved further, sometimes substantially. For example, imagine there are two call trees of continuation-callable programs. One call tree is deep, but the involved continuation-callable programs need only a small continuation stack. The other call tree is shallow, but the involved continuation-callable programs needs a quite large continuation stack. The estimate of cssCCTree can be improved as follows:

```
Listing 6.17

cssCCTree = max(maxCCDepth1 * cssCC1, maxCCDepth2 * cssCC2);
```

This improvement is implemented by the helper function optixUtilComputeStackSizesCssCCTree.

Similar improvements might be possible for all expressions involving maxTraceDepth if the ray types are considered separately, for example, camera rays and shadow rays.

6.7.1 Constructing a path tracer

A simple path tracer can be constructed from two ray types: camera rays and shadow rays. The path tracer will consist only of ray-generation, miss, and closest-hit programs, and will not use any-hit, intersection, continuation-callable, or direct-callable programs. The camera rays will invoke only the miss and closest-hit programs MS1 and CH1, respectively. CH1 might trace shadow rays, which invoke only the miss and closest-hit programs MS2 and CH2, respectively. That is, the maximum trace depth is two and the initial formulas simplify to:

```
Listing 6.18

directCallableStackSizeFromTraversal = maxDCDepth * dssDC;
directCallableStackSizeFromState = maxDCDepth * dssDC;
continuationStackSize =
    cssRG + 2 * max(cssCH1, cssCH2, cssMS1, cssMS2);
```

However, from the call graph structure it is clear that MS2 or CH2 can only be invoked from CH1. This restriction allows for the following estimate:

This estimate is never worse than the previous one, but often better, for example, in the case where the closest-hit programs have different stack sizes (and the miss programs do not dominate the expression).

The helper function optixUtilComputeStackSizesSimplePathTracer implements this formula by permitting two arrays of closest-hit programs instead of two single programs.

6.8 Compilation cache

Compilation work is triggered automatically when calling optixModuleCreateFromPTX or optixProgramGroupCreate, and also potentially during optixPipelineCreate. This work is automatically cached on disk if enabled on the OptixDeviceContext. Caching reduces compilation effort for recurring programs and program groups. While it is enabled by default, users can disable it through the use of optixDeviceContextSetCacheEnabled. See "Context" (page 15) for other options regarding the compilation cache.

Generally, cache entries are compatible with the same driver version and GPU type only.

7 Shader binding table

The *shader binding table* (SBT) is an array that contains information about the location of programs and their parameters. The SBT resides in device memory and is managed by the application.

7.1 Records

A *record* is an array element of the SBT that consists of a header and a data block. The header content is opaque to the application, containing information accessed by traversal execution to identify and invoke programs. The data block is not used by NVIDIA OptiX 7 and holds arbitrary program-specific application information that is accessible in the program. The header size is defined by the OPTIX_SBT_RECORD_HEADER_SIZE macro (currently 32 bytes).

The API function optixSbtRecordPackHeader and a given OptixProgramGroup object are used to fill the header of an SBT record. The SBT records must be uploaded to the device prior to an NVIDIA OptiX 7 launch. The contents of the SBT header are opaque, but can be copied or moved. If the same program group is used in more than one SBT record, the SBT header can be copied using plain device-side memory copies. For example:

```
Listing 7.1
template <typename T>
struct Record
   __align__(OPTIX_SBT_RECORD_ALIGNMENT)
       char header[OPTIX_SBT_RECORD_HEADER_SIZE];
   T data;
};
typedef Record<RayGenData> RayGenSbtRecord;
OptixProgramGroup raygenPG;
. . .
RayGenSbtRecord rgSBT;
rgSBT.data.color = make_float3(1.0f, 1.0f, 0.0f);
optixSbtRecordPackHeader(raygenPG, &rgSBT);
CUdeviceptr deviceRaygenSbt;
cudaMalloc((void**)&deviceRaygenSbt, sizeof(RayGenSbtRecord));
cudaMemcpy((void**)deviceRaygenSbt, &rgSBT,
    sizeof(RayGenSbtRecord), cudaMemcpyHostToDevice);
```

SBT headers can be reused between pipelines as long as the compile options match between modules and program groups. The data section of an SBT record can be accessed on the device using the optixGetSbtDataPointer device function.

7 Shader binding table 7.2 Layout

7.2 Layout

A shader binding table is split into five sections, where each section represents a unique program group type:

Group	Program types in group	Value of enum OptixProgramGroupKind
Ray generation	ray-generation	OPTIX_PROGRAM_GROUP_KIND_RAYGEN
Exception	exception	OPTIX_PROGRAM_GROUP_KIND_EXCEPTION
Miss	miss	OPTIX_PROGRAM_GROUP_KIND_MISS
Hit	intersection, any-hit, closest-hit	OPTIX_PROGRAM_GROUP_KIND_HITGROUP
Callable	direct-callable, continuation-callable	OPTIX_PROGRAM_GROUP_KIND_CALLABLES

OptiX program groups

See also "Program group creation" (page 48).

Pointers to the SBT sections are passed to the NVIDIA OptiX 7 launch:

```
Listing 7.2
typedef struct OptixShaderBindingTable
                                  Device address of the SBT record of the ray generation
    CUdeviceptr raygenRecord;
                                  program to start launch
    CUdeviceptr exceptionRecord;
                                       Device address of the SBT record of the exception shader
    CUdeviceptr missRecordBase;
                                                Arrays of SBT records. The base address,
    unsigned int missRecordStrideInBytes;
                                                stride in bytes and maximum index are
    unsigned int missRecordCount;
                                                defined.
    CUdeviceptr hitgroupRecordBase;
    unsigned int hitgroupRecordStrideInBytes;
    unsigned int hitgroupRecordCount;
   CUdeviceptr callablesRecordBase;
    unsigned int callablesRecordStrideInBytes;
    unsigned int callablesRecordCount;
} OptixShaderBindingTable;
```

All SBT records on the device are expected to have a minimum memory alignment, defined by OPTIX_SBT_RECORD_ALIGNMENT (currently 16 bytes). Therefore, the stride between records must also be a multiple of OPTIX_SBT_RECORD_ALIGNMENT. Each section of the SBT is an independent memory range and is not required to be allocated contiguously.

The selection of an SBT record depends on the program type and uses the corresponding base pointer. Since there can only be a single call to both ray-generation and exception programs, a stride is not required for these two program group types and the passed-in pointer is expected to point to the desired SBT records.

7.3 Acceleration structures 7 Shader binding table

For other types, the SBT record at index *sbt-index* for a program group of type *group-type* is located by the following formula:

```
group-typeRecordBase + sbt-index * group-typeRecordStrideInBytes
```

For example, the third record (index 2) of the miss group would be:

```
missRecordBase + 2 * missRecordStrideInBytes
```

The index to records in the shader binding table is used in different ways for the miss, hit, and callables groups:

Miss

Miss programs are selected for every optixTrace call using the missSBTIndex parameter.

Callables

Callables take the index as a parameter and call the direct-callable when invoking optixDirectCall and continuation-callable when invoking optixContinuationCall.

Any-hit, closest-hit, intersection

The computation of the index for the hit group (intersection, any-hit, closest-hit) is done during traversal. See "Acceleration structures" (page 59) for more detail.

7.3 Acceleration structures

The selection of the SBT hit group record for the instance is slightly more involved to allow for a number of use cases such as the implementation of different ray types. The SBT record index sbtIndex is determined by the following index calculation during traversal:

```
sbt-index =
     sbt-instance-offset
```

- + (sbt-geometry-acceleration-structure-index * sbt-stride-from-trace-call)
- + sbt-offset-from-trace-call

The index calculation depends upon the following SBT indices and offsets:

- Instance offset
- Geometry acceleration structure index
- Trace offset
- Trace stride

SBT instance offset 7.3.1

Instance acceleration structure instances (type OptixInstance) store an SBT offset that is applied during traversal. This is zero for single geometry-AS traversable because there is no corresponding instance-AS to hold the value. (See Traversal of a single geometry acceleration structure (page 32).) This value is limited to 28 bits (see the declaration of OptixInstance::sbtOffset).

SBT geometry-AS index 7.3.2

Each geometry acceleration structure build input references at least one SBT record. The first SBT geometry acceleration structure index for each geometry acceleration structure build

7 Shader binding table 7.3 Acceleration structures

input is the prefix sum of the number of SBT records. Therefore, the computed SBT geometry acceleration structure index is dependent on the order of the build inputs.

The following example demonstrates a geometry acceleration structure with three build inputs. Each build input references one SBT record by specifying numSBTRecords=1. When intersecting geometry at trace time, the SBT geometry acceleration structure index used to compute the sbtIndex to select the hit group record will be organized as follows:

SBT geometry-AS index	0	1	2
	Build input[0]		
Geometry-AS build input		Build input[1]	
			Build input[2]

In this simple example, the index for the build input equals the SBT geometry acceleration structure index. Hence, whenever a primitive from "Build input [1]" is intersected, the SBT geometry acceleration structure index is one.

When a single build input references multiple SBT records (for example, to support multiple materials per geometry), the mapping corresponds to the prefix sum over the number of referenced SBT records.

For example, consider three build inputs where the first build input references four SBT records, the second references one SBT record, and the last references two SBT records:

SBT geometry-AS index	0	1	2	3	4	5	6
Geometry-AS build	Build input[0] numSBTRecords=4						
input					Build input[1] numSBTRecords=1		
						Build input[2] SBTIndexOffset2	

These three build inputs result in the following possible SBT geometry acceleration structure indices when intersecting the corresponding geometry acceleration structure build input:

- One index in the range of [0,3] if a primitive from "Build input [0]" is intersected
- Four if a primitive from "Build input [1]" is intersected
- One index in the range of [5,6] if a primitive from "Build input [2]" is intersected

The per-primitive SBT index offsets, as specified by using sbtIndexOffsetBuffer, are local to the build input. Hence, per-primitive offsets in the range [0,3] for the build input 0 and in the range [0,1] for the last build input, map to the SBT geometry acceleration structure index as follows:

7.3 Acceleration structures 7 Shader binding table

SBT geometry-AS index	0	1	2	3	4	5	6
	[0]						
Build input[0]		[1]					
SBTIndexOffset:			[2]				
				[3]			
Build input[1] SBTIndexOffset=nullptr							
Build input[2]						[0]	
SBTIndexOffset:							[1]

Because build input 1 references a single SBT record, a sbtIndexOffsetBuffer does not need to be specified for the geometry acceleration structure build. See "Acceleration structures" (page 19).

7.3.3 SBT trace offset

The optixTrace function takes the parameter SBToffset, allowing for an SBT access shift for this specific ray. It is required to implement different ray types.

7.3.4 SBT trace stride

The parameter SBTstride, defined as an index offset, is multiplied by optixTrace with the SBT geometry acceleration structure index. It is required to implement different ray types.

7.3.5 Example SBT for a scene

In this example, a shader binding table implements the program selection for a simple scene containing one instance acceleration structure and two instances of the same geometry acceleration structure, where the geometry acceleration structure has two build inputs:




Fig. 7.1 – *Structure of a simple scene*

The first build input references a single SBT record, while the second one references two SBT records. There are two ray types: one for forward path tracing and one for shadow rays (next event estimation). The two instances of the geometry acceleration structure have different transforms and SBT offsets to allow for material variation in each instance of the same geometry acceleration structure. Therefore, the SBT needs to hold two miss records and 12 hit

7 Shader binding table 7.3 Acceleration structures

group records (three for the geometry acceleration structure, $\times 2$ for the ray types, $\times 2$ for the two instances in the instance acceleration structure).

The SBT is structured in the following way:

Raygen	Miss		instance0.sbtOffset = 0						instance1.sbtOffset = 6					
RG0	MS0 MS1		hit0	hit1	hit2	hit3	hit4	hit5	hit6	hit7	hit8	hit9	hit10	hit11
The preceding programs are called for the following combination of geometry and ray types														
Instance:			0	0	0	0	0	0	1	1	1	1	1	1
Build input:			0	0	1	1	1	1	0	0	1	1	1	1
SBT index:			0	1	2	3	4	5	6	7	8	9	10	11
SBT instance offset:			0	0	0	0	0	0	6	6	6	6	6	6
SBT geometry-AS index:			0	0	1	1	2	2	0	0	1	1	2	2
Build input SBT index offset:			-	-	0	0	1	1	-	-	0	0	1	1
Trace offset/ray type:	0	1	0	1	0	1	0	1	0	1	0	1	0	1

To trace a ray of type 0 (for example, for path tracing):

```
Listing 7.3

optixTrace(IAS_handle,
    ray_org, ray_dir,
    tmin, tmax, time,
    visMask, rayFlags,
    0, sbtOffset

2, sbtStride

0, missSBTIndex
    rayPayload0, ...);
```

Shadow rays need to pass in an adjusted sbtOffset as well as missSBTIndex:

```
Listing 7.4

optixTrace(IAS_handle,
    ray_org, ray_dir,
    tmin, tmax, time,
    visMask, rayFlags,
    1, sbtOffset

2, sbtStride

1, missSBTIndex
    rayPayload0, ...);
```

Program groups of different types (ray generation, miss, intersection, and so on) do not need to be adjacent to each other as shown in the example. The pointer to the first SBT record of each program group type is passed to optixLaunch, as described previously, which allows for arbitrary spacing in the SBT between the records of different program group types.

7.4 SBT record access on device

To access the SBT data section of the currently running program, request its pointer by using an API function:

```
Listing 7.5

CUdeviceptr optixGetSbtDataPointer();
```

Typically, this pointer is cast to a pointer that represents the layout of the data section. For example, for a closest hit program, the application gets access to the data associated with the SBT record that was used to invoke that closest hit program:

```
Listing 7.6 - Data for closest hit program

struct CHData {
    int meshIdx; Triangle mesh build input index
    float3 base_color;
};

CHData* material_info = (CHData*)optixGetSbtDataPointer();
```

The program is encouraged to rely on the alignment constraints of the SBT data section to read this data efficiently.

8 Curves and spheres

8.1 Differences between curves, spheres, and triangles

Ray tracing curves or spheres with NVIDIA OptiX 7 is similar to the procedure for ray tracing triangles;

```
see "Curve build inputs" (page 23).
```

The differences between curves, spheres, and triangles include the following:

• In the triangle build input, the index buffer is optional.

In the curves build input, it is mandatory.

In the spheres build input, it is missing.

• Each curves build input references just a single SBT record.

Unlike triangles or spheres, there is no per-primitive SBT index.

It is still possible to use multiple materials for curves in the same BVH,

by using multiple build inputs, one per material.

(Because there is only one SBT record, the OptixGeometryFlags are specified by only one int, rather than an array of ints.)

• There is no preTransform field for curves or spheres.

If there were, a nonuniform scale or shear transformation would yield different results as a pre-transform than as an instance transform.

Nonuniform instance transforms of curves create elliptical cross sections, while preTransform would still have a circular cross section.

• Each shader binding table record for curves requires a hit group that uses a built-in intersection program for curves.

In the OptixProgramGroupHitgroup, you must use a module returned by optixBuiltinISModuleGet() for moduleIS, and nullptr for entryFunctionNameIS.

This also applies to spheres.

• Curves or spheres must be explicitly enabled in the pipeline to be rendered; triangles and custom primitives are enabled by default.

This is enabled in the OptixPipelineCompileOptions::usesPrimitiveTypeFlags by setting the relevant bits from OptixPrimitiveTypeFlags.

```
Listing 8.1
OptixPipelineCompileOptions pipelineCompileOptions = {};
```

```
pipelineCompileOptions.usesPrimitiveTypeFlags =

OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE |

OPTIX_PRIMITIVE_TYPE_FLAGS_CUSTOM |

OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_LINEAR |

OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_QUADRATIC_BSPLINE |

OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BSPLINE |

OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CATMULLROM |

OPTIX_PRIMITIVE_TYPE_FLAGS_SPHERE;
```

 To render motion blur for any primitive, motion blur must be enabled in the pipeline.

But for curves or spheres, motion blur must also be enabled in the built-in intersection program,

by setting the OptixBuiltinISOptions::usesMotionBlur flag.

(Note this flag should only be set to true when using vertex motion blur, not when using motion transform blur.)

8.2 Splitting curve segments

NVIDIA OptiX 7 can split curve segments into multiple sub-segments, and bound the sub-segments separately.

This gives faster performance but costs more memory.

Splitting can be controlled via OptixBuildFlags, using OPTIX_BUILD_FLAG_PREFER_FAST_TRACE for a splitting factor higher than default, and OPTIX_BUILD_FLAG_PREFER_FAST_BUILD for a lower splitting factor.

Note: Splitting means that the same primitive (the same curve segment) can be hit multiple times by a ray.

Geometry with OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL set is not split; in this case, each segment can only be hit once, but a longer curve strand composed of multiple segments can still be hit more than once.

8.3 Curves and the hit program

In hit programs, curve hits provide a single attribute: the curve parameter ("u") within the segment corresponding to the intersection, returned by optixGetCurveParameter().

When and only when an end cap is hit, the "u" parameter returned is exactly 0.0 or 1.0.

As with all hit programs, optixGetRayTmax() returns the ray parameter ("t"), from which the hit point can be computed, and optixGetPrimitiveIndex() returns the segment's primitive index.

To maximize performance, no other geometry attributes are passed or precomputed.

Instead, the program must compute whatever curve geometry it requires (surface normals, etc.) using the vertex data.

To make vertex data available to your OptiX shaders (for example your closest-hit program), the geometry acceleration structure build flag must include OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS. (See "Build flags" (page 26).) To fetch the vertex positions and radius values for the segment, pass the primitive index to the function appropriate for the curve type:

```
optixGetLinearCurveVertexData
optixGetQuadraticBSplineVertexData
optixGetCubicBSplineVertexData
optixGetCatmullRomVertexData
```

Sample code is provided to interpolate the curve points and radii, and to compute tangents, normals, and derivatives; see header file SDK/cuda/curve.h.

A single hit program can (and should) handle multiple curve primitive types by checking the value of optixGetPrimitiveType().

For example, see optixHair.cu in the optixHair code sample.

The optixGetCurveParameter function returns the parameter value relative to a single polynomial segment of the curve.

If needed, the hit program can map this to the parameter value relative to the entire multi-segment strand.

For instance, this can be used to interpolate between two colors specified at the root and tip of a hair.

This segment-to-strand mapping is the application's responsibility;

see the optixHair code sample for an example implementation.

8.4 Spheres and the hit program

Hit programs for spheres report a maximum of two intersections of a ray with a sphere, ordered along the ray.

The second intersection is represented by the single attribute of the sphere hit: the ray parameter of the second hit with the sphere, if a second hit exists, otherwise 0.

The function optixGetRayTmax() returns the ray parameter ("t"), from which the first hit point can be computed, together with the hit type.

The function optixGetPrimitiveIndex() returns the sphere's primitive index.

Similar to curves, no other geometry attributes are passed or precomputed.

Instead, the program must compute whatever sphere geometry it requires (surface normals, etc.) using the vertex data.

To make vertex data available to OptiX shaders (for example the closest-hit program), the build flag of the geometry acceleration structure must include OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS. (See "Build flags" (page 26).) By including this flag, the function optixGetSphereData can acquire the vertex positions and radius values for the sphere.

8.5 Interpolating curve endpoints

A B-spline curve typically does not interpolate (that is, does not touch) its control points. In particular it does not reach as far as its first and last control points:




Fig. 8.1 – The curve does not reach the first and last control points

If desired, the application can modify the control point sequence to interpolate these points, by adding an additional control point at each end:




Fig. 8.2 – *Adding points (in green) to extend the curve*

Following the Universal Scene Description documentation, ¹² let's call these "phantom" points, resulting in "pinned" curves.

A phantom point is constructed by reflecting through the endpoint the point that preceded it.

Given control points p_1 , p_2 ... p_n , the phantom points can be defined geometrically by:

$$p_0 = p_1 + (p_1 - p_2)$$
$$p_{n+1} = p_n + (p_n - p_{n-1})$$

It is also possible to interpolate endpoints by repeating them.

^{12.} https://graphics.pixar.com/usd/docs/api/class_usd_geom_basis_curves.html#UsdGeomBasisCurves_Segment

8.6 Back-face culling 8 Curves and spheres

For cubic B-spline curves, a control point that is repeated 3 times will be interpolated.

OptiX allows this, but the phantom point method is preferred,

as it is numerically more stable, and permits control of curvature.

Note: The additional points must be added to the build input by the application. These points are not added by NVIDIA OptiX 7 itself.

8.6 Back-face culling

The tube of a curve primitive is considered hollow,

and back faces are culled.

Thus if a ray starts inside a curve primitive (inside the tube),

it will not hit that primitive.

This is convenient for secondary rays and for transparency.

However, see "Limitations" (page 69) below.

Back faces of spheres are not culled.

A ray is allowed to start inside the sphere.

In this case, the reported (single) hit would be a back-face hit.

Functions optixIsBackFaceHit or optixIsFrontFaceHit can be used to determine which face has been hit.

For secondary rays, it can be useful to ignore back-face hits.

8.7 Limitations

There are some caveats to be aware of when using curves and curve hit programs.

Multiple hits

For a ray that intersects a single curve segment more than once, NVIDIA OptiX 7 does not guarantee that all intersections will be reported as hits.

In particular, the any-hit program will in general not be called more than once for a given segment.

To implement transparency, the alternative approach to using an any-hit program is to use closest-hit and relaunch a continuation ray from each hit.

Back-face culling

While the tube is mostly hollow, in the current implementation a ray can hit an internal endcap, meaning an endcap between two segments of a strand.

For typical curves that are much longer than they are wide, this is often not noticeable.

To avoid hitting internal endcaps, adjust secondary rays to launch from outside the tube.

Triple control points

As noted in "Interpolating curve endpoints" (page 68),

8 Curves and spheres 8.7 Limitations

duplicating control points is possible in NVIDIA OptiX 7, but the use of phantom points is preferred.

Duplicating the ending control points is numerically challenging (the derivative is zero) and the first segment is forced to be straight.

Convoluted cases

Curves for hair, fur, cloth fibers, etc., are typically thin with relatively gentle curvature.

It is possible to construct curve segments with tight curvature (relative to width), self-intersections, or rapidly varying radii that will exhibit artifacts, particularly if rendered up close.

In many cases, these can be remedied by splitting the segment into 3 smaller segments.

9 Ray generation launches

The API function described in this section is:

optixLaunch

A ray generation launch is the primary workhorse of the NVIDIA OptiX API. A launch invokes a 1D, 2D or 3D array of threads on the device and invokes ray generation programs for each thread. When the ray generation program invokes optixTrace, other programs are invoked to execute traversal, intersection, any-hit, closest-hit, miss and exception programs until the invocations are complete.

A pipeline requires device-side memory for each launch. This space is allocated and managed by the API. Because launch resources may be shared between pipelines, they are only guaranteed to be freed when the OptixDeviceContext is destroyed.

To initiate a pipeline launch, use the optixLaunch function. All launches are asynchronous, using CUDA streams. When it is necessary to implement synchronization, use the mechanisms provided by CUDA streams and events.

In addition to the pipeline object, the CUDA stream, and the launch state, it is necessary to provide information about the SBT layout, including: This includes:

- The base addresses for sections of the SBT that hold the records of different types
- The stride, in bytes, along with the maximum valid index for arrays of SBT records. The stride is used to calculate the SBT address for a record based on a given index. (See "Layout" (page 57).)

The value of the pipeline launch parameter is specified by the pipelineLaunchParamsVariableName field of the OptixPipelineCompileOptions struct. It is determined at launch with a CUdeviceptr parameter, named pipelineParams, that is provided to optixLaunch. Note the following restrictions:

- If the size specified by the pipelineParamsSize argument of optixLaunch is smaller than the size of the variable specified by the modules, the non-overlapping values of the parameter will be undefined.
- If the size is larger, an error will occur.

(See "Pipeline launch parameter" (page 45).)

The kernel creates a copy of pipelineParams before the launch, so the kernel is allowed to modify pipelineParams values during the launch. This means that subsequent launches can run with modified pipeline parameter values. Users cannot synchronize with this copy between the invocation of optixLaunch and the start of the kernel.

Note: Concurrent launches with different values for pipelineParams in the same pipeline triggers serialization of the launches. Concurrency requires a separate pipeline for each concurrent launch.

The dimensions of a launch must also be specified. If one-dimensional launches are required, use the width as the dimension of the launch and set both a height and a depth of 1. If two-dimensional launches are required, set the width and the height as the dimension of the launch and set a depth of 1.

Dimension	Width	Height	Depth
1D	width	1	1
2D	width	height	1
3D	width	height	depth

Specifying different dimensions for a launch

For example:

```
Listing 9.1
CUstream stream = nullptr;
cuStreamCreate(&stream);
CUdeviceptr raygenRecord, hitgroupRecords;
             Generate acceleration structures and SBT records
unsigned int width = ...;
unsigned int height = ...;
unsigned int depth = ...;
OptixShaderBindingTable sbt = {};
sbt.raygenRecord = raygenRecord;
sbt.hitgroupRecords = hitgroupRecords;
sbt.hitgroupRecordStrideInBytes = sizeof(HitGroupRecord);
sbt.hitgroupRecordCount = numHitGroupRecords;
MyPipelineParams pipelineParams = ...;
CUdeviceptr d_pipelineParams = 0;
             Allocate and copy the params to the device
optixLaunch(pipeline, stream,
   d_pipelineParams, sizeof(MyPipelineParams),
   &sbt, width, height, depth);
```

10 Limits

The previous chapters described properties that have an upper limit lower than the limit implied by the data type of the property. The values of these limits depend on the GPU generation for which the device context is created. These values can be queried at runtime using optixDeviceContextGetProperty.

Limit values may change from one OptiX SDK version to the next but not internally with updated NVIDIA drivers. Updated drivers use the limit values of the SDK version employed during application compilation as well as the GPU generation. The following table lists the NVIDIA OptiX 7 limit values for the currently supported GPU generations, including Turing:

			<i>7</i> .43		
Type of limit	Limit	nonchi	Conds	on. Ampere	
Acceleration structure	Maximum number of primitives per geometry acceleration structure including motion keys	2 ²⁹	2 ²⁹	2 ²⁹	
	Maximum number of referenced SBT records per geometry acceleration structure	2 ²⁴ †	2 ²⁴ †	2 ²⁴ †	
	Maximum number of instances per instance acceleration structure	2 ²⁸ *	2 ²⁸ *	2 ²⁸ *	
	Number of bits for SBT offset	28*	28*	28*	
	Number of bits for user ID	28*	28*	28*	
	Number of bits for visibility mask	8	8	8	
Pipeline	Maximum trace (recursion) depth	31	31	31	
	Maximum traversable graph depth	31	31	31	
Device functions	$Number\ of\ bits\ for\ optix {\tt Trace-visibility} {\tt Mask}$	8	8	8	
	Number of bits for optixTrace — SBTstride	4	4	4	
	Number of bits for optixTrace - SBToffset	4	4	4	
	$Number\ of\ bits\ for\ optix {\tt ReportIntersection-hitKind}$	7	7	7	
Hardware version	RT Cores version (read as x.x)	00	10	20	

NVIDIA OptiX 7 limits

Note: In the table, values marked with * were raised beginning in NVIDIA OptiX version 7.1. For code compiled with OptiX SDK version 7.0, the limit is 24. Values marked with † were incorrect in previous documentation versions. All versions of OptiX 7 support a maximum number of referenced SBT records per geometry acceleration structure of 2²⁴.

å,

For the instance properties SBT offset, user ID, and visibility mask, the higher bits of the 32-bit struct member must be set to zero. In case of the device functions, any bits higher than those specified in the table are ignored. Limits for device functions cannot be queried at runtime.

For more information on CUDA limits and supported features, see Appendix K: Compute Capabilities ¹³ in the Cuda Toolkit documentation. However, note that the upper limit for the size of an OptiX launch requires $width \times height \times depth \leq 2^{30}$.

^{13.} https://docs.nvidia.com/cuda/cuda-c-programming-guide/index.html#compute-capabilities

11 Device-side functions

The NVIDIA OptiX device runtime provides functions to set and get the ray tracing state and to trace new rays from within user programs. The following functions are available in all program types: 14

```
optixGetTransformTypeFromHandle
optixGetInstanceChildFromHandle
optixGetInstanceIdFromHandle
optixGetInstanceTransformFromHandle
optixGetInstanceInverseTransformFromHandle
optixGetStaticTransformFromHandle
optixGetMatrixMotionTransformFromHandle
{\tt optixGetSRTMotionTransformFromHandle}
optixGetGASMotionTimeBegin
optixGetGASMotionTimeEnd
optixGetGASMotionStepCount
optixGetPrimitiveType(hitKind)
optixIsFrontFaceHit(hitKind)
optixIsBackFaceHit(hitKind)
optixGetTriangleVertexData
optixGetLinearCurveVertexData
optixGetQuadraticBSplineVertexData
optixGetCubicBSplineVertexData
optixGetCatmullRomVertexData
optixGetSphereData
optixGetInstanceTraversableFromIAS
optixGetLaunchIndex
optixGetLaunchDimensions
optixGetSbtDataPointer
```

Other functions are available only in specific program types. The following table identifies the program types within which the OptiX device functions are valid.

^{14.} The abbreviation "GAS" is used for geometry acceleration structures in function names.

	ć	Seneration Ter	10,000;	### SO	sthit Viss	o E	, 70 to	Contin
Device function	*\$\tilde{\psi}	·\$	- ♦	\ \frac{5}{1}	\$	<i>•</i>	\ 	ည
<pre>optixTrace optixContinuationCall</pre>	✓			✓	✓			√
optixSetPayload_0 optixSetPayload_7 optixGetPayload_0 optixGetPayload_7 optixSetPayloadTypes optixGetWorldRayOrigin optixGetWorldRayDirection optixGetRayTmin optixGetRayTmax optixGetRayTime optixGetRayFlags optixGetRayVisibilityMask		✓	✓	✓	✓			
optixGetObjectRayOrigin optixGetObjectRayDirection		✓	✓					
<pre>optixGetTransformListSize optixGetTransformListHandle optixGetSbtGASIndex</pre>		✓	✓	√		✓		
optixGetWorldToObjectTransformMatrix optixGetObjectToWorldTransformMatrix optixTransformPointFromWorldToObjectSpace optixTransformVectorFromWorldToObjectSpace optixTransformVectorFromObjectToWorldSpace optixTransformVectorFromObjectToWorldSpace optixTransformNormalFromWorldToObjectSpace optixTransformNormalFromObjectToWorldSpace optixTransformNormalFromObjectToWorldSpace optixGetGASTraversableHandle optixGetPrimitiveIndex optixGetInstanceId optixGetInstanceId optixGetAttribute_0 optixGetAttribute_7		✓	✓	√				
optixGetHitKind optixGetPrimitiveType optixIsFrontFaceHit optixIsBackFaceHit optixIsTriangleHit (header function) optixIsTriangleFrontFaceHit (header function) optixIsTriangleBackFaceHit (header function) optixGetTriangleBarycentrics optixGetCurveParameter			√	√				
optixReportIntersection		√						
optixTerminateRay optixIgnoreIntersection			√					
optixDirectCall optixThrowException	✓	✓	✓	✓	✓		✓	✓
optixGetExceptionCode optixGetExceptionInvalidTraversable optixGetExceptionInvalidSbtOffset optixGetExceptionInvalidRay optixGetExceptionParameterMismatch optixGetExceptionLineInfo optixGetExceptionDetail_0 optixGetExceptionDetail_7						√		

11.1 Launch index 11 Device-side functions

Any function in the module that calls an NVIDIA OptiX device-side function is inlined into the caller (with the exceptions noted below). This process is repeated until only the outermost function contains these function calls.

For example, consider a closest-hit program that calls a function called computeValue, which calls computeDeeperValue, which itself calls optixGetTriangleBarycentrics. The inlining process inlines the body of computeDeeperValue into computeValue, which in turn, is inlined into the closest-hit program. Recursive functions that call device-side API functions will generate a compilation error.

The following functions do not trigger inlining:

```
optixGetTransformTypeFromHandle
optixGetInstanceChildFromHandle
optixGetInstanceIdFromHandle
optixGetInstanceTransformFromHandle
optixGetInstanceInverseTransformFromHandle
optixGetStaticTransformFromHandle
optixGetMatrixMotionTransformFromHandle
optixGetSRTMotionTransformFromHandle
optixGetLaunchDimensions
optixGetGASMotionTimeBegin
optixGetGASMotionTimeEnd
optixGetGASMotionStepCount
optixGetInstanceTraversableFromIAS
optixGetTriangleVertexData
optixGetLinearCurveVertexData
optixGetQuadraticBSplineVertexData
optixGetCubicBSplineVertexData
optixGetCatmullRomVertexData
optixGetSphereData
```

11.1 Launch index

The *launch index* identifies the current thread, within the launch dimensions specified by optixLaunch on the host. The launch index is available in all programs.

```
Listing 11.1
uint3 optixGetLaunchIndex();
```

Typically, the ray generation program is only launched once per launch index.

In contrast to the CUDA programming model, program execution of neighboring launch indices is not necessarily done within the same warp or block, so the application must not rely on the locality of launch indices.

11 Device-side functions 11.2 Trace

11.2 Trace

The optixTrace function initiates a ray tracing query starting with the given traversable and the provided ray origin and direction. If the given OptixTraversableHandle is null, only the miss program is invoked.

The tmin and tmax arguments set the extent associated with the current ray. Any reported hits with hitT outside of this range are ignored. The tmin value must be equal or greater than zero. The optixTrace functions' behavior is undefined for negative tmin values.

An arbitrary payload is associated with each ray that is initialized with this call; the payload is passed to all the intersection, any-hit, closest-hit and miss programs that are executed during this invocation of trace. The payload can be read and written by each program using the pairs of optixGetPayload and optixSetPayload functions (for example, optixGetPayload_0 and optixSetPayload_0). The payload is subsequently passed back to the caller of optixTrace and follows a copy-in/copy-out semantic. See "Payload" (page 93).

The rayTime argument sets the time allocated for motion-aware traversal and material evaluation. If motion is not enabled in the pipeline compile options, the ray time is ignored and removed by the compiler. To request the ray time, use the optixGetRayTime function. In a pipeline without motion, optixGetRayTime always returns 0.

The rayFlags argument can represent a combination of OptixRayFlags. The following flags are supported. Illegal combinations are noted.

OPTIX_RAY_FLAG_NONE

No change from the behavior configured for the individual acceleration structure.

OPTIX_RAY_FLAG_DISABLE_ANYHIT

Disables any-hit programs for the ray. Overrides potential instance flag OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT when intersecting instances. This flag is mutually exclusive with OPTIX_RAY_FLAG_ENFORCE_ANYHIT, OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT, OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT.

OPTIX_RAY_FLAG_ENFORCE_ANYHIT

Forces any-hit program execution for the ray. Overrides OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT and OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT.

OPTIX_RAY_FLAG_TERMINATE_ON_FIRST_HIT

Terminates the ray after the first hit and executes the closest-hit program of that hit.

OPTIX_RAY_FLAG_DISABLE_CLOSESTHIT

Disables closest-hit programs for the ray, but still executes the miss program in case of a miss.

OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES

Prevents intersection of triangle back faces (respects a possible face change due to instance flag OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING). This flag is mutually exclusive with OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES.

OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES

Prevents intersection of triangle front faces (respects a possible face change due to instance flag OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING). This flag is mutually exclusive with OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES.

11.2 Trace 11 Device-side functions

OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT

Prevents intersection of geometry which disables any-hit programs (due to setting geometry flag OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT or instance flag OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT). This flag is mutually exclusive with OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT, OPTIX_RAY_FLAG_ENFORCE_ANYHIT, OPTIX_RAY_FLAG_DISABLE_ANYHIT.

```
OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT
```

Prevents intersection of geometry which have an enabled any-hit program (due to not setting geometry flag OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT or setting instance flag OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT). This flag is mutually exclusive with OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT, OPTIX_RAY_FLAG_ENFORCE_ANYHIT, OPTIX_RAY_FLAG_DISABLE_ANYHIT.

Ray flags modify traversal behavior. For example, setting ray flag OPTIX_RAY_FLAG_TERMINATE_ON_FIRST_HIT causes the very first hit (that is not ignored in any-hit) to abort further traversal, defining it as the closest hit. This particular flag can be useful for shadow rays to allow for the early termination of a traversal without the need for a special any-hit program that calls optixTerminateRay.

The visibility mask controls intersection against configurable masks of instances. (See "Instance build inputs" (page 25).) Intersections are computed if there is at least one matching bit in both masks. The same limit applies in the number of available bits as for the instance visibility mask. See "Limits" (page 73).

The SBT offset and stride adjust the SBT indexing when selecting the SBT record for a ray intersection. Like the visibility mask, both parameters are limited. See "Limits" (page 73) and "Acceleration structures" (page 59).

The specified miss SBT index is used to identify the program that is invoked on a miss. (See "Layout" (page 57).) The argument must be a valid index for a SBT record for a miss program.

```
Listing 11.2

__device__ void optixTrace(OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int int ssSBTIndex,
    unsigned int& p0,
    ...
    unsigned int& p7);
```

11.3 Payload access

In intersection, any-hit, closest-hit, and miss programs, the payload is used to communicate values from the optixTrace that initiates the traversal, to and from other programs in the traversal, and back to the caller of optixTrace. There are up to thirty-two 32-bit payload values available. Getting and setting the thirty-two payload values use functions whose names end with a payload index. For example, payload 0 is set and accessed by these two functions:

```
Listing 11.3

__device__ void optixSetPayload_0(unsigned int p);
__device__ unsigned int optixGetPayload_0();
```

If the user configured payload types using the OptixModuleCompileOptions::numPayloadTypes and

OptixModuleCompileOptions::payloadTypes compile options, the optixSetPayloadTypes function associates a program with particular payload types. When used, this function must be called unconditionally at the top of the program. See "Payload" (page 93).

```
Listing 11.4

__device__ void optixSetPayloadTypes(unsigned int typeMask);
```

11.4 Reporting intersections and attribute access

To report an intersection with the current traversable, the intersection program can use the optixReportIntersection function. The hitKind of the given intersection is communicated to the associated any-hit and closest-hit program and allows the any-hit and closest-hit programs to customize how the attributes should be interpreted. The lowest 7 bits of the hitKind are interpreted; values [128, 255] are reserved for internal use.

Up to eight 32-bit primitive attribute values are available. Intersection programs write the attributes when reporting an intersection using optixReportIntersection. Then closest-hit and any-hit programs are able to read these attributes. For example:

```
Listing 11.5

__device__ bool optixReportIntersection(
    float hitT,
    unsigned int hitKind,
    unsigned int a0, ..., unsigned int a7);

__device__ unsigned int optixGetAttribute_0();
```

To reject a reported intersection in an any-hit program, an application calls optixIgnoreIntersection. The closest-hit program is called for the closest accepted intersection with the attributes reported for that intersection. An any-hit program may not be called for all possible hits along the ray. When an intersection is accepted (not discarded by optixIgnoreIntersection), the interval for intersection and traversal is updated. Further intersections outside the new interval are not performed.

11.5 Ray information 11 Device-side functions

Although the type of the attributes is exclusively integer data, it is expected that users will wrap one or more of these data types into more readable data structures using __int_as_float and __float_as_int, or other data types where necessary.

Triangle intersections return two attributes, the barycentric coordinates (u,v) of the hit, which may be read with the convenience function optixGetTriangleBarycentrics. Curve primitive intersections return one attribute, the curve parameter (u) within the polynomial curve segment, which may be read with the convenience function optixGetCurveParameter. Sphere intersections return one attribute, the ray parameter of the second intersection, or 0 it doesn't exist.

No more than eight values can be used for attributes. Unlike the ray payload that can contain pointers to local memory, attributes should not contain pointers to local memory. This memory may not be available in the closest-hit or intersection programs when the attributes are consumed. More sophisticated attributes are probably better handled in the closest-hit program. There are generally better memory bandwidth savings by deferring certain calculations to the closest-hit program or reloading values once in the closest-hit program.

11.5 Ray information

To query the properties of the currently active ray, use the following functions:

optixGetWorldRayOrigin / optixGetWorldRayDirection

Returns the ray's origin and direction passed into optixTrace. It may be more expensive to call these functions during traversal (that is, in intersection or any-hit) than their object space counterparts.

optixGetObjectRayOrigin / optixGetObjectRayDirection

Returns the object space ray direction or origin based based on the current transformation stack. These functions are only available in intersection and any-hit programs.

optixGetRayTmin

Returns the minimum extent associated with the current ray. This is the tmin value passed into optixTrace.

optixGetRayTmax

Returns the maximum extent associated with the current ray. Note the following:

- In intersection and closest-hit programs, this is the smallest reported hitT or if no intersection has been recorded yet the tmax that was passed into optixTrace.
- In any-hit programs, this returns the hitT value as passed into optixReportIntersection.
- In miss programs, the return value is the tmax that was passed into optixTrace.

optixGetRayTime

Returns the time value passed into optixTrace. Returns 0 if motion is disabled in the pipeline.

 ${\tt optixGetRayFlags}$

Returns the ray flags passed into optixTrace.

optixGetRayVisibilityMask

Returns the visibility mask passed into optixTrace.

Note: In ray-generation and exception programs, these functions are not supported because there is no currently active ray.

11.6 Undefined values

Advanced application writers seeking more fine-grained control over register usage may want to reduce total register use in heavy intersect and any-hit programs by writing an unknown value to payload slots not used during traversal. NVIDIA OptiX provides the following function to make this straightforward:

```
Listing 11.6

__device__ unsigned int optixUndefinedValue();
```

11.7 Intersection information

The primitive index of the current intersection point can be queried using optixGetPrimitiveIndex. The primitive index is local to its build input.

The SBT index of the current intersection point can be queried using optixGetSbtGASIndex. The SBT index is local to its build input. (See "Shader binding table" (page 57).)

The application can query the 8-bit hit kind by using optixGetHitKind. The hit kind is analyzed by calling optixGetPrimitiveType, which tells whether a custom primitive, built-in triangle, built-in sphere, or built-in curve primitive was hit, as well as whether the curve was linear, quadratic or cubic, or a Catmull-Rom spline. For built-in primitives, optixIsFrontFaceHit and optixIsBackFaceHit tell whether the ray hit a front or back face of the primitive. The front face of a built-in triangle primitive is defined by the counter-clockwise winding of the vertices. For custom primitives, the hit kind is the value reported by optixReportIntersection when it was called in the intersection.

The default counter-clockwise winding that defines the front face can be changed to clockwise winding by setting the OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING instance flag. The value of this flag in an instance overrides the flag's value that may have been set during the traversal of the acceleration structures of parent instances. (For a description of instance flags, see "Instance build inputs" (page 25).)

Note: It is generally more efficient to have one hit shader handle multiple primitive types (by switching on the value of optixGetPrimitiveType), rather than have several hit shaders that implement the same ray behavior but differ only in the type of geometry they expect.

For triangle hits, there are several notational shortcuts. The hit kind is either OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE or OPTIX_HIT_KIND_TRIANGLE_BACK_FACE, depending on whether the ray came from the front or back of the triangle.

The device functions optixIsTriangleHit, optixIsTriangleFrontFaceHit, and optixIsTriangleBackFaceHit may also be used.

The functions optixGetPrimitiveType, optixIsFrontFaceHit, and optixIsBackFaceHit each have two forms. Without an argument, they analyze the current ray intersection; this form

11.8 SBT record data 11 Device-side functions

can only be used in a closest-hit or any-hit program. Or, an explicit hit kind argument may be used; this form can be called from any type of program.

When traversing a scene with instances, that is, a scene containing instance acceleration structure objects, two properties of the most recently visited instance can be queried in intersection and any-hit programs. In the case of closest-hit programs, the properties reference the instance most recently visited when the hit was recorded with optixReportIntersection. Using optixGetInstanceId the value supplied to the OptixInstance::instanceId can be retrieved. Using optixGetInstanceIndex the zero-based index within the instance acceleration structure's instances associated with the instance is returned. If no instance has been visited between the geometry primitive and the target for optixTrace, optixGetInstanceId returns ~0u (the bitwise complement of a unsigned int zero) and optixGetInstanceIndex returns an unsigned int zero.

11.8 SBT record data

The data section of the current SBT record can be accessed using optixGetSbtDataPointer. It returns a pointer to the data, omitting the header of the SBT record (see "Shader binding table" (page 57)).

11.9 Vertex random access

Triangle vertices are baked into the triangle data structure of the geometry acceleration structure. When a triangle geometry acceleration structure is built with the OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS flag set, the application can query in object space the triangle vertex data of any triangle in the geometry acceleration structure. Because the geometry acceleration structure contains the triangle data, the application can safely release its own triangle data buffers on the device, thereby lowering overall memory usage.

The function optixGetTriangleVertexData returns the three triangle vertices at the rayTime passed in. Motion interpolation is performed if motion is enabled on the geometry acceleration structure and pipeline.

```
Listing 11.7

void optixGetTriangleVertexData(
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGasIdx,
    float rayTime,
    float3 data[3]);
```

The user can call functions optixGetGASTraversableHandle, optixGetPrimitiveIndex, optixGetSbtGASIndex and optixGetRayTime to obtain the geometry acceleration structure traversable handle, primitive index, geometry acceleration structure local SBT index and motion time associated with an intersection in the closest-hit and any-hit programs. The function optixGetTriangleVertexData also performs motion vertex interpolation for triangle position data.

For example:

```
Listing 11.8

OptixTraversableHandle gas = optixGetGASTraversableHandle();
unsigned int primIdx = optixGetPrimitiveIndex();
unsigned int sbtIdx = optixGetSbtGASIndex();
float time = optixGetRayTime();

float3 data[3];
optixGetTriangleVertexData(gas, primIdx, sbtIdx, time, data);
```

NVIDIA OptiX may remove degenerate (unintersectable) triangles from the acceleration structure during construction. Calling optixGetTriangleVertexData on a degenerate triangle returns NaN as triangle data, not the original triangle vertices.

The potential decompression step of triangle data may come with significant runtime overhead. Enabling random access may cause the geometry acceleration structure to use slightly more memory.

Care has to be taken if optixGetTriangleVertexData is used with a primitive index other than the value returned by optixGetPrimitiveIndex. optixGetTriangleVertexData expects a local primitive index corresponding to the build input / sbtGASIndex plus the primitive index offset as specified in the build input at the acceleration structure build.

Curve primitive vertices and radii are also stored in the geometry acceleration structure, and may be retrieved in an analogous way using the function optixGetLinearCurveVertexData, optixGetQuadraticBSplineVertexData, optixGetCubicBSplineVertexData, or optixGetCatmullRomVertexData, depending on the type of curve.

Sphere vertices and radii can be retrieved by using the function optixGetSphereData.

These functions' behavior is undefined when the traversable handle doesn't reference a valid geometry acceleration structure traversable, the geometry acceleration structure wasn't built with the OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS flag set, or the primitive index or geometry acceleration structure local SBT index are not within the valid range.

11.10 Geometry acceleration structure motion options

In addition to the motion vertex interpolation performed by optixGetTriangleVertexData, interpolation may also be desired for other user-managed vertex data, such as interpolating vertices in a custom motion intersection, or interpolating user-provided shading normals in the closest-hit shader. NVIDIA OptiX 7 provides the following functions to obtain the motion options for a geometry acceleration structure:

```
optixGetGASMotionTimeBegin
optixGetGASMotionTimeEnd
optixGetGASMotionStepCount
```

For example, if the number of motion keys for the user vertex data equals the number of motion keys in the geometry acceleration structure, the user can compute the left key index and intra-key interpolation time as follows:

11.11 Transform list 11 Device-side functions

```
Listing 11.9

OptixTraversableHandle gas = optixGetGASTraversableHandle();

float currentTime = optixGetRayTime();
 float timeBegin = optixGetGASMotionTimeBegin(gas);
 float timeEnd = optixGetGASMotionTimeEnd(gas);
 int numIntervals = optixGetGASMotionStepCount(gas) - 1;

float time =
    (globalt - timeBegin) * numIntervals / (timeEnd - timeBegin);
 time = max(0.f, min(numIntervals, time));
 float fltKey = floorf(time);

float intraKeyTime = time - fltKey;
 int leftKey = (int)fltKey;
```

11.11 Transform list

In a multi-level/IAS scene graph, one or more transformations are applied to each primitive. NVIDIA OptiX provides intrinsics to read a transform list at the current primitive. The transform list contains all transforms on the path through the scene graph from the root traversable (passed to optixTrace) to the current primitive. Function optixGetTransformListSize returns the number of entries in the transform list and optixGetTransformListHandle returns the traversable handle of the transform entries.

Function optixGetTransformTypeFromHandle returns the type of a traversable handle and can be of one of the following types:

```
OPTIX_TRANSFORM_TYPE_INSTANCE
```

An instance in an instance acceleration structure. Function optixGetInstanceIdFromHandle returns the instance user ID. Functions optixGetInstanceTransformFromHandle and optixGetInstanceInverseTransformFromHandle return the instance transform and its inverse. Function optixGetInstanceChildFromHandle returns the traversable handle referenced by the instance via OptixInstance::traversableHandle.

```
OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM
```

A transform corresponding to the OptixStaticTransform traversable. Function optixGetStaticTransformFromHandle returns a pointer to the traversable.

```
OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM
```

A transform corresponding to the OptixMatrixMotionTransform traversable. Function optixGetMatrixMotionTransformFromHandle returns a pointer to the traversable.

```
OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM
```

A transform corresponding to the OptixSRTMotionTransform traversable. Function optixGetSRTMotionTransformFromHandle returns a pointer to the traversable.

11 Device-side functions 11.11 Transform list

Only use these pointers to read data associated with these nodes. Writing data to any traversables that are active during a launch produces undefined results.

For example:

```
Listing 11.10 – Generic world to object transform computation
float4 mtrx[3];
for (unsigned int i = 0; i < optixGetTransformListSize(); ++i) {</pre>
   OptixTraversableHandle handle = optixGetTransformListHandle(i);
   float4 trf[3];
   switch(optixGetTransformTypeFromHandle(handle)) {
   case OPTIX_TRANSFORM_TYPE_INSTANCE: {
       const float4* trns =
           optixGetInstanceInverseTransformFromHandle(handle);
       trf[0] = trns[0];
       trf[1] = trns[1];
       trf[2] = trns[2];
   } break;
   case OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM : {
       const OptixStaticTransform* traversable =
           optixGetStaticTransformFromHandle(handle);
        . . .
                     Compute trf
   } break;
   case OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM : {
       const OptixMatrixMotionTransform* traversable =
           optixGetMatrixMotionTransformFromHandle(handle);
        . . .
                     Compute trf
   } break;
   case OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM : {
       const OptixSRTMotionTransform* traversable =
           optixGetSRTMotionTransformFromHandle(handle);
        . . .
                     Compute trf
   } break;
   default:
       continue;
   if (i == 0) {
       mtrx[0] = trf[0];
       mtrx[1] = trf[1];
       mtrx[2] = trf[2];
   } else {
        float4 m0 = mtrx[0], m1 = mtrx[1], m2 = mtrx[2];
        mtrx[0] = rowMatrixMul(m0, m1, m2, trf[0]);
                                                              Right multiply rows with
                                                              pre-multiplied matrix
        mtrx[1] = rowMatrixMul(m0, m1, m2, trf[1]);
        mtrx[2] = rowMatrixMul(m0, m1, m2, trf[2]);
   }
}
```

An application can implement a customized transformation evaluation function (for example, to get the world-to-object transformation matrix) using these intrinsics. Doing so can be beneficial as one can take advantage of the particular structure of the scene graph, for example, when a scene graph features a known maximum of transforms and only a subset of transform types are used. However, it is more important to properly specify the OptixPipelineCompileOptions::traversableGraphFlags and OptixPipelineCompileOptions::usesMotionBlur compile options based on which subset of scene graphs need to be supported. These compile options allow for optimizations to the intrinsics by compile-time removal of non-supported cases. For example, if only one level of instancing is necessary and no motion blur transforms need to be supported, set traversableGraphFlags to OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_LEVEL_INSTANCING. If set, device functions such as optixGetWorldToObjectTransformMatrix and optixGetObjectToWorldTransformMatrix are equally performant as a custom implementation.

Handles passed back from optixGetTransformListHandle can be stored or passed to other functions in which they can be decoded. Functions optixGetWorldToObjectTransformMatrix and optixGetObjectToWorldTransformMatrix are only available in the context of an intersection (IS, AH, CH programs). As such, it may also be required to use a customized transformation evaluation function, fetching the transformations from previously stored handles.

11.12 Instance random access

Transform lists are the preferred way to access data of an NVIDIA OptiX 7 instance associated with the current intersection in intersection, any-hit and closest-hit programs. However, a user may require random access to instance data of any other instance in the instance acceleration structure, not associated with the current intersection. When an instance acceleration structure is built with the OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS flag set, the application can query the instance traversable handle of any instance in the instance acceleration structure. Because the instance acceleration structure contains the instance data, the application can safely release its own instance data buffers on the device, thereby lowering overall memory usage.

The function optixGetInstanceTraversableFromIAS returns the traversable handle of an instance in the instance acceleration structure.

```
Listing 11.11
```

OptixTraversableHandle optixGetInstanceTraversableFromIAS(
 OptixTraversableHandle ias,
 unsigned int instIdx);

The user can call functions optixGetInstanceIdFromHandle, optixGetInstanceChildFromHandle, optixGetInstanceTransformFromHandle and optixGetInstanceInverseTransformFromHandle to obtain the user instance id, child traversable handle, object-to-world transform and world-to-object transform from the instance traversable handle.

For example:

11 Device-side functions 11.14 Exceptions

```
Listing 11.12

OptixTraversableHandle instanceHandle = 
   optixGetInstanceTraversableFromIAS( iasHandle, instanceIdx );
const float4* transform = 
   optixGetInstanceTransformFromHandle( instanceHandle );
```

This functions' behavior is undefined when the traversable handle doesn't reference a valid instance acceleration structure traversable, the instance acceleration structure wasn't built with the OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS flag set or the instance index is not within the valid range.

11.13 Terminating or ignoring traversal

In any-hit programs, use the following functions to control traversal:

```
optixTerminateRay
```

Causes the traversal execution associated with the current ray to immediately terminate. After termination, the closest-hit program associated with the ray is called.

```
optixIgnoreIntersection
```

Causes the current potential intersection to be discarded. This intersection will not become the new closest hit intersection associated with the ray.

These functions do not return to the caller and they immediately terminate the program. Any modifications to ray payload values must be set before calling these functions.

11.14 Exceptions

Exceptions allow NVIDIA OptiX to check for invariants and to report details about violations.

To enable exception checks, set the <code>OptixPipelineCompileOptions::exceptionFlags</code> field with a bitwise combination of <code>OptixExceptionFlags</code>. Depending on the scenario and combination of flags, enabling exceptions can lead to severe overhead, so some flags should be mainly used in internal and debug builds.

There are several different kinds of exceptions, which are enabled based on the set of flags specified:

```
OPTIX_EXCEPTION_FLAG_NONE
```

No exception set (default).

```
OPTIX_EXCEPTION_FLAG_STACK_OVERFLOW
```

Checks for overflow in the continuation stack specified with the continuationStackSize parameter to optixPipelineSetStackSize. When this exception is enabled, the overhead is usually negligible.

```
OPTIX_EXCEPTION_FLAG_TRACE_DEPTH
```

Before tracing a new ray, checks to see if the ray depth exceeds the value specified with OptixPipelineLinkOptions::maxTraceDepth. Some stack overflows are only detected if the exception for trace depth is enabled as well (or the value of

OptixPipelineLinkOptions::maxTraceDepth is correct). When this exception is enabled, the overhead is usually negligible.

11.14 Exceptions 11 Device-side functions

```
OPTIX_EXCEPTION_FLAG_USER
```

Enables the use of optixThrowException().

```
OPTIX_EXCEPTION_FLAG_DEBUG
```

Enables a number of run time checks including overflows for the traversable list, the validation of the set of traversables encountered at runtime, the validation of traced rays for nan or inf values, the validation of parameter counts for callable programs, and the validation of the sbt index when calling callable programs. When enabled, the overhead of this exception ranges from negligible to severe, depending on the type of GPU and the set of RTX features that are active.

If an exception occurs, the exception program is invoked. The exception program can be specified with an SBT record set in OptixShaderBindingTable::exceptionRecord. If exception flags are specified but no exception program is provided, a default exception program is provided by NVIDIA OptiX 7. This built-in exception program prints the first five exceptions that occurred to stdout to limit the amount of exception printing. Control does not return to the location that triggered the exception, and execution of the launch index ends.

In exception programs, the kind of exception that occurred can be queried with optixGetExceptionCode.

A number of exception codes are defined for the built-in exceptions.

Some exceptions provide additional information, accessed by API functions.

```
OPTIX_EXCEPTION_CODE_STACK_OVERFLOW
```

Stack overflow of the continuation stack. No information functions.

```
OPTIX_EXCEPTION_CODE_TRACE_DEPTH_EXCEEDED
```

The trace depth was exceeded. No information functions.

```
OPTIX_EXCEPTION_CODE_TRAVERSAL_DEPTH_EXCEEDED
```

The traversal depth was exceeded. Information functions:

```
optixGetTransformListSize()
optixGetTransformListHandle()
```

OPTIX_EXCEPTION_CODE_TRAVERSAL_INVALID_TRAVERSABLE

Traversal encountered an invalid traversable type. Information functions:

```
optixGetTransformListSize()
optixGetTransformListHandle()
optixGetExceptionInvalidTraversable()
```

OPTIX_EXCEPTION_CODE_TRAVERSAL_INVALID_MISS_SBT

The miss SBT record index is out of bounds. Information function:

```
optixGetExceptionInvalidSbtOffset()
```

```
OPTIX_EXCEPTION_CODE_TRAVERSAL_INVALID_HIT_SBT
```

The traversal hit sbt record index was out of bounds. Information functions:

```
optixGetTransformListSize()
optixGetTransformListHandle()
optixGetExceptionInvalidSbtOffset()
optixGetSbtGASIndex()
```

11 Device-side functions 11.14 Exceptions

```
OPTIX_EXCEPTION_CODE_INVALID_RAY
```

The shader encountered a call to optixTrace with at least one of the float arguments being inf or nan, or the tmin argument is negative. Information function:

```
optixGetExceptionInvalidRay()
```

```
OPTIX_EXCEPTION_CODE_CALLABLE_PARAMETER_MISMATCH
```

The shader encountered a call to either optixDirectCall or optixContinuationCall where there is a mismatch of the provided arguments and the parameters of the callable program which is called. Information function:

```
optixGetExceptionParameterMismatch()
```

```
OPTIX_EXCEPTION_CODE_CALLABLE_INVALID_SBT
```

The callable program sbt record index was out of bounds. Information functions:

```
optixGetExceptionInvalidSbtOffset()
```

```
OPTIX_EXCEPTION_CODE_CALLABLE_NO_DC_SBT_RECORD
```

The callable program sbt record does not contain a direct callable program. Information functions:

```
optixGetExceptionInvalidSbtOffset()
```

```
OPTIX_EXCEPTION_CODE_CALLABLE_NO_CC_SBT_RECORD
```

The callable program sbt record does not contain a continuation callable program. Information functions:

```
optixGetExceptionInvalidSbtOffset()
```

```
OPTIX_EXCEPTION_CODE_UNSUPPORTED_SINGLE_LEVEL_GAS
```

The traversable handle passed to optixTrace references a geometry acceleration structure, but the associated pipeline doesn't support single level geometry acceleration structure traversal (See OptixPipelineCompileOptions::traversableGraphFlags). Information functions:

```
optixGetTransformListSize()
optixGetTransformListHandle()
optixGetExceptionInvalidTraversable()
```

The following exception codes can be triggered by optixGetTriangleVertexData and optixGetInstanceTraversableFromIAS when exceptions are enabled.

```
OPTIX_EXCEPTION_CODE_INVALID_VALUE_ARGUMENT_0
```

Two conditions can trigger this exception code:

- The value for argument ias in a call to optixGetInstanceTraversableFromIAS is not a valid instance acceleration structure.
- The value for argument gas in a call to optixGetTriangleVertexData is not a valid geometry acceleration structure.

```
OPTIX_EXCEPTION_CODE_INVALID_VALUE_ARGUMENT_1
```

The index passed is out of range.

```
OPTIX_EXCEPTION_CODE_INVALID_VALUE_ARGUMENT_2
```

The sbtGASIndex passed to optixGetTriangleVertexData is out of range.

11.14 Exceptions 11 Device-side functions

OPTIX_EXCEPTION_CODE_UNSUPPORTED_DATA_ACCESS

Three conditions can trigger this exception code:

• Function optixGetTriangleVertexData was called on an acceleration structure that was built without OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS set.

- Function optixGetInstanceTraversableFromIAS was called on an acceleration structure built without OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS set.
- An acceleration structure built with motion was used in a pipeline without motion enabled.

User exceptions can be thrown with values between 0 and $2^{30} - 1$. Zero to eight 32-bit-value details can also be used to pass information to the exception program using a set of functions of one to nine arguments, as shown in Listing 11.13.

```
Listing 11.13 – Function signatures for user exceptions
optixThrowException(
    unsigned int code);
optixThrowException(
    unsigned int code,
    unsigned int detail0);
optixThrowException(
    unsigned int code,
   unsigned int detail0,
    unsigned int detail1);
             Exceptions for three to seven detail arguments
optixThrowException(
   unsigned int code,
    unsigned int detail0,
    unsigned int detail1,
   unsigned int detail2,
   unsigned int detail3,
   unsigned int detail4,
   unsigned int detail5,
    unsigned int detail6,
    unsigned int detail7);
```

The details can be queried in the exception program with eight functions, optixGetExceptionDetail_0() to optixGetExceptionDetail_7().

These functions' behavior is undefined when exception detail for another exception code is queried or if user exception detail that is queried was not set with optixThrowException.

11 Device-side functions 11.14 Exceptions

12 Payload

The ray payload is used to pass data between optixTrace and the programs invoked during ray traversal. Payload values are passed to and returned from optixTrace, and follow a copy-in/copy-out semantic. The payload is passed to all the intersection, any-hit, closest-hit and miss programs that are invoked during the execution of optixTrace. The payload can be read and written by each program using the thirty-two pairs of optixGetPayload and optixSetPayload functions (for example, optixGetPayload_0 and optixSetPayload_0). Setting a payload value using optixSetPayload causes the updated value to be visible in any subsequent optixGetPayload calls until the return to the caller of optixTrace. Payload values that are not explicitly set in a program remain unmodified. Payload values can be set anywhere in a program. Payloads are limited in size and are encoded in a maximum of thirty-two 32-bit integer values, which are held in registers where possible. To hold additional state, these values may also encode pointers to stack-based variables or application-managed global memory.

The number of available payload values can be configured globally for the entire pipeline using the numPayloadValues field of OptixPipelineCompileOptions. When configured globally per pipeline, all intersection, any-hit, closest-hit and miss programs agree on the number of values in the payload and have read and write access to all payload values. The lifetime of all payload values therefore extends over the entire optixTrace call. Configuring a larger payload will thus generally increase register consumption.

Alternatively, the user can specify more fine-grained payload type semantics per program. Each payload type is defined as some number of 32-bit integer values, with specific read/write semantics for each value. These semantics declare which programs may read and/or write to a particular payload value. OptiX can use these semantics to limit the lifetime of payload values and possibly improve register consumption. Each optixTrace call is associated with a single payload type. Similarly, each intersection, any-hit, closest-hit and miss program is associated with one or more payload types. Up to eight payload types can be specified per module using the OptixModuleCompileOptions as follows:

```
Listing 12.1

unsigned int semantics[2] = {
   OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_WRITE | OPTIX_PAYLOAD_SEMANTICS_CH_READ,
   OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ | OPTIX_PAYLOAD_SEMANTICS_CH_WRITE,
};

OptixPayloadType payloadType;
payloadType.numPayloadValues = 2;
payloadType.payloadSemantics = semantics;

OptixModuleCompileOptions moduleCompileOptions = {};
... Option assignment
```

```
moduleCompileOptions.numPayloadTypes = 1;
moduleCompileOptions.payloadTypes = &payloadType;

OptixPipelineCompileOptions pipelineCompileOptions = {};

Option assignment
pipelineCompileOptions.numPayloadValues = 0;
```

Note: Shader output payload values that are exclusively written in closest-hit and/or miss shaders and read by the caller generally have the shortest lifetime (OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ | OPTIX_PAYLOAD_SEMANTICS_CH_WRITE | OPTIX_PAYLOAD_SEMANTICS_MS_WRITE), thus providing OptiX with the most optimization potential.

Setting the OptixPipelineCompileOptions::numPayloadValues to zero signals that the modules in a pipeline use payload types. Modules compiled with different payload types may be freely combined in a pipeline. While the maximum number of payload types per module is eight, the pipeline itself can exceed this limit due to the ability to link modules with disjoint payload types. Within a module the payload types are referenced by ID, where the ID of a type equals its index in the payload type array payloadTypes specified in OptixModuleCompileOptions. Each program in a module specifies one or more supported payload types using the optixSetPayloadTypes function. When called, this function must be invoked unconditionally at the top of the program. Omitting the call to optixSetPayloadTypes or with OPTIX_PAYLOAD_TYPE_DEFAULT as argument indicates that the program supports all payload types specified in OptixModuleCompileOptions. If the OptixModuleCompileOptions specify multiple payload types each optixTrace call must supply a single payload type. All programs invoked during the execution of an optixTrace call must be associated with the payload type passed to that optixTrace. It is the responsibility of the user to setup the Shader Binding Table so the payload type of any programs invoked in a trace execution match the type associated with the optixTrace call. See "Shader binding table" (page 57). Type mismatches result in undefined behavior. When debug exceptions are enabled, OptiX will raise an OPTIX_EXCEPTION_CODE_PAYLOAD_TYPE_MISMATCH exception when program payload type mismatches are detected. The payload types argument passed to optixTrace and optixSetPayloadTypes must be a compile time constant. Note that a user may assign matching payload types to different IDs in different modules. Payload types are considered to match if they agree on the number of payload values and the semantics of each value, irrespective of their IDs within a module.

```
extern "C" __global__ void __anyhit__ah()
{
    optixSetPayloadTypes(
        OPTIX_PAYLOAD_TYPE_ID_1 |
        OPTIX_PAYLOAD_TYPE_ID_3);
}

extern "C" __global__ void __intersection__default()
{
```

```
optixSetPayloadTypes(
    OPTIX_PAYLOAD_TYPE_DEFAULT);

extern "C" __global__ void __raygen__rg()
{
    unsigned int p0, p1;

    optixTrace(
        OPTIX_PAYLOAD_TYPE_ID_0, ..., p0, p1);
}
All IS, AH, CH and MS programs associated with this call need to be associated with payload type 0.
}
```

Note that reading or writing a payload value inside a program without the appropriate read or write semantics for that value will result in a compilation failure. Programs associated with multiple types will be compiled once for each type. Programs in a program group are associated with a single specific type only. The user configures the target type with OptixProgramGroupOptions::payloadType. If there is only one unique payload type that is supported by all programs specified in the group description OptiX will deduce the unique type and OptixProgramGroupOptions::payloadType may be left zero.

13 Callables

Callable programs allow for additional programmability within the standard set of NVIDIA OptiX 7 programs. They are invoked using their index in the shader binding table. Invoking a function with its index enables a function call to change its target at runtime without having to recompile the program. This increase in flexibility can enable, for example, different shading effects in response to user input or programs that can be customized based on the scene setup.

Two types of callable programs exist in NVIDIA OptiX 7: direct callables and continuation callables. Unlike direct callables, continuation callables can call the function optixTrace. Direct callables are called immediately, but because of their additional capability, continuation callables need to be executed by the scheduler. This may result in additional overhead when running continuation callables.

Since continuation-callable programs can only be called from other continuation-callable programs, nested callables that need to call optixTrace must be marked as continuation callables. This has implications when creating a shader network from callables that trace rays. In such cases, refactoring the shader network to avoid calling optixTrace is recommended to improve overall performance.

The use of continuation callables can also lead to better overall performance, especially if the code block in question is part of divergent code execution. A simple example is a variety of material parameter inputs, such as different noise functions or a complex bitmap network. Using a continuation callable for each of these inputs allows the scheduler to more efficiently execute these complex snippets and to potentially resolve most of the divergent code execution.

Direct callables can be called from any program type except exception. Continuation callables can be called from ray-generation, closest-hit, and miss programs.

There are three parts to calling a callable program.

- 1. Implementation of the program you wish to call. That program needs to be annotated with the appropriate name prefix __direct_callable__ or __continuation_callable__.
- 2. The inclusion of a shader binding table record for the program group that contains the callable program.
- 3. The call in a program of the callable using the functions optixDirectCall and optixContinuationCall, shown in Listing 13.1 (page 98).

```
Listing 13.1 - Device functions with variadic templates

template<typename ReturnT, typename... ArgTypes>
ReturnT optixDirectCall(
   unsigned int sbtIndex, ArgTypes... args);

template<typename ReturnT, typename... ArgTypes>
ReturnT optixContinuationCall(
   unsigned int sbtIndex, ArgTypes... args);
```

The device-code compilation of these variadic templates requires C++11 or later.

The sbtIndex argument is an index of the array of callable shader binding table entries specified with the OptixShaderBindingTable::callablesRecordBase parameter to optixTrace. The program group for a callable can contain both a direct-callable and continuation-callable program, though these programs share a single record in the shader binding table.

To keep compilation time low for large functions (such as complex noise calculations) that are called from multiple sections of the code base, it is possible to use non-inlined functions. This mechanism is useful when a callable turns out to be too costly, requiring longer compilation times or degrading runtime performance. It also avoids the need to add callables to the shader binding table and to schedule the function during runtime execution (which might be preferable in some cases).

14 NVIDIA AI Denoiser

Image areas that have not yet fully converged during rendering will often exhibit pixel-scale noise due to the insufficient amount of information gathered by the renderer. This grainy appearance in an image may be caused by low iteration counts, especially in scenes with complex lighting environments and material calculations.

The NVIDIA AI Denoiser can estimate the converged image from a partially converged image. Instead of improving image quality through a larger number of path tracing iterations, the denoiser can produce images of acceptable quality with far fewer iterations by post-processing the image.

The denoiser is based on statistical data sets that guide the denoising process. These data, represented by a binary blob called a *training model*, are produced from a large number of rendered images in different stages of convergence. The images are used as input to an underlying *deep learning* system. (See the NVIDIA Developer article "Deep Learning" for more information about deep-learning systems.)

Because deep-learning training needs significant computational resources — even obtaining a sufficient number of partially converged images can be difficult — a general-purpose model is included with the OptiX software. This model is suitable for many renderers. However, the model may not yield optimal results when applied to images produced by renderers with very different noise characteristics compared to those used in the original training data.

Post-processing rendered images includes image filters, such as blurring or sharpening, or reconstruction filters, such as box, triangle, or Gaussian filters. Custom post-processing performed on a noisy image can lead to unsatisfactory denoising results. During post-processing, the original high-frequency, per-pixel noise may become smeared across multiple pixels, making it more difficult to detect and be handled by the model. Therefore, post-processing operations should be done *after* the denoising process, while reconstruction filters should be implemented by using filter importance-sampling.

In general, the pixel color space of an image that is used as input for the denoiser should match the color space of the images on which the denoiser was trained. However, slight variations, such as substituting sRGB with a simple gamma curve, should not have a noticeable impact. Images used for the training model included with the NVIDIA AI Denoiser distribution were output directly as HDR data.

^{15.} http://developer.nvidia.com/deep-learning

14.1 Functions and data structures for denoising

Calling function optixDenoiserCreate creates a denoiser object:

The OptixDenoiserModelKind is one of the following enum values:

```
OPTIX_DENOISER_MODEL_KIND_LDR
```

The input image data contains values of limited dynamic range with RGB values in the range 0.0 to 1.0.

```
OPTIX_DENOISER_MODEL_KIND_HDR
```

The input image data contains values of high dynamic range with RGB values in the range of 0.0 to approximately 10,000.0 or more.

```
OPTIX_DENOISER_MODEL_KIND_AOV
```

Separate passes can be defined by many rendering systems using *arbitrary output variables*, or AOVs. AOV images from a rendering system can contain diffuse, emission, glossy, specular or other types of data. High dynamic range AOV images can be passed as input layers to optixDenoiserInvoke in addition to the beauty, RGB, albedo and normal images. The AOV mode can be used to denoise multiple layers simultaneously and may reduce processing time.

After denoising, the denoised output layers can be composited to a noise-free beauty layer, typically by adding all RGB values from the denoised layers.

The first OptixDenoiserLayer in the list of layers passed to optixDenoiserInvoke is the noisy beauty image. Subsequent layers in this list are noisy AOVs. A noisy beauty image is required in all modes of OptixDenoiserModelKind and the denoised image for each given layer is written back in OptixDenoiserLayer::output.

```
OPTIX_DENOISER_MODEL_KIND_TEMPORAL
```

In this mode, a sequence of images is denoised to eliminate temporal noise. It requires the denoised beauty image from the previous frame in

OptixDenoiserLayer::previousOutput. The flow vector image is specified by OptixDenoiserGuideLayer::flow.OptixDenoiserParams::hdrIntensity must be set in this mode.

In the first frame of a sequence, previousOutput could be set to the noisy beauty image of the first frame instead of the denoised version and all flow vectors set to zero. previousOutput is read in optixDenoiserInvoke before writing a new output, so previousOutput could be set to output (the same buffer) for efficiency if useful in the application.

OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV

In this mode, the following two additional fields are defined:

- OptixDenoiserGuideLayer::previousOutputInternalGuideLayer
- OptixDenoiserGuideLayer::outputInternalGuideLayer

The image type for both fields is a <code>guide</code> <code>layer</code>, an <code>OptixImage2D</code> of type <code>OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER</code>. A <code>guide</code> <code>layer</code> is a densely packed format, where each pixel has size <code>OptixDenoiserSizes::internalGuideLayerPixelSizeInBytes</code>, and each row is width \times pixel size. The width and height of the guide layers are set to the same dimensions that are used for the other layer images. The <code>pixelStrideInBytes</code> field of the guide layer is set to <code>internalGuideLayerPixelSizeInBytes</code>. The <code>rowStrideInBytes</code> field is set to <code>width</code> \times <code>internalGuideLayerPixelSizeInBytes</code>.

The parameter OptixDenoiserParams::temporalModeUsePreviousLayers controls the use of previous layers in denoising calculations. For the first frame, temporalModeUsePreviousLayers must be set to zero if the image content of previousOutputInternalGuideLayer is invalid (has a value of zero).

For all frames after the first, temporalModeUsePreviousLayers is set to one. However, if the image content of previousOutputInternalGuideLayer is initialized with previously saved internal guide layer data (for example, denoising was restarted at a later frame), the value of temporalModeUsePreviousLayers can also be set to one for the first frame.

In case of a change of camera angle or other significant temporal change in which the accumulated image should no longer be re-used during denoising, temporalModeUsePreviousLayers can be set to zero to indicate the beginning of a new sequence. Beginning a new sequence in this way applies to all temporal modes (in which temporalModeUsePreviousLayers is set to one), including the temporal mode for upscaling by a factor of two. (See the following enum values.)

Each new sequence should contain the noisy beauty image as the value of previousOutput. The previousOutputInternalGuideLayer image content must be set to zero for the first frame.

Motion vectors must be set to zero if they are not available for the first frame.

After each frame, the previousOutputInternalGuideLayer and OptixDenoiserGuideLayer::outputInternalGuideLayer values can be exchanged so that no new memory must be allocated. This optimization is similar to exchanging previousOutput and output after each frame.

```
OPTIX_DENOISER_MODEL_KIND_UPSCALE2X
OPTIX_DENOISER_MODEL_KIND_TEMPORAL_UPSCALE2X
```

These modes upscale the input image by a factor of two in both dimensions. All output images must be allocated accordingly using twice the original size of the input width and height:

- OptixDenoiserLayer::previousOutput
- OptixDenoiserLayer::output
- OptixDenoiserGuideLayer::previousOutputInternalGuideLayer
- OptixDenoiserGuideLayer::outputInternalGuideLayer

When using OPTIX_DENOISER_MODEL_KIND_TEMPORAL_UPSCALE2X mode for the first frame, previousOutputInternalGuideLayer image content must be set to zero. The previousOutput field is ignored in this mode and just the memory needs to be allocated. Internally, the noisy beauty image will be upscaled by a factor of two and used as the

previous output (similar to the non-upcaling mode where the noisy beauty image should be passed as the previously denoised output).

The denoiser options determine the type of guide layers used:

```
Listing 14.2

typedef struct OptixDenoiserOptions {
   unsigned int guideAlbedo;
   unsigned int guideNormal;
} OptixDenoiserOptions;
```

A denoiser object can also be created using a user-defined model:

```
Listing 14.3

OptixResult optixDenoiserCreateWithUserModel(
    OptixDeviceContext context,
    const void* userData,
    size_t userDataSizeInBytes,
    OptixDenoiser* denoiser);
```

After denoising, optixDenoiserDestroy should be called to destroy the denoiser object along with associated host resources:

```
Listing 14.4

OptixResult optixDenoiserDestroy(
OptixDenoiser denoiser);
```

14.1.1 Structure and use of image buffers

An RGB image buffer that contain a noisy image is provided as input to the denoising process. The optional fourth (alpha) channel of the image can be configured so that it is ignored by the denoiser. Note that this buffer must contain values between 0 and 1 for each of the three color channels (for example, as the result of tone-mapping) and should be encoded in sRGB or gamma space with a gamma value of 2.2 when working with low dynamic range (LDR) input.

When working with high dynamic range (HDR) input instead, RGB values in the color buffer should be in a range from zero to 10,000, and on average not too close to zero, to match the built-in model. Images in HDR format can contain single, extremely bright, nonconverted pixels, called *fireflies*. Using a preprocess pass that corrects drastic under- or over-exposure along with clipping or filtering of fireflies on the HDR image can improve the denoising quality dramatically. Note, however, that no tone-mapping or gamma correction should be performed on HDR data.

An optional, noise-free normal buffer contains the surface normal vectors of the primary hit in camera space. The normal buffer is enabled by OptixDenoiserOptions::guideNormal and specified by OptixDenoiserGuideLayer::normal. This buffer contains data in format OPTIX_PIXEL_FORMAT_HALF3 or OPTIX_PIXEL_FORMAT_FLOAT3. These two formats can represent

the x, y and z components of a vector. The normal buffer must have the same type and dimensions as the input buffer. The vectors in the normal buffer are normalized.

The camera space is assumed to be right-handed such that the camera is looking down the negative z axis, and the up direction is along the y axis. The x axis points to the right.

Visualizing the normal vectors as colors for debugging purposes should produce images similar to Figure 14.1 and Figure 14.2. The scanlines of the normal buffer proceed from top to bottom in the images. The surface normal vector components have values in the range [-1.0, 1.0]. Figure 14.1 maps the component values to the range [0.0, 1.0]. Figure 14.2 clamps the component values to [0.0,1.0]. The value of a normal buffer pixel for which there was no primary hit is (0,0,0).




Fig. 14.1 – Surface normal vector components mapped to [0.0, 1.0]

Fig. 14.2 – Surface normal vector components clamped to [0.0, 1.0]

The normal buffer can improve denoising quality for scenes containing a high degree of geometric detail. This detail may be part of the geometric complexity of the surface itself, or may be the result of high-resolution images used in normal or bump mapping.

The optional, noise-free albedo image represents an approximation of the color of the surface of the object, independent of view direction and lighting conditions. In physical terms, the albedo is a single color value approximating the ratio of radiant exitance to the irradiance under uniform lighting. The albedo value can be approximated for simple materials by using the diffuse color of the first hit, or for layered materials, by using a weighted sum of the albedo values of the individual BRDFs. For some objects such as perfect mirrors or highly glossy materials, the quality of the denoising result might be improved by using the albedo value of a subsequent hit instead. The fourth channel of this buffer is ignored, but must have the same type and dimensions as the input buffer. Specifying albedo can dramatically improve denoising quality, especially for very noisy input images.

14.1.2 Temporal denoising modes

In temporal denoising modes, pixels in the two-dimensional flow image represents the motion from the previous to the current frame for that pixel. Pixels in the flow image can be in one of two formats:

- OPTIX_PIXEL_FORMAT_FLOAT2
- OPTIX_PIXEL_FORMAT_HALF2

Figure 14.3 shows the definition of the flow vector based on the hit points of the current and previous frames.




Fig. 14.3 – Definition of the flow vector based on the previous and current hit points

If the hit point of the surface at position (4,2) in the current frame has moved from position (1,4) in the previous frame, the flow vector at position (4,2) would be x=3, y=-2. This flow vector definition assumes that images define y=0 at the top of the image. If images define y=0 at the bottom, this flow vector would be x=3, y=2. The flow vector coordinates must be described with subpixel (fractional) precision.

The OptiX SDK provides the OptixDenoiser sample which could be used to verify properly specified flow vectors. When invoked with -z, the tool looks up the position in the previous frame of each pixel using the flow vector. The pixel value from the previous frame position is looked up in the current frame position and written. When denoising a sequence with the -z option, frame N with motion applied should look similar to frame N+1 in the noisy input sequence. There should be no major jumps when comparing these images, just shading differences as well as differences due to disocclusion and so forth.

14.1.3 Allocating denoiser memory

To allocate the required, temporary device memory to run the denoiser, call function optixDenoiserComputeMemoryResources:

```
Listing 14.5

OptixResult optixDenoiserComputeMemoryResources(
    const OptixDenoiser denoiser,
```

The memory requirements are returned in the fields of struct OptixDenoiserSizes:

The OptixDenoiserSizes values are used as input to function optixDenoiserSetup:

In tiling mode, the inputWidth and inputHeight values should include two times the overlap size in the tile window dimensions.

14.1.4 Using the denoiser

To execute denoising on a given image, call function optixDenoiserInvoke:

```
Listing 14.8
OptixResult optixDenoiserInvoke(
   OptixDenoiser
                                    denoiser,
   CUstream
                                    stream,
   const OptixDenoiserParams*
                                    params,
   CUdeviceptr
                                    denoiserState,
   size_t
                                    denoiserStateSizeInBytes,
   const OptixDenoiserGuideLayer* guideLayer,
   const OptixDenoiserLayer*
                                    layers,
   unsigned int
                                    numLayers,
   unsigned int
                                    inputOffsetX,
```

When guide layers are enabled in OptixDenoiserOptions, the corresponding image buffers are specified by the OptixDenoiserGuideLayer struct. In temporal modes a flow vector image is specified by the OptixDenoiserGuideLayer::flow field.

```
Listing 14.9

typedef struct OptixDenoiserGuideLayer {
    OptixImage2D albedo;
    OptixImage2D normal;
    OptixImage2D flow;
    OptixImage2D previousOutputInternalGuideLayer;
    OptixImage2D outputInternalGuideLayer;
} OptixDenoiserGuideLayer;
```

Beauty and AOV layers are specified by the OptixDenoiserLayer::input. The denoised output of the beauty image in the layer is written to output. In temporal modes the denoised beauty image from the previous frame for a layer is specified by OptixDenoiserLayer::previousOutput.

```
Listing 14.10

typedef struct OptixDenoiserLayer {
    OptixImage2D input
    OptixImage2D previousOutput
    OptixImage2D output
} OptixDenoiserLayer;
```

The denoiser layers are defined by sets of struct OptixImage2D:

```
Listing 14.11

typedef struct OptixImage2D {
   CUdeviceptr data
   unsigned int width
   unsigned int height
   unsigned int rowStrideInBytes
   unsigned int pixelStrideInBytes
   OptixPixelFormat format
} OptixImage2D;
```

Function optixDenoiserInvoke executes the denoiser on a set of input data and produces one output image. State memory must be available during the execution of the denoiser or until optixDenoiserSetup is called with a new state memory pointer. Scratch memory passed as a CUdeviceptr must be exclusively available to the denoiser during execution. It is only used

for the duration of optixDenoiserInvoke. Scratch and state memory sizes must have a size greater than or equal to the sizes returned by optixDenoiserComputeMemoryResources.

Input and output to the denoiser uses struct OptixImage2D to represent pixel data:

```
typedef struct OptixImage2D {
   CUdeviceptr data
   unsigned int width;
   unsigned int height;
   unsigned int rowStrideInBytes;
   unsigned int pixelStrideInBytes;
   OptixPixelFormat format;
} OptixImage2D;
```

Parameters inputOffsetX and inputOffsetY are pixel offsets in the inputLayers image. These offsets specify the beginning of the image without overlap. When denoising an entire image without tiling, there is no overlap and inputOffsetX and inputOffsetY must be zero. When denoising a tile which is adjacent to one of the four sides of the entire image the corresponding offsets must also be zero; there is no overlap at the side adjacent to the image border. Parameters inputWidth and inputHeight correspond to the values passed to optixDenoiserComputeMemoryResources.

The structure of pixel data is defined by the enum OptixPixelFormat:

Field name	Description
OPTIX_PIXEL_FORMAT_HALF2	Two halfs, XY
OPTIX_PIXEL_FORMAT_HALF3	Three halfs, RGB/XYZ
OPTIX_PIXEL_FORMAT_HALF4	Four halfs, RGBA/XYZW
OPTIX_PIXEL_FORMAT_FLOAT2	Two floats, XY
OPTIX_PIXEL_FORMAT_FLOAT3	Three floats, RGB/XYZ
OPTIX_PIXEL_FORMAT_FLOAT4	Four floats, RGBA/XYZW

Note that the OptixPixelFormat value of the inputLayers must match the format that was specified during optixDenoiserCreate. The outputLayer must have the same width, height and pixel format as the input RGB(A) layer. All input layers must have the same width and height.

Further control over denoising is provided by the OptixDenoiserParams struct:

```
Listing 14.13

typedef struct OptixDenoiserParams {
   unsigned int denoiseAlpha;
   CUdeviceptr hdrIntensity;
   float blendFactor;
   CUdeviceptr hdrAverageColor;
```

```
unsigned int temporalModeUsePreviousLayers;
} OptixDenoiserParams;
```

The denoiseAlpha field of OptixDenoiserParams can disable the denoising of the (optional) alpha channel of the noisy image. The blendFactor field specifies an interpolation weight between the noisy input image (1.0) and the denoised output image (0.0). Calculation of hdrIntensity is described in "Calculating the HDR intensity parameter" (page 108).

Parameter hdrIntensity is used when the OPTIX_DENOISER_MODEL_KIND_AOV model kind is set. This parameter is a pointer to three floats that are the average log color of the RGB channels of the input image. The default value (the null pointer) will produce results that are not optimal.

14.1.5 Calculating the HDR average color of the AOV model

The function optixDenoiserComputeAverageColor computes the average logarithmic value for each of the first three channels of the input image. When denoising tiles the intensity of the entire image should be computed — not per tile — for consistent results. This function needs scratch memory with a size of at least:

```
sizeof(int) * (3 + 3 * inputImage::width * inputImage::height)
```

When denoising entire images without tiling, the same scratch memory as passed to optixDenoiserInvoke could be used.

The inputImage parameter must contain three or four components of type half or float. The data type unsigned char is not supported.

```
Listing 14.14

OptixResult optixDenoiserComputeAverageColor(
   OptixDenoiser denoiser,
   CUstream stream,
   const OptixImage2D* inputImage,
   CUdeviceptr outputAverageColor,
   CUdeviceptr scratch,
   size_t scratchSizeInBytes);
```

14.1.6 Calculating the HDR intensity parameter

The value of hdrIntensity in OptixDenoiserParams can be calculated in one of two ways. A custom application-side, preprocessing pass on the image data could provide a result value of type float.

Intensity can also be calculated by calling function optixDenoiserComputeIntensity:

```
Listing 14.15

OptixResult optixDenoiserComputeIntensity(
    OptixDenoiser denoiser,
    CUstream stream,
    const OptixImage2D* inputImage,
    CUdeviceptr outputIntensity,
```

CUdeviceptr scratch, size_t scratchSizeInBytes);

Function optixDenoiserComputeIntensity calculates the logarithmic average intensity of parameter inputImage. The calculated value is returned in parameter outputIntensity as a pointer to a single value of type float.

Intensity calculation can be dependent on optixDenoiserInvoke. The params parameter of optixDenoiserInvoke is a struct of type OptixDenoiserParams. By default, the hdrIntensity field of OptixDenoiserParams is a null pointer. If hdrIntensity is not a null pointer, it points to an array of RGB values that are multiplied by the output values in outputIntensity. This is useful for denoising HDR images which are very dark or bright. When denoising with tiles, the intensity of the entire image should first be computed for consistent results across tiles. (Tiling is described in the "Using image tiles with the denoiser" (page 109).)

For each RGB pixel in the inputImage the intensity is calculated and summed if it is greater than 1e-8f as follows:

$$intensity = log(r \times 0.212586 + g \times 0.715170 + b \times 0.072200)$$

The function returns:

$$\frac{0.18}{exp\left(\frac{sum_of_intensities}{number_of_summed_pixels}\right)}$$

Execution of optixDenoiserComputeIntensity requires a scratch memory size in bytes of at least:

When denoising entire images (without tiling) the same scratch memory that is passed to optixDenoiserInvoke can be used.

Further information about this tone-mapping strategy can be found in "Photographic Tone Reproduction for Digital Images" by Erik Reinhard, et al.

14.2 Using image tiles with the denoiser

Denoising can be performed incrementally on subregions of an image to limit memory usage during the denoising process. An image is divided in to a set of *tiles* defined by their width and height, as well as a surrounding region of overlapping pixels to avoid discontinuities at tile boundaries.

For example, Figure 14.4 (page 110) describes a possible structure for tiles and their overlapping regions using OptixImage2D:

^{16.} http://www.cmap.polytechnique.fr/~peyre/cours/x2005signal/hdr_photographic.pdf




Fig. 14.4 – An example of a denoiser tiling layout

The tiling code must accommodate tile sizes that do not evenly divide the image buffers. Figure 14.5 shows a tile that with a consistent overlap size on all edges:




Fig. 14.5 – Output tile with overlap

Figure 14.6 (page 111) shows how a tiling procedure could vary the tile sizes based on their position in the input and output buffers.




Fig. 14.6 – Tiles in corners showing variable overlap

The OptiX SDK includes an example of the tiling process. See header file optix_denoiser_tiling.h in the SDK examples.

15 Demand-loaded sparse textures

This section describes the OptiX Demand Loading library, which is a standalone CUDA library that is distributed as open-source code in the OptiX SDK. (It is free for commercial use.) Although it is part of the OptiX SDK, the Demand Loading library has no OptiX dependencies, and it is technically not part of the OptiX API.

The OptiX Demand Loading library allows hardware-accelerated sparse textures to be loaded on demand, which greatly reduces memory requirements, bandwidth, and disk I/O compared to preloading textures. It works by maintaining a page table that tracks which texture tiles have been loaded into GPU memory. An OptiX closest-hit program fetches from a texture by calling library device code that checks the page table to see if the required tiles are present. If not, the library records a page request, which is processed by library host code after the kernel has terminated. Kernel launches are repeated until no tiles are missing, typically using adaptive sampling to avoid redundant work. Although it is currently focused on texturing, much of the library is generic and can be adapted to load arbitrary data on demand, such as per-vertex data like colors or normals.

Before describing the design and implementation of the library in more detail, we first provide some motivation and background information.

15.1 Motivation

The size of film-quality texture assets has been a longstanding obstacle to rendering final-frame images for visual effects shots and animated films. It's not unusual for a hero character to have 50-100 GB of textures, and many sets and props are equally detailed (sometimes for no good reason, except that it would be more expensive to author at a more appropriate resolution).

Film models are usually painted at extremely high resolution in case of extreme closeup. A character's face is typically divided into several regions (for example, eye, nose, mouth), each of which is painted at 4K or 8K resolution. In addition, numerous layers are often used, including coarse and fine displacement and various material layers such as dirt, each of which is a separate collection of textures.

It's not practical to preload entire film-quality textures into GPU memory. Besides wasting GPU memory, it also requires time and bandwidth to read the textures from disk and transfer them to GPU memory. Nor is it possible to downscale the images, since the level of detail that is required depends on the distance of the textured object from the camera. Simply clamping the maximum resolution can lead to a loss of detail that is not acceptable in a film-quality renderer.

To make matters worse, it's not unusual for a production shot to have thousands of textured objects that are outside the camera view or completely occluded by other objects. It's generally not possible to know *a priori* which textures are required without actually rendering a scene.

All of these factors make it difficult to load textures into GPU memory before rendering. Our approach is a multi-pass one: the initial passes identify missing texture data, which is loaded from disk on demand and transferred to GPU memory between passes.

15.2 Background

Mipmapping is a well known technique for dealing with high resolution textures. The idea is to precompute downscaled images, as illustrated in Figure 15.1, that can be used when a lower level of detail is acceptable, such as when a textured object is far from the camera.




Fig. 15.1 – Mipmapped texture showing downscaled images

In a ray tracer, choosing which level of detail to use is usually accomplished using ray differentials to determine the gradients of the texture coordinates. The texture hardware on the GPU then uses those gradients to choose two miplevels, and then it performs a filtered lookup in each miplevel, and blends between the two.

Needless to say, that's a very expensive operation. But it's necessary to avoid temporal aliasing when the camera or the geometry is moving, which would otherwise create a pop when the choice of miplevels suddenly changes from one frame to the next. GPU acceleration for mipmapped texturing is often taken for granted, but it offers a huge performance gain compared to texturing on the CPU.

15.2.1 Sparse textures

Mipmapped textures are usually tiled, which divides each miplevel into a number of smaller sub-images. This allows a sparse memory layout to be used. Instead of loading an entire miplevel onto the GPU, only the individual tiles that are required are loaded, which saves memory and bandwidth.

For example, consider rendering a quad angled away from the camera, as shown in Figure 15.2 (page 115). The region that is closest to the camera must use tiles from a high resolution miplevel to ensure adequate detail. However, tiles from coarser miplevels can be used farther from the camera.




Fig. 15.2 – Texture-mapped quad angled away from the camera

For example, the tiles highlighted in Figure 15.3 illustrate which tiles might be required:




Fig. 15.3 – Mipmap tiles potentially required by Figure 15.3

Sparse textures are now supported in CUDA, starting with the CUDA 11.1 toolkit. Under the hood, CUDA sparse textures employ the virtual memory system in a clever way. The main complication is that texture filtering often requires samples from multiple tiles for a single texture fetch. In that case, the GPU texture units require those tiles to be contiguous in memory. But it would be wasteful to reserve enough space to allow that.

The trick is to use the virtual memory system to provide the illusion of contiguous tiles to the GPU texture units. That's accomplished by binding the texture sampler to virtual memory, and then mapping individual tiles as virtual pages.

Figure 15.4 illustrates how that works. On the left each tile is labeled with its virtual address. The page table shown in the middle maps that virtual address to a tile stored at an arbitrary offset in the physical backing storage, shown on the right.




Fig. 15.4 – Tiles label-led by virtual addresses stored by offsets in the backing storage

Of course, the level of indirection is not free, but it's hardware accelerated by the virtual memory system. The benefit is that the backing storage is quite compact, compared to the memory that would be required if physical memory was allocated for all the tiles in contiguous order.

15.3 Library overview

The OptiX Demand Loading library provides a framework for loading CUDA sparse textures on demand. It is based on a multi-pass approach to rendering:

A page table tracks which tiles are resident on the GPU. As an OptiX kernel discovers missing tiles, it records page requests. After a batch of requests has been accumulated, the kernel exits to allow the page requests to be processed on the CPU. For each request, a tile is loaded from disk, decompressed, and copied to GPU memory. Once the required tiles have been loaded into GPU memory, the page table is updated and the OptiX kernel is relaunched Any pixels with missing texture tiles are resampled. Each pass might encounter other missing tiles, for example due to dependent texture reads or newly followed ray paths, so the process is repeated until there are no more misses.

15.4 Texture fetch

The OptiX Demand Loading library provides the following CUDA function (implemented entirely as header code), which used to fetch from a demand-loaded sparse texture with four floating-point channels. (Additional overload functions are available for other formats. Only 2D textures are currently supported.)

Listing 15.1 float4 tex2DGrad(const DemandTextureContext& context, unsigned int textureId, float x, float y, float2 ddx, float2 ddy, bool* isResident);

The arguments are as follows:

context

Contains the page table and other data.

textureId

Used to determine the offset in the page table at which the texture tiles are tracked.

х, у

The texture coordinates (normalized from zero to one).

ddx, ddy

The gradients of the texture coordinates, which are used to determine the level of detail required (that is, which miplevel). The gradients are usually calculated from ray differentials in an OptiX closest-hit shader.

isResident

An output parameter, which is set to true if the required tiles are resident in GPU memory.

The following steps are performed, as illustrated by Figure 15.5.




Fig. 15.5 – Texture fetch steps

1. First the required miplevels are calculated, which is based on the gradients. As usual, two miplevels are typically selected, and the final result is a weighted average.

- 2. The texture footprint is then calculated, using the texture coordinates to determine the offsets of the texture samples within the required miplevel. Linear filtering employs multiple samples, so up to four tiles might be required per miplevel.
- 3. For each required tile, its page table index is calculated by adding the tile index to the offset of this texture's page table entries.
- 4. If the required tiles are resident, the usual texture fetch instruction is executed, as shown on the right side of the illustration. That provides fully hardware accelerated sampling and filtering.
- 5. If a tile is missing a tile request is recorded (as shown on the left). Typically the ray is then terminated by throwing an OptiX user exception. But this step is user-programmable, in the closest hit program. So alternatively a default color could be substituted to allow shading to continue. Of course that's an approximation that might only be acceptable in a preview render or as an interim step during progressive refinement.

15.5 Page request processing

After a batch of tile requests has accumulated on the GPU, the OptiX kernel exits to allow them to be processed on the CPU.

As illustrated in Figure 15.6, the tile requests are processed by a parallel for loop that reads tiles from disk, decompresses them, and copies them into GPU memory. The OptiX Demand Loading library provides support for reading OpenEXR textures; incorporating other third-party libraries is straightforward.

When all the requests are processed, the OptiX kernel is relaunched for another rendering pass. Additional page requests might arise, for example due to dependent texture reads, so the entire process is repeated until there are no more requests.

This fits quite naturally into an adaptive sampling framework. It's not necessary to keep track of which rays failed due to missing tiles. Those rays make no contribution to the framebuffer, so the adaptive sampler will naturally resample the missing pixels in the next kernel launch.




Fig. 15.6 – An adaptive sampling framework

15.6 Host-side library

In addition to the texture fetch function described above, which is implemented entirely as CUDA header code, the OptiX Demand Loading library provides a C++ interface for host side operations.

The primary interface is the DemandTextureManager, which is obtained from the following function by providing a list of active devices and a few configuration options:

```
Listing 15.2

DemandTextureManager*
    createDemandTextureManager(
        const std::vector<unsigned int>& devices,
        const DemandTextureManagerConfig& config);
```

The following method creates a demand-loaded sparse texture. The texture descriptor specifies the filter mode and wrap mode, etc.

```
Listing 15.3

const DemandTexture& createTexture(
   std::shared_ptr<ImageReader> image,
   const TextureDescriptor& textureDesc);
```

The texture initially has no backing storage. The ImageReader argument has a readTile() method that serves as a callback during page request processing.

The returned DemandTexture object is mostly opaque. It provides a getId() method that provides the texture identifier, which is required by the texture fetch function described above. The texture id would typically be associated with an object in the OptiX shader binding table (SBT).

Before launching an OptiX kernel, the host program calls the following DemandTextureManager method, which updates device-side data structures including the page table and an array of sparse texture samplers. The method returns a context (by result parameter) that is required by the texture fetch function. The host program typically passes the context to the OptiX kernel as a launch parameter after copying it to device memory.

```
Listing 15.4

void launchPrepare(
   unsigned int deviceIndex,
   DemandTextureContext& demandTextureContext);
```

After an OptiX kernel has exited, the host program calls the following DemandTextureManager method, which processes any accumulated page requests. As described above, the tile requests are processed by a parallel for loop that reads tiles from disk, decompresses them, and copies them into GPU memory.

```
Listing 15.5
int processRequests();
```

When rendering is complete, the following function is used to destroy the DemandTextureManager, which frees all its resources, including device-side sparse texture memory.

```
Listing 15.6
void destroyDemandTextureManager(DemandTextureManager* manager);
```

15.7 Implementation

The full source for the OptiX Demand Loading library is provided in the OptiX SDK, along with a sample that illustrates its use. It is free for commercial use. The source code is accompanied by documentation (generated by Doxygen) that describes the implementation in detail. Questions are welcome on the NVIDIA OptiX forums.

We expect that some developers will fork the library to customize it, while others will rely on NVIDIA for continued feature development. The source code might move to a public repository in the future to facilitate such uses, with periodic library deliveries as part of the OptiX SDK.

