

License server - obtain licenses via VPN

Technical Support FAQ

Category: Technical Services->Licensing->Wibu Lizenzserver

Programs: Allplan 2020
Allplan 2019
Allplan 2018
Allplan 2017
Allplan 2016

Document ID: 20180109095437

Internet: <https://connect.allplan.com/en/faqid/20180109095437.html>

Question:

How can I use a license server license outside the office (external, e.g. with my own computer in my home office)?

Answer:

Computers that are not directly in the office must access the server with a VPN connection for the process. Licenses can be obtained directly from the license server via network or VPN.

The following must be observed with VPN:

Communication with the license server is via TCP/IP on port 22350.

You only have to make sure that the VPN connection is permanently active and does not go into sleep mode. Otherwise you should rather borrow a license via VPN and not obtain the license directly from the server.

VPN connection only with IPv4, IPv6 is not supported by Allplan.

The firewall must also be configured on both sides, client and server side, so that the connection is allowed, otherwise you should rather release the port in the firewall as an exception.

In most cases, a license server is automatically found in the local network. If no licenses are selected, the first suitable free license is automatically selected.

After installation, the license selection can be configured in the 'License Settings' dialog on the client.

Allmenu/Services -> Utilities -> License settings

License selection

Find license server automatically:

If this option is enabled, a license server in the LAN is automatically detected. In some cases (e.g. when connecting via VPN) it may happen that a server is not automatically detected, in this case you can enter the server manually (see additional server name).

Note: This option can only be changed as Windows Administrator.

Additional server name:

If 'Find license server automatically' is disabled or a license server could not be found automatically, you can

enter the name or IP address of the server manually. Enter only the server name or IP address, no UNC path. After entering the server name, click 'Update' to display the license server licenses. Multiple server names are separated by semicolons.

If the license is displayed and the connection is stable, you can directly pull the license from the server at the Allplan start, if the VPN connection is shaky, it is recommended to simply borrow a license. Please refer to the instructions at the following link.

<https://connect.allplan.com/en/faqid/20160523165423.html>

Hint:

We cannot recommend the use of VPN for a shared project repository, but obtaining a license via VPN works.

Allplan GmbH and affiliated sales organizations not assume any responsibility or liability for the reliability and usefulness of the articles offered and any information provided. You assume sole responsibility for use of the articles offered and the information provided. Terms and conditions of license of Allplan GmbH and / or the general terms and conditions of the sales organizations rendering the service apply.

© 2020 Allplan GmbH. All rights reserved.