

Workgroup manager: Check out computers and work with user rights

Technical Support FAQ

Category: Technical Services->Workgroup manager

Programs: Allplan 2020
Allplan 2019
Allplan 2018
Allplan 2017
Allplan 2016
Allplan 2015
Allplan 2014

Document ID: 20160923105251

Internet: <https://connect.allplan.com/en/faqid/20160923105251.html>

Question:

How can you check out a laptop and continue working as a normal CAD user with your usual settings and permissions?

Answer:

Install the "Microsoft Loopback Adapter" driver

This driver is necessary so that network services are always available on the laptop.

You can find the exact description in Allplan Connect: <https://connect.allplan.com/en/faqid/000162ae.html>

Log on to the laptop as an Allplan administrator.

Step 1: Add the computer to the workgroup manager

The laptop must be included once in the workgroup as a possible location for data storage (data server). Proceed as follows:

Set up a data folder:

Create a folder on the laptop, e.g. 'Nemdaten', for which you set up a folder share (with full access).

Create a subfolder 'Allplan' in this folder. In the Allplan folder, create two subfolders 'usr' and 'prj'.

In our example there are thus: '...\Nemdaten\Allplan\prj' and '...\Nemdaten\Allplan\usr'.

To share a folder for Allplan file storage

1. Start Windows Explorer on the laptop that is to be used for file storage and change to the folder that is to be shared (in our example this is the folder 'Nemdaten').
2. Right click on the folder you want to share and then in the context menu click on **Share with -> Specific people**
3. For People, add the person **Everyone**, and click Share


Adding the computer:

Start Allmenu/Services application as Workgroup Administrator

In the Allmenu/Services application, click **Workgroupmanager - Administer projects and computers.**

Click on **Add any computer in Allplan Workgroup** icon and select the computer that you want to include in the workgroup environment.

Select the 'Allplan' subfolder below the share on this computer and confirm your entry with OK. This computer is now listed under Workgroup Server.



Note: If you have problems adding the computer in the Workgroup Manager, because no computers are displayed and the computers are not listed in the search function, please follow the instructions below.

<https://connect.allplan.com/en/faqid/20200317162849.html>

Step 2 Define project owner:

To be able to move projects as a user, the user must be the owner of these projects.

The ownership of a project can only be changed by an Allplan administrator (or the owner of the project).

Allplan -> File -> Project pilot - Administration ->

Select the desired project under the node Projects with the right mouse button and click on **Properties** in the context menu

The owner can be specified here.

Step 3: Move projects

Log in as the user who wants to check out on the computer.

Start Services application -> Workgroupmanager -> Administer projects and computers.

The easiest way is to move a project

Click on the main server and select the project you want to move.

Drag and drop the projects one by one onto the computer you want to check out.

Addition: You basically have several possibilities to take projects with you.

1. You move the project to the laptop.

Move the project: Move project with pressed mouse button or click Cut in the context menu of the project, then click Paste in the context menu of the target computer.

Later when the computer has been checked in again, move the project back to the server so that it is available for everyone and can be saved again.

2. You can also copy projects. Click on the project, press the CTRL key and drag it to the target computer while holding down the mouse button. Or: Click on Copy in the context menu of the project, then click on Paste in the context menu of the target computer.

Here you then have 2 options. Either you lock the original project on the server and thus protect it from changes. This means that nobody in the office can work with the project during this time, but it is stored as a backup on the server.

When you check the laptop back in, you unlock the project on the server, delete it and copy your copy back to the server if changes have been made to it.

Or you can leave both projects active, then you can work on the laptop in the copy and on the server in the original. In this case, however, you must perform a manual data synchronization when you are back in the office and copy the drawing files of the projects together using the ProjectPilot.

Step 4: Check out your laptop

Start Allmenu/Services application -> Workgroup manager -> Administer projects and computers.

Click on your computer and then on **Check Out** in the lower right-hand corner.

You can confirm the message that there are still user directories on the computer to be checked out.

Enter a comment that users in the office will see when you want to access a project that is located on the computer you are checking out and confirm with OK.

Specify which areas of the office standard should be copied to the laptop and confirm with OK.

When you check out for the first time, you must copy the complete office standard once so that the STD is completely on the computer. This is no longer necessary for all subsequent checkouts, since the STD rarely changes.

Conclusion:

You can now remove the laptop from the network and edit your projects on the road or work from home.

Note:

You can only check out computers you are logged in directly. You cannot check out another computer over the network.

Projects on this computer must neither be locked nor in use.

For installations with license server: A license must be borrowed from the license server for the computer to be checked out.

Description Nemetschek Softlock License Server:

<https://connect.allplan.com/en/faqid/20120321113607.html>

Description WiBu license server:

<https://connect.allplan.com/en/faqid/20160523165423.html>

the articles offered and any information provided. You assume sole responsibility for use of the articles offered and the information provided. Terms and conditions of license of Allplan GmbH and / or the general terms and conditions of the sales organizations rendering the service apply.

© 2020 Allplan GmbH. All rights reserved.