17. Packed Decimal Instructions

Please note that these are often wrongly considered to be the most difficult of all Assembler instructions, even by advanced programmers. The misconception most likely comes down to the fact that the material was inadequately taught! There is a lot of detail, so pay attention!

Also, note that there is a space between each byte in depictions of filled bytes in the examples below. Of course, this space does not really exist but makes it easier to understand when learning.

Declaring Packed Decimal Fields and Variables in Storage

label DS PL3 AN UNITIALIZED 3-BYTE PACKED DECIMAL FIELD

label DC PL5'0' AN INITIALIZED 5-BYTE PACKED DECIMAL FIELD

In this class, please declare ALL packed decimal fields with DC and initialize it to 0 if nothing else!

To Convert from Zoned to Packed: Pack

Format: label PACK $D_1(L_1, B_1), D_2(L_2, B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- Packs the L_2 byte zoned decimal number at $D_2(B_2)$ and stores it as a L_1 byte packed decimal number at $D_1(B_1)$.
- The packing process:
 - 1. The zone and numeric digit of the **rightmost** byte of the zoned decimal number are reversed and placed in the rightmost byte of the packed decimal number.
 - 2. The remaining numeric digits are moved to the packed decimal number, proceeding from right to left. If the zoned number has more digits than the packed number can hold, the extras are ignored. If the zoned number has less digits than the packed number, the remaining packed digits are filled with zero
- The second operand does NOT have to be a valid zoned decimal number.

Suppose FLD1 is 4 packed bytes and FLD2 is 7 zoned bytes, with the initial values:

FLD1 00 00 00 00 FLD2 F9 F8 F7 F6 F5 F4 F3 Execution of:

```
PACK FLD1(4),FLD2(7) will set FLD1 to 98 76 54 3F

PACK FLD1(3),FLD2(7) will set FLD1 to 76 54 3F 00

PACK FLD1(4),FLD2(5) will set FLD1 to 00 98 76 5F
```

To swap the hexadecimal digits of any byte, pack the byte into itself:

PACK BYTE(1),BYTE(1) will simply reverse the zone and numeric digit

To Convert from Packed to Zoned Decimal: Unpack

Format: label UNPK $D_1(L_1, B_1), D_2(L_2, B_2)$

- Again, note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- Unpacks the L_2 byte packed decimal number at $D_2(B_2)$ and stores it as a L_1 byte zoned decimal number at $D_1(B_1)$
- The unpacking process:
 - 1. The zone and numeric digit of the rightmost byte of the packed decimal number are reversed and placed in the rightmost byte of the zoned decimal number
 - 2. The remaining numeric digits are padded with a zone digit of F and moved to the zoned decimal number. If the packed number has more digits than the zoned number can hold, the extras are ignored. If the packed number has less digits than the zoned number, the remaining digits are filled with F0
- The second operand does NOT have to be a valid packed decimal number

Suppose FLD1 is 5 zoned bytes and FLD2 is 3 packed bytes

FLD1 00 00 00 00 00 FLD2 12 34 5C

Execution of:

UNPK FLD1(5),FLD2(3) will set FLD1 to F1 F2 F3 F4 C5

UNPK FLD1(1),FLD2(3) will set FLD1 to C5 00 00 00 00

UNPK FLD1(5),FLD2(2) will set FLD1 to F0 F0 F1 F2 43

To Add One Packed Decimal Field to Another: Add Packed

Format: label AP $D_1(L_1,B_1),D_2(L_2,B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- The L_2 byte packed decimal number at $D_2(B_2)$ is added to the L_1 byte packed decimal number at $D_1(B_1)$. The sum is stored at $D_1(B_1)$.
- If L_1 bytes is not large enough to hold all of the non-zero digits of the result, overflow will occur.
- If either field is not a valid packed decimal number, a data exception (SOC 7) will occur.
- Sets the condition code as follows:

To Subtract One Packed Decimal Field from Another: Subtract Packed

Format: label SP $D_1(L_1,B_1),D_2(L_2,B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- The L_2 byte packed decimal number at $D_2(B_2)$ is subtracted from the L_1 byte packed decimal number at $D_1(B_1)$. The difference is stored at $D_1(B_1)$.
- If L_1 bytes is not large enough to hold all of the non-zero digits of the result, overflow will occur.
- If either field is not a valid packed decimal number, a data exception (SOC 7) will occur.
- Sets the condition code as follows:

<u>Code</u>	<u>Meaning</u>
0	Result is 0
1	Result is negative
2	Result is positive
3	Overflow

To Copy One Packed Decimal Field Into Another: Zero and Add Packed

Format: label ZAP $D_1(L_1, B_1), D_2(L_2, B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.

- The L_1 byte packed decimal field at $D_1(B_1)$ is zeroed out and the L_2 byte packed decimal number at $D_2(B_2)$ is added to the L_1 byte packed decimal number at $D_1(B_1)$. The sum is stored at $D_1(B_1)$.
- If the second operand is not a valid packed decimal number, a data exception (SOC 7) will occur.
- Sets the condition code as follows:

<u>Code</u>	<u>Meaning</u>
Θ	Result is 0
1	Result is negative
2	Result is positive
3	Overflow

- Use this instruction to copy packed numbers: ZAP FLD1(3),FLD2(2)
- Use this instruction to initialize a field: ZAP FLD1(4),=P'0'

To Multiply One Packed Decimal Field by Another: Multiply Packed

Format: label MP $D_1(L_1, B_1), D_2(L_2, B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- The L_2 byte packed decimal number at $D_2(B_2)$ and the L_1 byte packed decimal number at $D_1(B_1)$ are multiplied together. The product is stored at $D_1(B_1)$.
- A specification exception (SOC 6) will occur if $L_2 > 8$ or if $L_2 > = L_1$.
- A data exception (SOC 7) will occur if the first L_2 bytes of the first operand are not all zeroes or if either field is not a valid packed decimal number.

To Divide One Packed Decimal Field by Another: Divide Packed

Format: label DP $D_1(L_1, B_1), D_2(L_2, B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- The L_2 byte packed decimal number at $D_2(B_2)$ is divided into the L_1 byte packed decimal number at $D_1(B_1)$.
- Packed decimal divide is integer division. The quotient AND remainder are stored at $D_1(B_1)$.
- The length of the quotient is equal to $(L_1 L_2)$ bytes. The quotient is stored at $D_1(B_1)$ for $(L_1 L_2)$ bytes.
- The length of the remainder is L_2 bytes. The remainder is stored at $D_3(B_1)$

where $D_3 = D_1 + (L_1 - L_2)$.

- A specification exception (SOC 6) will occur if $L_2 > 8$ or if $L_2 >= L_1$.
- A data exception (SOC 7) will occur if either field is not a valid packed decimal number.
- A decimal divide exception (SOC B) will occur if the quotient is too large or if the second operand is zero.

Review of Packed Decimal Divide

- Using the divide packed (DP) instruction as it is results in integer division. In other words, it results in a quotient and remainder being produced.
- For example, when you divide a 10-byte field (the dividend) by a 3-byte field (the divisor), the quotient of the integer division is in the left 7 bytes of the original 10-byte dividend field and the remainder is in the rightmost 3 bytes of the original 3-byte divisor field.
- This means that the single field defined as the dividend, i.e., the first operand, will hold two valid packed decimal numbers after execution.
- The quotient of the division is on the left and the remainder is on the right in this field.
- The size in bytes of the remainder part of the result on the right or at the end of the first operand field is the SAME SIZE IN BYTES as the original divisor field, i.e., the second operand of the Divide Packed.
- The size in bytes of the quotient part of the result on the left or at the beginning of the first operand field - is the LENGTH OF THE ORIGINAL FIELD (the first operand length) minus LENGTH OF THE DIVISOR FIELD (the second operand length).

Integer Division vs. Real Number Division

- There IS a way to "fake" real number, or floating point, division, though.
- If the number in the the dividend field is shifted using the SRP instruction (described below) the number of decimal places to which the answer number is to be rounded **plus** 1 to the left before the division, the quotient will actually hold a real number result!
- Then, to round it, just the quotient part of the answer is then shifted one digit back to the right with rounding using the SRP instruction.
- Then the edit pattern can be set up to print the result putting the decimal point where it needs to be.

- See the extended example at the end of this document.

To Compare One Packed Field With Another: Compare Packed

Format: label CP $D_1(L_1, B_1), D_2(L_2, B_2)$

- Note that L_1 and L_2 refer to lengths in bytes and NOT index register numbers.
- A numeric comparison of the L_2 byte packed decimal number at $D_2(B_2)$ and the L_1 byte packed decimal number at $D_1(B_1)$ is performed and the condition code is set as follows:

To Add Decimal Zeros On the Left or Right Side of a Packed Decimal Field: Shift and Round Packed

Format: label SRP $D_1(L,B_1),D_2(B_2),i$

- Note that L refers to a length in bytes and NOT an index register number.
- The L byte field at $D_1(B_1)$ is shifted.
- The amount and direction of the shift is determined by $D_2(B_2)$.
- i is used as the *rounding factor*. It is usually 0 or 5, but can be between 0 and 9. On a RIGHT shift, i is added to the leftmost digit shifted off the right. If the sum is greater than 9, the result is rounded up by 1.
- A shift to the LEFT is equivalent to multiplying by a power of 10

Left Shift Format: SRP $D_1(L,B_1),n,i$

n is a decimal number from 1 to 31 which is the number of positions to shift

If non-zero digits are lost on the shift, decimal overflow occurs.

SRP NUM(6),3,0 LEFT SHIFT BY 3 WHICH IS EQUIVALENT TO MULTIPLYING THE NUMBER BY 10³

Before execution: NUM 00 00 01 20 75 9C

After execution: NUM 00 12 07 59 00 0C

- A shift to the right is equivalent to dividing by a power of 10

Right Shift Format: SRP $D_1(L,B_1)$, (64-n), i

n is a decimal number from 1 to 32 which is the number of positions to shift

SRP NUM(6),(64-2),0 RIGHT SHIFT BY 2 WHICH IS EQUIVALENT TO

DIVIDING BY 102 WITHOUT ROUNDING

Before execution: NUM 00 00 01 20 75 9C

After execution: NUM 00 00 00 01 20 7C

SRP NUM(6),(64-2),5 RIGHT SHIFT BY 2 WHICH IS EQUIVALENT TO

DIVIDING BY 102 WITH STANDARD ROUNDING

Before execution: NUM 00 00 01 20 75 9C

After execution: NUM 00 00 00 01 20 8C

- Both left and right shifts set the condition code as follows:

<u>Code</u> <u>Meaning</u>

- 0 Result is 0
- 1 Result is negative
- 2 Result is positive
- 3 Overflow

Formatting Packed Decimal Numbers for Printing

To Convert a Packed Decimal Number to EBCDIC for PRINTING: Edit

Format: label ED $D_1(L,B_1),D_2(B_2)$

- Note that L refers to a length in bytes and NOT an index register number.
- $D_1(B_1)$ is the address of an L byte field that initially contains a hexadecimal **pattern**. After execution of the instruction, this field will contain the formatted result.
- $D_2(B_2)$ is the **source field** and is the address of one or more contiguous packed decimal numbers to be formatted
- The pattern is made up of four types of characters
 - 1. X'20' digit selector

Used to print one packed decimal digit

2. X'21' significance starter

Used to print one packed decimal digit and turns the significance indicator on **after** this byte

- 3. X'22' **field separator**
 - Used in formatting multiple packed numbers in one ED instruction
- 4. Anything else is a **message character**. Common punctuation marks are found on page 35 of the yellow card.
- The **significance indicator** is used to indicate when leading zeroes should start to be printed. Initially is off.
- The first byte of the pattern is called a **fill character**. Leading zeros or message characters that are to be suppressed are replaced by this character.
- The pattern and packed decimal number are both processed from left to right. The pattern is processed one BYTE at a time, while the packed decimal number is processed one DIGIT at a time.
- Execution proceeds as follows:
 - If the character from the pattern is a digit selector, a packed digit is examined.
 - If the significance indicator is off and the packed digit is a zero, the character in the pattern is replaced by the fill character.
 - If the significance indicator is off and the packed digit is non-zero, the digit is converted to zoned format and the result replaces the character in the pattern. The significance indicator is turned on.
 - If the significance indicator is on, the packed digit is converted to zoned format and the result replaces the character in the pattern.
 - If the character from the pattern is a *significance starter*, the result is the same as above except that the significance indicator is always turned on AFTER the character in the pattern is replaced.
 - If the character from the pattern is a *field separator*, it is replaced by the fill character and the significance indicator is turned off.
 - If the character from the pattern is a message character:
 - If the significance indicator is off, the character is replaced by the fill character.
 - If the significance indicator is on, the message character is left unchanged.

- A data exception (SOC 7) will occur if the second operand is not a valid packed decimal number.
- Sets the condition code as follows:

<u>Code</u> <u>Meaning</u>

- O The inspected character in the last field is O
- 1 The inspected character in the last field < 0</pre>
- 2 The inspected character in the last field > 0
- Most ED instructions are preceded by a MVC that moves the pattern to $D_1(B_1)$.
- Examples:

ED Example 1 - Zero Suppression

Source Field: NUM 00 12 3C

Pattern Field: 40 20 20 20 20 20 <= a space as fill character

MVC NUMOUT(6),=X'402020202020'

ED NUMOUT(6), NUM

Output: NUMOUT 40 40 40 F1 F2 F3

When displayed: ___123 where ___ is 3 spaces

ED Example 2 - Zero Suppression

Source Field: NUM 00 00 0C

Pattern Field: 40 20 20 20 20 <= a space as fill character

MVC NUMOUT(6),=X'402020202020'

ED NUMOUT(6), NUM

Output: NUMOUT 40 40 40 40 40 40

When displayed: 6 spaces

ED Example 3 - Zero Suppression with Significance Indicator

Source Field: NUM 00 00 0C

Pattern Field: 40 20 20 20 21 20 <= a space as fill character

MVC NUMOUT(6),=X'402020202120'

ED NUMOUT(6), NUM

Output: NUMOUT 40 40 40 40 40 F0

When displayed: ____0 where ____ is 5 spaces.

ED Example 4 - With Commas

Source Field: NUM 00 32 90 7C

Pattern Field: 40 20 6B 20 20 6B 20 21 20

MVC NUMOUT(10),=X'40206B2020206B202120'

ED NUMOUT(10), NUM

Output: NUMOUT 40 40 40 40 F3 F2 6B F9 F0 F7

When displayed: ____32,907 where ____ is 4 spaces

ED Example 5 - With Decimal Point

Source Field: NUM 15 32 90 7C

Pattern Field: 40 20 20 6B 20 21 20 4B 20 20

MVC NUMOUT(10),=X'4020206B2021204B2020'

ED NUMOUT(10), NUM

Output: NUMOUT 40 F1 F5 6B F3 F2 F9 4B F0 F7

When displayed: _15,329.07 where _ is a space

ED Example 6 - Printing After a Number

Source Field: NUM 90 7B

Pattern Field: 40 20 21 20 60

MVC NUMOUT(5),=X'4020212060'

ED NUMOUT(5), NUM

Output: NUMOUT 40 F9 F0 F7 60

When displayed: _907- where _ is a space.

ED Example 7 - Printing After a Number

Source Field: NUM 90 7F

Pattern Field: 40 20 21 20 60

MVC NUMOUT(5),=X'4020212060'

ED NUMOUT(5), NUM

Output: NUMOUT 40 F9 F0 F7 40

When displayed: _907_ where _ are spaces.

ED Example 8 - Printing More Than One Number

Source Field: NUM 36 0F 46 5F

Pattern Field: 40 20 21 20 22 20 21 20

MVC NUMOUT(8),=X'4020212022202120'

ED NUMOUT(8), NUM

Output: NUMOUT 40 F3 F6 F0 40 F4 F6 F5

When displayed: _360_465 where _ are spaces.

To Convert a Packed Decimal Number to EBCDIC for PRINTING and Put a Sign (+ or -) or Dollar Sign (\$) to the Left of the First Non-Zero Digit: Edit and Mark

Format: label EDMK $D_1(L,B_1),D_2(B_2)$

- Note that L refers to a length in bytes and NOT an index register number.
- Performs exactly like the ED instruction but also sets a pointer to the first non-zero digit of an edited number.
- The address of the first non-zero digit is stored in the last 3 bytes of register 1 ONLY if a X'20' or X'21' was replaced by a source digit before a X'21' is reached

Example 1: Floating Dollar Sign

Source Field: NUM 46 78 23 9C

Pattern Field: 40 20 20 6B 20 21 20 4B 20 20

LA 1,NUMOUT+6 POINT R1 AT FIRST NON-BLANK CHARACTER BYTE

MVC NUMOUT(10),=X'4020206B2021204B2020' ← 10 bytes of edit pattern

EDMK NUMOUT(10), NUM

BCTR R1,0

MVI 0(R1),C'\$'

Output: NUMOUT 5B F4 F6 6B F7 F8 F2 4B F3 F9

When displayed: \$46,782.39 \leftarrow 10 columns (10 bytes)

Since register 1 may not be altered by the EDMK instruction, it is a good idea to point register 1 to where the first non-blank character will occur.

Example 2:

Source Field: NUM 00 00 12 0C

Pattern Field: 40 20 20 6B 20 21 20 4B 20 20

LA R1,NUMOUT+6 POINT R1 AT FIRST NON-BLANK CHARACTER BYTE

MVC NUMOUT(10),=X'4020206B2021204B2020'

EDMK NUMOUT(10), NUM

BCTR R1.0

MVI 0(R1),C'\$'

When displayed: ____\$1.20 where ____ is 5 spaces

Example 3:

Source Field: NUM 00 00 0C

Pattern Field: 40 20 21 20 4B 20 20

LA R1,NUMOUT+3 POINT R1 AT FIRST NON-BLANK CHARACTER BYTE

MVC NUMOUT(7),=X'402021204B2020'

EDMK NUMOUT(7), NUM

BCTR R1,0

MVI 0(R1),C'\$'

When displayed: __\$0.00 where __ is 2 spaces

Convert a Packed Decimal Number to Binary: Convert to Binary

Format: label CVB R,D(X,B)

- The packed decimal number at D(X,B) is converted to its binary presentation and stored in R.
- Note that the second operand is a D(X,B) address with index register.
- D(X,B) is the address of an 8-byte field on a doubleword boundary.
- A specification exception (SOC 6) will occur if D(X,B) is not on a doubleword boundary.
- A data exception (SOC 7) will occur if the number at D(X,B) is not a valid packed decimal number
- A fixed point divide exception (SOC 9) will occur if the number at D(X,B) is too large to be represented in 32 bits.
- This is the replacement for XDECI.
- Examples:

Example 1:

DWORD is a double word whose contents are 00 00 00 00 00 00 01 0F

CVB R4,DWORD will place 0000000A into R4

Example 2:

Before CVB: XDECI R5,BUFFER getting a 6 digit stock number

With CVB: PACK TEMP(8), BUFFER(6)

CVB R5, TEMP

•

TEMP DS D TO INSURE TEMP IS ON A DOUBLEWORD BOUNDARY

Convert a Binary Number to Packed Decimal: Convert to Decimal

Format: label CVD R,D(X,B)

- The binary number in R is converted to an 8 byte packed decimal number and stored starting at D(X,B).
- Note that the second operand is a D(X,B) address with index register.
- D(X,B) must be on a doubleword boundary.
- A specification exception (SOC 6) will occur if D(X,B) is not on a doubleword boundary.
- This is the replacement for XDECO.
- Examples:

Example 1:

R7 contains FFFFFFF

CVD R7,DWORD where DWORD DS D

will place 00 00 00 00 00 00 1D into DWORD

Example 2:

Before CVD: XDECO R5, NUMOUT where NUMOUT DS CL12

With CVD: CVD R5,TEMP

MVC NUMOUT(8),=X'4020202020202120'

ED NUMOUT(8), TEMP+4

TEMP DS D TO INSURE TEMP IS ON A DOUBLEWORD BOUNDARY NUMOUT DS CL8

TEMP+4 is used so that the first 8 digits are skipped because they will all be zeroes.

Example Packed Multiplication

- The following is an example of calculating interest:

	PACKED	ACTUAL VALUES
Account Balance: Interest Rate:	03 12 34 44 8F x 00 27 5F 08 58 94 73 20 0F	0312344.48 <u>x .0275</u> \$8,589.47

٨

If this packed decimal result is shifted and rounded four digits to the right, it yields the correct answer and can then be EDMK'd with the correct editing and two decimal places.

- Remember that the account balance from the input record must be packed into a 5-byte packed field (if it is zoned decimal or EBCDIC).
- It can then be EDMK'd directly into the print line from there.
- Then the 5-byte packed account balance can be ZAP'd into an 8-byte packed decimal field to prepare it for multiplication.
- After the multiplication, the 8-byte field can be SRP'd four digits to the right with rounding and the answer will be in the rightmost five bytes of the 8-bytes packed decimal field, rounded to two decimal places!

Extended Example Packed Division

- Numbers stored as packed decimal numbers are always stored as integers and have NO decimal point either stored or implied.
- The programmer has responsibility to keep track of the decimal places so that the right results can be obtained when doing math with packed decimal numbers.
- This is usually most important when packed decimal numbers or the results of arithmetic need to be displayed or printed.
- When an integer is divided by another, integer division occurs and the result is NOT like what results when two numbers are divided with a calculator.
- An integer quotient and an integer remainder are the results.

- The same thing happens when you simply divide one packed decimal number by another.

For example:

```
ZAP FIELD3(4),FIELD1(3) GET THE DIVIDEND INTO FIELD3 DP FIELD3(4),FIELD2(1) DIVIDE 45 BY
```

- * NOTE: AFTER THIS DIVIDE, THE QUOTIENT WILL BE IN THE FIRST 3 BYTES OF
- * FIELD3 AND THE REMAINDER ALWAYS THE SAME SIZE AS THE DIVISOR WILL BE
- * IN THE LAST BYTE OF FIELD3. HERE IS WHAT THE 4 BYTES OF FIELD3 LOOK
- * LIKE AFTER THE DIVISION: 00 01 0F 5F NOTE THAT THERE ARE 2 PACKED
- * DECIMAL NUMBERS STORED IN FIELD3. THE FIRST THREE ARE THE QUOTIENT OF 10
- * AND THE LAST BYTE IS THE REMAINDER OF 5.

and in storage:

FIELD1	DC	PL3'45'	STORAGE:	00 04 5F
FIELD2	DC	PL1'4'	STORAGE:	4F
FIELD3	DC	PL4'0'	STORAGE:	00 00 00 0F

- FIELD 3 is necessary to hold the result of the division. (Most commonly, just add the lengths of the field to be divided and the divisor.)

Turning Integer Division into Real (Floating Point) Division

- There **is** a way to turn this integer division into floating point division and get an answer similar to what would result using a calculator.

- Example:

	SRP	FIELD2,2,0	FIRS	T, EVEN UP THE NUMBER OF IMPLIED
*			DECI	MAL PLACES. BECAUSE FIELD1 HAS TWO
*			IMPL	IED, FIELD2 SHOULD HAVE THE SAME
*			BEFO	RE DOING ANYTHING ELSE
*				
	ZAP	FIELD3(11),FIELD1	(8)	COPY FIELD1 INTO FIELD3 TO PREPARE
*				FOR DIVISION
*				
	SRP	FIELD3(11),3,0	SHIF	T THE NUMBER TO BE DIVIDED 3 DIGITS TO
*			THE	LEFT TO ADD SOME "FAKE" DECIMAL
*			PLAC	ES.
*				
*			THE	RULE IS: SHIFT THE NUMBER OF DIGITS
*			TO R	OUND TO PLUS 1 MORE.
*				
	DP	FIELD3(11),FIELD2	(3)	NOW DIVIDE
	SRP	FIELD3(8),64-1,5		SHIFT JUST THE QUOTIENT PART ONE TO
*		,		THE RIGHT WITH ROUNDING. THE RESULT
*				IS NOW ROUNDED TO TWO DECIMAL PLACES!
*				JUST REMEMBER THAT THE ANSWER DESIRED

* IS IN THE FIRST 8 BYTES, THE QUOTIENT

* PART OF FIELD3. IGNORE THE REMAINDER

* FIELD.

and in storage:

FIELD1 DC PL8'345622.97' STORAGE: 00 00 00 03 45 62 29 7F STORAGE: 00 02 3F FIELD2 DC PL3'23' ONCE AGAIN, THE LENGTH OF THIS FIELD IS DC PL11'0' FIELD3 EQUAL TO THE LENGTHS OF THE TWO FIELDS INVOLVED IN THE DIVISION, FIELD1 AND * * FIELD2.

Pitfalls

- Before doing any of this, know the data and know it well!
- For example, if the largest dollar amount ever to be divided is \$99,999,999.99, a number which fits into a minimum number of 6 packed bytes.
- If the maximum number ever used to divide this by is \$99.99, a number which fits into a minimum number of 3 packed bytes.
- Do not let this trip you up, though!
- The programmer might be tempted to think that the result will always fit into 6 bytes, right? But this is not true!
- To be a better Assembler programmer, it is important and critical to think in extremes: What if the largest dollar number is divided by the smallest divisor dollar amount?
- In other words, divide \$99,999,999.99 by \$0.01?
- The result would be \$9,999,999,999.00 which would require 7 bytes minimum!
- AND! What if the result had to have more than just two implied decimal places?
- It could require even more than 7!
- So, what is the moral of this story? ALWAYS KNOW THE DATA AND ANTICIPATE!
- This is what is commonly referred to as "defensive programming."
- Always take the largest amount ever to be divided and divide it by the smallest amount it will ever be divided by.
- Then, and only then, consider how many bytes are necessary before doing the divide pack!

- Example:

ZAP	FIELD3(10),FIELD1(6)	PREPARE FOR DIVIDE
SRP	FIELD3(10),3,0	SHIFT 3 TO ROUND RESULT TO 2
DP	<pre>FIELD3(10),FIELD2(3)</pre>	DIVIDE
SRP	FIELD3(7),64-1,5	SHIFT 1 DIGIT RIGHT WITH ROUNDING

- * THE RESULT IS IN THE FIRST 7 BYTES OF FIELD3 AND ROUNDED TO AN IMPLIED 2
- * DECIMAL PLACES. IT IS READY TO BE EDMK'd INTO THE OUTPUT FIELD.

FIELD1	DC	PL6'783452.75'	STORAGE: 00 07 83 45 27 5F
FIELD2	DC	PL3'3.98'	STORAGE: 00 39 8F
FIELD3	DC	PL10'0'	FIELD INTO WHICH DIVISION WILL BE DONE