


vSFG-7 · AI ATC ON SRS

# SKYEYE ATC

## HORNET · VIPER

Command · Deckboss · Marshal · Paddles · JTAC · Texaco · GCI · Towers

Persian Gulf · Syria · Black Sea

**v1.42 · 12 NOV 2026**

Intellectual property of vSFG-7. For virtual simulation only.

# SKYEYE ATC

AI controllers on SRS · Command, Deckboss, Marshal, towers · Persian Gulf · Syria · Black Sea

## WHAT IT IS

read this first

- **An AI controller that talks to you over SRS.** It hears you with speech recognition, answers in a generated voice, and sees where you are through Tacview - so when you say "10 DME" it can check.
- **It listens for key words, not exact sentences.** Speak normally, but use the words on these cards - they are the triggers the code actually matches.

## THE ROLES

same calls in every theatre

| | |
|---|---|
| COMMAND - squadron net | **282.000 AM** |
| DECKBOSS - carrier deck | **128.600 AM** |
| MARSHAL - carrier stack | **306.300 AM · every theatre** |
| PADDLES - LSO, Black Sea + Syria | **128.300 AM · card 10** |
| HITMAN 1-1 / 2-1 - JTAC, Black Sea | **61.0 / 62.0 FM · cards 13 - 14** |
| RANGE AREAS + OVERLORD - on Command | **cards 15 - 16** |
| TEXACO 1-1 / 2-1 / 3-1 - Hornet tankers | **252.1 / .2 / .3 AM · card 17** |
| SHELL 1-1 / 2-1 - Viper boom tankers | **253.1 / 253.2 AM · card 18** |
| DARKSTAR / OVERLORD - GCI | **264.0 / 266.0 AM · cards 19 - 20** |
| COMBAT CALLS - shots, CSAR, damaged jet | **AWACS or Command · card 21** |
| TOWERS - one per airfield | **cards 23 - 29** |

## HOW TO BE HEARD

every call

- **Lead with the role name, then your callsign.** "Marshal, Raider 1, ..." - for a tower, the field name. Marshal ignores any call that does not start with its name; Deckboss ignores most of them.
- **Say your full callsign every time.** "Raider 1", not "1".
- **Pause half a second after you key the mic,** then speak. Calls shorter than about 0.2 s are thrown away.
- **Wait 2 - 3 seconds for the answer.** Recognition, the reply and the voice take that long. Do not re-key over it.
- **Radios AM (Hitman FM), encryption off.** Keep each call short - two short calls beat one long one.

ATIS is listen-only. Paddles answers your ball call; the rest is his calls.

# FREQUENCIES



Where SkyEye actually listens · per theatre · Hornet preset shown for each; Vipers use Command only.

## PERSIAN GULF — Hornet preset

| | |
|---|---|
| COMMAND 282.000 | COMM 1 CH 4 · Viper COMM 1 CH 1 |
| DECKBOSS 128.600 | COMM 1 CH 1 |
| MARSHAL 306.300 | COMM 1 CH 3 |

## SYRIA — Hornet preset

| | |
|---|---|
| COMMAND 282.000 | COMM 1 CH 4 · Viper COMM 1 CH 1 |
| DECKBOSS 128.600 | COMM 1 CH 1 |
| MARSHAL 306.300 | COMM 1 CH 3 |
| OVERLORD 266.000 - GCI | dial it |

## BLACK SEA — Hornet preset

| | |
|---|---|
| COMMAND 282.000 | COMM 1 CH 4 · Viper COMM 1 CH 1 |
| DECKBOSS 128.600 | COMM 1 CH 1 |
| MARSHAL 306.300 | COMM 1 CH 3 |
| DARKSTAR 264.000 - GCI | COMM 1 CH 5 |

## READING THE PRESET CARDS — read this

- **"AI" on a carrier preset means SkyEye.** COMM 1 CH 3 "CVN-72 AI MARSHALL" 306.300 is SkyEye Marshal in every theatre (operator ruling 2026-09-20).
- **COMM 1 CH 2 "CVN-72 MARSHAL" 306.200 is for a live human Marshal.** SkyEye never answers there.
- **Deckboss 128.600 is shared** with the DCS AI carrier controller - you may hear both.
- **SkyEye Paddles is 128.300 - dial it.** Black Sea and Syria. LSO 128.100 on the cards is for a human LSO.

Voices: towers British or Australian · Command, Marshal, Deckboss American · Hitman 1-1 Australian.

# DECKBOSS

Carrier deck · 128.600 AM · Hornet COMM 1 CH 1 · Cat assignment, conga line, launch.

## THE LAUNCH — in order

| | |
|---|---|
| **REQUEST TAXI** | "Deckboss, Raider 1, request taxi" - or green jet. |
| | Reply: cleared to cat N, or join the conga line. |
| **TENSION** | "Deckboss, Raider 1, ready cat 2" - or shoot. |
| | Reply: under tension, spin it up, shooter's discretion. |
| **T + 10 s** | Your cat is freed; the next jet hears cat N is clear. |
| **AIRBORNE** | "Raider 1, airborne" - no address needed. |
| | Reply: copy airborne, push Marshal and its frequency. |

## THE RULES

- **Deckboss does not call the shot.** Nobody says shoot on the radio - the shooter fires you. Run up when you hear "spin it up".
- **Four cats: 1 and 2 on the bow, 3 and 4 on the waist.** If all four are taken you join the conga line; it holds six. After that you hear "deck is full, hold clear".
- **Checking in twice does not take a second cat.** If you are already in the line you are told your number.

# DECKBOSS CALLS

Every call it answers · lead with "Deckboss," · The airborne call is the only one that works without it.

| YOU SAY | Deckboss replies |
|---|---|
| request taxi / ready for taxi / green jet | cat N or conga |
| ready cat N / tension cat N / shoot | under tension |
| airborne / clear traffic | push Marshal |
| remain in bolter | contact LSO |
| say BRC / request BRC | mother's BRC, magnetic |
| radio check / comm check / how copy | loud and clear |
| pushing Marshal / pushing command | short ack |

**SAMPLE** — Raider 1 and Raider 2 on the deck

| | |
|---|---|
| RAIDER 1 | Deckboss, Raider 1, request taxi. |
| DECKBOSS | Raider 1, Deckboss, cleared to cat two. |
| RAIDER 1 | Deckboss, Raider 1, ready cat two. |
| DECKBOSS | Raider 1, Deckboss, under tension cat two, |
| | spin it up, shooter's discretion. |
| DECKBOSS | Raider 2, Deckboss, cat two is clear. |
| RAIDER 1 | Raider 1, airborne. |
| DECKBOSS | Raider 1, Deckboss, copy airborne, |
| | push Marshal, three zero six point three. |

Bolter practice: Deckboss hands you to the LSO - Paddles 128.300 in the Black Sea and Syria.

# MARSHAL CASE I

Carrier stack · 306.300 · every theatre · Lead every call with "Marshal," - or it is ignored.

## THE RECOVERY

Case I and Case II use these calls

| | |
|---|---|
| **MARKING MOMS** | Marshal, Raider 1, marking moms, 30 DME, |
| | angels 12, state 6.5. |
| | Reply: radar contact, weather, case, BRC, |
| | altimeter, Marshal at angels N, |
| | report see me at ten. |
| **DME REPORTS** | Marshal, Raider 1, 20 DME - optional, acked. |
| **SEE YOU AT 10** | Reply: visual at ten, say state. |
| **STATE** | Marshal, Raider 1, state 5.2 - under 2.0 is priority. |
| **ESTABLISHED** | Marshal, Raider 1, established angels 3 |
| | Reply: signal Charlie - or your stack position, hold. |
| **COMMENCING** | Reply: call three mile initial. |
| **INITIAL** | At 3 nm. Reply: contact paddles, good luck. |

## THE STACK

- **"Marshal at angels N" is your stack altitude.** The lowest free altitude from angels 2 to angels 9. Marshal counts aircraft already in the stack and any contact within 50 nm at that altitude.
- **When someone commences, the stack steps down silently.** There is no radio call for it - keep flying your assigned angels.
- **After initial, switch to Paddles.** Black Sea and Syria: SkyEye Paddles on 128.300, card 10. Gulf: fly the ball and trap.

## ANY TIME

- **"Marshal, Raider 1, say BRC"** - mother's BRC, magnetic. "request BRC" and a bare "BRC" work too.
- **"Marshal, Raider 1, checking in"** - your range and bearing from mother, then marking moms please.

Word-for-word calls and replies: cards 7 - 9.

# MARSHAL CASE III

Night or low weather · same trigger words, new answers · Marshal picks the case itself from time and weather.

## WHICH CASE — decided by SkyEye

| | |
|---|---|
| Night (local 1800 - 0600) | CASE III |
| Ceiling under 1,500 ft or vis under 3 nm | CASE III |
| Ceiling under 3,000 ft or vis under 5 nm | CASE II |
| Otherwise | CASE I |

- **If the case changes while you are inbound,** you hear: "All marshal aircraft, recovery is now Case Three, acknowledge on next push."

## CASE III CALLS — what changes

| | |
|---|---|
| **MARKING MOMS** | Reply: marshal on the NNN, DD DME, angels N, expected approach time is MM, report established. |
| **ESTABLISHED** | Reply: approach time MM. There is no Charlie. |
| **COMMENCING** | At your MM. Reply: radar contact, descend to platform 5,000, final bearing NNN, confirm BRC NNN, report platform. |
| **PLATFORM** | Passing 5,000 ft. Reply: final bearing NNN. |
| **8 MILES** | Marshal: eight miles, dirty up. No reply. |
| **3 MILES** | Marshal: contact paddles, call the ball. Switch and make the ball call at three-quarters. No initial call. |
| **BOLTER** | Marshal: climb to 1,200, at 4 miles turn downwind, report abeam. Abeam: turn final, Paddles again at 3 miles. |

- **Marshal radial = final bearing + 180. Final bearing = BRC - 9.** All magnetic. The stack starts at angels 6; the DME is angels + 15 (angels 6 at 21 DME).
- **MM is minutes past the hour.** The first aircraft commences 10 minutes out; each one after is 10 minutes later. Miss your time and Marshal gives you a new one.

# MARSHAL CALLS 1

Word for word · check-in, marking moms, BRC, radar · Example: BRC 275, alt 29.92, angels 12, 30 nm on the 340.

## CHECKING IN — optional first call

| | |
|---|---|
| **YOU** | Marshal, Raider 1, checking in. |
| **MARSHAL** | Raider 1, Union Marshal, radar contact, angels 12, |
| | 30 miles from mother, bearing three four zero, |
| | say marking mom's and state. |
| **NO RADAR** | Raider 1, Union Marshal, go ahead with |
| | marking mom's and state. |

## MARKING MOMS — Case I and Case II

| | |
|---|---|
| **YOU** | Marshal, Raider 1, marking moms 340 for 30, |
| | angels 12, state 6.5. |
| **MARSHAL** | Raider 1, Union Marshal, radar contact, angels 12, |
| | range 30 miles, bearing three four zero from mother, |
| | mother's weather ceiling unrestricted, |
| | visibility ten plus, expect Case One recovery, |
| | BRC 275, altimeter two niner niner two, |
| | Marshal at angels two, report see me at ten. |
| **2+ IN STACK** | The reply ends: Stack has 2 aircraft. |
| **NO RADAR** | The radar contact part is left out. |

## BRC — any time

| | |
|---|---|
| **YOU** | Marshal, Raider 1, say BRC. |
| **MARSHAL** | Raider 1, Union Marshal, mother's BRC is 275. |
| **NO CARRIER** | Raider 1, Union Marshal, BRC unknown, mother off scope. |

## RADAR CHECK AND RADIO CHECK

| | |
|---|---|
| **YOU** | Marshal, Raider 1, radar check. |
| **MARSHAL** | Raider 1, Union Marshal, radar contact, angels 12, |
| | range 30 miles, bearing three four zero from mother. |
| **NO RADAR** | Raider 1, Union Marshal, negative radar contact, |
| | say posit relative mother. |
| **YOU** | Marshal, Raider 1, radio check. |
| **MARSHAL** | Raider 1, Union Marshal, loud and clear. |

Marshal picks one of 2 - 4 wordings at random - the first is shown. Same facts, same order of calls.

# MARSHAL CALLS 2

Word for word · inbound to the trap, and the departure · Case I and Case II. Example as card 7.

## INBOUND — in order

| | |
|---|---|
| **YOU** | Marshal, Raider 1, 20 DME. |
| **MARSHAL** | Raider 1, Union Marshal, radar contact, 20 DME, continue. |
| **YOU** | Marshal, Raider 1, see you at ten. |
| **MARSHAL** | Raider 1, Union Marshal, visual carrier at ten miles, |
| | say state. |
| **YOU** | Marshal, Raider 1, state 5.2. |
| **MARSHAL** | Raider 1, Union Marshal, copy state 5.2. |
| **UNDER 2.0** | Raider 1, Union Marshal, state 1.8, expedite recovery. |

## THE STACK — to the trap

| | |
|---|---|
| **YOU** | Marshal, Raider 1, established angels two. |
| **DECK CLEAR** | Raider 1, Union Marshal, signal Charlie. |
| **DECK BUSY** | Raider 1, Union Marshal, entering stack at angels two, |
| | position one, hold for Charlie. |
| **YOU** | Marshal, Raider 1, commencing, state 4.0. |
| **MARSHAL** | Raider 1, Union Marshal, copy commencing, state 4.0, |
| | check in three mile initial. |
| **YOU** | Marshal, Raider 1, initial. |
| **MARSHAL** | Raider 1, Union Marshal, contact paddles, good luck. |

## OFF THE BOAT — after Deckboss pushes you

| | |
|---|---|
| **YOU** | Marshal, Raider 1, clear seven miles. |
| **MARSHAL** | Raider 1, Union Marshal, clear of Union control zone, |
| | push vSFG-7-Command, two eight two point zero, |
| | channel four, for tasking. |
| **YOU** | Marshal, Raider 1, pushing command. |
| **MARSHAL** | Raider 1, Union Marshal, cleared handoff to |
| | vSFG-7-Command, good day. |

Marshal picks one of 2 - 4 wordings at random - the first is shown. Same facts, same order of calls.

# MARSHAL CALLS 3



Word for word · Case III (night or low weather) · Example: BRC 275, ceiling 800, vis 2, approach time 15.

## MARKING MOMS — Case III

| | |
|---|---|
| **YOU** | Marshal, Raider 1, marking moms 340 for 30, |
| | angels 12, state 6.5. |
| **MARSHAL** | Raider 1, Union Marshal, radar contact, angels 12, |
| | range 30 miles from the Abe, bearing three four zero, |
| | mother's weather ceiling eight hundred overcast, |
| | visibility 2, Case Three recovery, BRC 275, |
| | altimeter two niner niner two, |
| | marshal on the zero eight six, two one DME, angels six, |
| | expected approach time is one five, report established. |

## HOLD TO PLATFORM — in order

| | |
|---|---|
| **YOU** | Marshal, Raider 1, established angels six. |
| **MARSHAL** | Raider 1, Union Marshal, roger established angels six, |
| | marshal on the zero eight six, two one DME, |
| | expected approach time is one five. |
| **YOU** | Marshal, Raider 1, commencing. |
| **MARSHAL** | Raider 1, Union Marshal, copy commencing, radar contact, |
| | descend to platform five thousand, final bearing |
| | two six six, confirm BRC two seven five, report platform. |
| **YOU** | Marshal, Raider 1, platform. |
| **MARSHAL** | Raider 1, Union Marshal, copy platform, |
| | final bearing two six six. |
| **8 MILES** | Raider 1, Union Marshal, eight miles, dirty up. |
| **3 MILES** | Raider 1, Union Marshal, three miles, |
| | contact paddles, call the ball. |

## BOLTER / WAVE-OFF — Marshal sees it, or you call it

| | |
|---|---|
| **YOU** | Raider 1, bolter. (or: Raider 1, wave off.) |
| **MARSHAL** | Raider 1, Union Marshal, roger bolter, climb to one |
| | thousand two hundred, at four miles turn downwind, |
| | report abeam. |
| **YOU** | Raider 1, abeam. |
| **MARSHAL** | Raider 1, Union Marshal, roger abeam, four miles past |
| | abeam turn final, final bearing two six six. |

## CASE CHANGE — to everyone in the stack

| | |
|---|---|
| **MARSHAL** | All marshal aircraft, Union Marshal, recovery is now |
| | Case Three, acknowledge on next push. |

- **Radial 086 = final bearing 266 + 180. Final bearing = BRC 275 - 9.** "Approach time one five" is 15 minutes past the hour; the next jet's is ten minutes later.

Marshal picks one of 2 - 4 wordings at random - the first is shown. Same facts, same order of calls.

# PADDLES

SkyEye LSO · 128.300 AM · Black Sea + Syria · dial it · You call the ball; he talks you down. No readbacks.

## ABEAM AND THE BALL CALL

after Marshal's "contact paddles"

| | |
|---|---|
| **ABEAM** | 302 abeam. |
| **PADDLES** | Paddles contact, 302, Hornet in the groove, |
| | at three-quarters of a mile call the ball. |
| **YOU** | 302, Hornet ball, 5.5. |
| **PADDLES** | Roger ball. |
| **CLARA** | 302, Clara, 5.0. -> Paddles contact, keep it coming. |
| **NO CALL** | By 0.6 nm: Call the ball. |
| **RADIO CHECK** | Paddles, Raider 302, radio check. -> loud and clear. |

## IN THE GROOVE

he calls, you fly

| | |
|---|---|
| a little high / high | **A little high. / You're high.** |
| still high after 3 s | **You're high, bring it down.** |
| low, far out / in close | **You're low, power. / Power!** |
| still low / low and sinking | **POWER! / Power, power, POWER!** |
| over-correcting after power | **Easy with it.** |
| left / right of the line | **Right for lineup. / Come left.** |
| Hornet AoA off by 2 | **You're fast. / You're slow.** |

## WAVE OFF AND BOLTER

| | |
|---|---|
| low or off line in close | **Wave off, wave off, wave off.** |
| deck foul at 1/4 nm | **302, foul deck, wave off, wave off, proceed to bolter pattern.** |
| past the wires | **Bolter, bolter, bolter.** |
| trap | **nothing - the grade goes in the log** |

After your trap, on 128.3: "red deck", then "green deck" once clear - Paddles sends you to Deckboss.

Say the modex first - with two in the groove it is how he knows whose ball.

# OFF THE BOAT

Launch to Command · Deckboss -> Marshal -> Command · Three legs, three frequencies.

## THE CHAIN — in order

| | |
|---|---|
| **1 DECKBOSS** | Raider 1, airborne. |
| | Reply: copy airborne, push Marshal and its frequency. |
| **2 MARSHAL** | Marshal, Raider 1, clear seven miles. |
| | Reply: clear of Union control zone, |
| | push vSFG-7-Command, |
| | two eight two point zero, channel four, for tasking. |
| **3 COMMAND** | Command, Raider 1, checking in. |
| **4 DARKSTAR** | Black Sea: Darkstar 264.0 for picture - card 19. |

## GET THE CLEAR CALL RIGHT

- **Say "clear" and a distance:** "clear seven miles", "clear seven DME", "clear of mother" or "clear mothers".
- **Do not add recovery words to it.** If the call also has marking moms, state, initial, established, commencing, platform or bolter in it, Marshal treats you as inbound.
- **"Channel four" is the Hornet's Command preset.** Vipers never launch from the boat - their Command is COMM 1 CH 1.
- **Deckboss names the right Marshal for the theatre:** 306.300 in every theatre.

# COMMAND



282.000 AM · Hornet COMM 1 CH 4 · Viper COMM 1 CH 1 · The squadron net. Both jets, every theatre.

## YOU SAY — Command replies

| | |
|---|---|
| radio check / comm check / how copy | **loud and clear** |
| checking in / check in | **proceed mission** |
| fence in / fence check | **cleared hot · where the GCI is** |
| in hot / pickle / Fox 3 / splash | **cleared hot · copy** |
| 302 ejecting / I'm hit / mayday | **CSAR · nearest field - card 21** |
| on station | **good hunting** |
| off station / departing station | **proceed to assigned pattern** |
| fence out | **safe passage** |
| RTB / request recovery / bingo home plate | **expect handoff at 30 nm** |
| state 5.2 | **copy state** |
| say bullseye / request bullseye | **bullseye NNN for NN** |
| request tanker / say texaco | **bearing, range, angels · Black Sea: cards 17 - 18** |
| request tasking (Black Sea training) | **contact Hitman 1-1 or 2-1 - card 13** |
| proceeding to / request Alpha (Black Sea) | **range areas - cards 15 - 16** |

- **"RTB, fence out" is read as RTB.** The recovery words are checked before fence out.
- **Add your state to any call.** "fence out, state 1.8" - under 2.0 Command tells you you are bingo.

## BULLSEYE AND TANKER — from the radar picture

- **Bearings are magnetic.** Bullseye is your own side's. The tanker is the nearest friendly one - by type, or a Texaco, Arco or Shell callsign.
- **No picture, no answer:** you hear "unable" or "negative tanker on scope".

## THE AUTOMATIC HANDOFF — you do not ask for it

- **Once you have talked to Command, it watches you on Tacview** - when the rig has Tacview connected. Inside 30 nm of your nearest recovery - a field or the carrier - it calls you once.
- **Field:** "contact <field> tower on <frequency>, switching now approved, good landing."
- **Carrier:** "contact Marshal on <frequency>, switching now approved, call marking mom."
- **Launched from the boat?** You are sent to Marshal inside 30 nm of it, even when a field is nearer.

# HITMAN 1-1 / 2-1

1-1 61.000 FM · Hornet COMM 2 CH 12 · Viper COMM 2 CH 8 · 2-1 62.000 FM · no preset yet - dial it

## THE RUN

every call starts "Hitman, Raider 1, ..."

| | |
|---|---|
| **COMMAND** | request tasking -> contact Hitman 1-1 or 2-1 |
| **CHECK IN** | checking in -> say ordnance and playtime |
| **ORDNANCE** | 4 GBU-12, 30 minutes -> target + lines 1-3 |
| **LINES 4-6** | read back 1-3 -> elevation, target, grid |
| **LINES 7-9** | read back 4-6 -> mark, friendlies, egress |
| **COPY** | read back 7-9 -> confirmed, report IP inbound |
| **AT THE IP** | established IP <name> -> run-in heading |
| **IN** | in from the <dir> -> cleared hot, or abort |
| **OFF** | off -> egress per line 9 |

## THE 9-LINE

by reference to your kneeboard card

- **Two JTACs, one sector each.** Nine sites: Hitman 1-1 runs targets 1, 2, 3, 4, 6; Hitman 2-1 runs 5, 7, 8, 9. Each site is the red force first, then its static target. Command sends you to the one with a free target.
- **Hitman asks ordnance and playtime** on your first check-in - answer it and he passes the target.
- **Hitman picks the target, at random.** Not one another flight is working, not the one you just did. Hitman reads the 9-line in three blocks, lines 1-3, 4-6, 7-9, and you read each back. He reads the lines slower than the rest of his talk, so you can copy them. Wrong readback: he says the block again.
- **Missed it? Ask him to repeat.** "Hitman, Raider 1, say again" gives you the block again; "say again line 6" gives you that one line.
- **Another target:** after "off", say "request tasking" to Hitman - or ask Command again.

JTAC LIVE 60.000 (Hornet COMM 2 CH 15) is for a human JTAC. Hitman never answers there.

# CLEARED HOT?

What Hitman checks · from Tacview, against your 9-line card · Bearings and headings magnetic.

## HITMAN CHECKS — or tells you why not

| | |
|---|---|
| Established IP <name> | **run-in heading + attack window** |
| IP inbound | **within 20 nm of the IP** |
| not there | **negative - IP bears NNN for NN** |
| off the run-in line | **continue, run in heading NNN** |
| nose off the target | **continue, check heading** |
| In call | **inside the final attack heading (20 deg slack)** |
| and | **0.5 - 15 nm from the target** |
| outside either | **abort, abort, abort - and why** |

## AFTER CLEARED HOT — Hitman keeps watching

- **Swing more than 20 deg outside the final attack heading** inside 6 nm, still pointed at the target, before a weapon comes off, and Hitman calls the abort. Go round from the IP.
- **Pulling off, a release, or 1.5 nm to go** ends the watch.
- **No radar picture of you** (Tacview down, callsign not matched): no checks - still cleared hot.

## BDA — about 15 s after your bombs land

| | |
|---|---|
| good effects / good hits / shack | **egress, ready for more tasking** |
| partial effects | **kills so far, re-attack approved** |
| no effects | **correct <dir> <metres>, re-attack** |
| unable to assess (the bridges) | **say your observed effects** |

- **Asked for your effects?** "bridge dropped" or "good hits" closes it; "no effects" gets a re-attack. "request BDA" repeats the call.

## ALSO — any time

| | |
|---|---|
| abort | **copy abort, re-attack from the IP** |
| radio check | **loud and clear** |

# RANGE AREAS



Command · 282.000 AM · Black Sea training · Letters match the kneeboard TARGET RANGES card.

| WHAT COMMAND TELLS YOU | threat |
|---|---|
| A Maykop airfield · SA-6, parked aircraft | SA-6 |
| B Krasnodar Pashkovsky · SA-6, aircraft | SA-6 |
| C 22 nm NE Maykop · SA-6, armour, infantry | SA-6 |
| D 9-line targets 1 + 2 | Hitman 1-1 |
| E 191 nm NW Anapa · SA-10 site | SA-10 |
| F 14 nm SW Krasnodar · armour, infantry | none |
| G 9 nm N Krymsk · SA-2 site | SA-2 |
| H / I 9-line targets 4 / 5 | Hitman 2-1 |
| J 9 nm SW Krymsk · armour, trucks | none |
| K 104 nm N Anapa · Kuznetsov, 2 corvettes | SA-N-9, SA-15 |
| L 36 nm NE Krasnodar · train | none |
| M 187 nm W Anapa · cruiser Moskva group | SA-N-6, SA-N-9 |
| N / O Anapa trucks / Kutaisi boats | none |

- **The kneeboard card under-reports three:** E and G are listed "soft x5" - they are an SA-10 and an SA-2 site. M is blank - it is the Moskva's group.

# OVERLORD ACTUAL

Ask for an area, close out the run · Command 282.000 AM · Overlord is a second voice on Command's frequency.

## THE EXCHANGE — "Command, Raider 1, ..."

| | |
|---|---|
| **ASK** | permission to proceed to Alpha -> stand by for Overlord |
| **~10 S** | Overlord: you are Irene for Alpha, report copy |
| **COPY** | copy Irene -> Command: what is there, threat, bearing |
| **OFF** | off target -> copy off Alpha, say intentions |
| **HOME** | Winchester, RTB -> handoff at 30 nm |

## ALSO — Command replies

| | |
|---|---|
| request Alpha / request to work Alpha | **goes to Overlord** |
| proceeding / pushing / inbound Alpha | **brief at once, no Overlord** |
| negative Irene | **another flight has it - ask again** |
| Bingo, RTB | **nearest tanker, handoff at 30 nm** |
| Joker | **copy Joker** |

- **"Irene" and "cleared to engage" both mean go.** Overlord uses either. A flight already on your area is called out - call off target when you are done so it frees up.

# TEXACO

Texaco 1-1, 2-1 and 3-1 · Black Sea Day / Night · the same calls on all three · pick the nearest

## THE FLOW

two baskets each · "Texaco 1 (2 or 3), Raider 1-1"

| | |
|---|---|
| **COMMAND** | request tanker -> bearing, range, contact the nearest Texaco |
| **INITIAL** | 15 mile initial for port observation, intent to refuel |
| | -> cleared port observation ... How much do you request? |
| **GIVE** | request 5.0 (or full) -> cleared for five thousand pounds |
| **TRAIL** | 1 mile trail for port observation -> continue |
| **OBSERVATION** | established port observation -> baskets open |
| **BASKET** | moving to starboard basket -> cleared starboard basket |
| | established starboard basket -> call ready pre-contact |
| | ready pre-contact -> cleared contact starboard basket |
| **DCS MENU** | Ready pre-contact -> cleared contact, plug, take fuel |
| **REFORM** | satisfied, moving to starboard reform -> cleared |
| **CHECK OUT** | checking out / moving on to mission -> cleared to depart |

## RULES

- **Observation is always port, reform always starboard.** Lead makes the initial, trail, observation and check-out calls; each jet its own basket and reform calls.
- **One jet per basket.** A held basket gets "standby, basket occupied" - it frees when that jet calls reform, or after 10 minutes.
- **Fuel won't flow?** SkyEye is radio only - DCS still needs the AI menu Ready pre-contact.

## THE TANKERS

Hornet presets

| | |
|---|---|
| TEXACO 1-1 - KC-130 · TACAN 51Y | **252.100 AM · COMM 2 CH 8** |
| angels 13, about 260 KIAS | |
| TEXACO 2-1 - KC-135 MPRS · TACAN 52Y | **252.200 AM · COMM 2 CH 9** |
| angels 24, about 265 KIAS | |
| TEXACO 3-1 - KC-135 MPRS · TACAN 53Y | **252.300 AM · COMM 2 CH 10** |
| angels 24, about 265 KIAS | |

Radio check any time - loud and clear. Angels and velocity come live off Tacview.

# SHELL

Shell 1-1 and Shell 2-1 · Black Sea Day / Night · KC-135 boom · the same calls on both · pick the nearer one

## THE FLOW

one boom, one jet · "Shell 1 (or 2), Venom 1-1"

| | |
|---|---|
| **COMMAND** | request tanker -> bearing, range, contact the nearest Shell |
| **INITIAL** | 15 mile initial for port observation, intent to refuel |
| | -> cleared port observation ... How much do you request? |
| **GIVE** | request 5.0 (or full) -> cleared for five thousand pounds |
| **TRAIL** | 1 mile trail for port observation -> continue |
| **OBSERVATION** | established port observation -> boom open |
| **BOOM** | moving to the boom -> cleared to the boom |
| | established pre-contact -> call ready pre-contact |
| | ready pre-contact -> cleared contact |
| **DCS MENU** | Ready pre-contact -> cleared contact, boom on, take fuel |
| **REFORM** | satisfied, moving to starboard reform -> cleared |
| **CHECK OUT** | checking out / moving on to mission -> cleared to depart |

## RULES

- **Observation is always port, reform always starboard.** Lead makes the initial, trail, observation and check-out calls; each jet its own boom and reform calls.
- **One jet on the boom.** The next gets "standby, boom occupied" and holds port observation - the boom frees when that jet calls reform, or after 10 minutes.
- **Fuel won't flow?** SkyEye is radio only - DCS still needs the AI menu Ready pre-contact.

## THE TANKERS

Viper presets

| | |
|---|---|
| SHELL 1-1 - KC-135 · TACAN 61Y | **253.100 AM · COMM 1 CH 7** |
| SHELL 2-1 - KC-135 · TACAN 62Y | **253.200 AM · COMM 1 CH 8** |
| both angels 22, Mach 0.68 (about 288 KIAS) | |

Radio check any time - loud and clear. Angels and velocity come live off Tacview.

# DARKSTAR

GCI · Darkstar 264.000 AM Black Sea · Overlord 266.000 AM Syria · SkyEye's AWACS controller, our voice. Picture, threats, bogey dope.

## THE FREQUENCIES

**Hornet · Viper preset**

| | |
|---|---|
| DARKSTAR - Black Sea Day / Night, Kola | **264.000 AM · CH 5 · CH 4** |
| OVERLORD - Syria (Foothold) | **266.000 AM · CH 7 · CH 5** |

Foothold: CH 5 Hornet / CH 4 Viper is 264, the DCS AI E-3 - not SkyEye.

## THE FLOW

**"Darkstar, Raider 302, ..."**

| | |
|---|---|
| **COMMAND** | checking in on 282 · Command still runs your recovery |
| **CHECK IN** | checking in -> radar contact |
| **FENCE IN** | fence in -> copy fence in, picture follows |
| **FLY** | picture · bogey dope · declare · splash - card 20 |
| **FENCE OUT** | fence out -> copy fence out |
| **CHECK OUT** | checking out -> copy, good day. Then Command: RTB |

## TO BE HEARD

**and to get threat calls**

- **Your name must carry your callsign.** DCS name "Raider 302 | Name" or "Venom 212 | Name" - the GCI finds Raider / Venom and the number anywhere in it. SRS name the same as DCS, or threat and merged calls never reach you.
- **Lead with "Darkstar", "Overlord" or "Anyface", then your callsign.** Bearings as three digits ("zero six five"), ranges and altitudes as numbers. No "niner".
- **Command still copies fence in** and adds "Darkstar is up on two six four point zero for picture" - the fence check goes to the GCI, the picture follows.

Overlord Actual on Command (cards 15 - 16) is the range officer, not the GCI.

# GCI CALLS

Every call the GCI answers · as Raider 302 hears them · Bullseye and BRAA numbers are examples.

## YOU SAY

| | Darkstar replies |
|---|---|
| radio check / comm check | good copy · 5 by 5 |
| checking in | radar contact |
| fence in / fence out | copy · picture follows fence in |
| alpha check | contact, alpha check bullseye 010/48 |
| picture | up to 3 groups, from bullseye |
| bogey dope | group BRAA 045/32, 25000, hot, hostile |
| any fast movers / any slow movers | bogey dope: jets / helicopters |
| declare bullseye 010 for 48 at 25000 | hostile, friendly, furball, clean |
| snaplock 125 for 10 at 8000 | threat BRAA 125/10, 8000, hot |
| spiked 080 / strobe 080 | spike range 35 ... · clean 080 |
| vector to tanker | bearing and range |
| splash one / splash | copy splash one |
| checking out | copy, good day |

## UNASKED

only if you are on the GCI frequency

| | |
|---|---|
| every 5 minutes | PICTURE |
| a hostile inside 25 nm · repeats every 3 min | THREAT |
| inside 3 nm of a hostile (fixed wing) | MERGED |
| a hostile off scope 30 s / the GCI comes up | FADED / SUNRISE |
| no AWACS airborne / back up | OFF / ON STATION |

- **It sees what the mission's AWACS sees:** E-3 about 217 nm, E-2 about 200 nm, nothing below its radar horizon or behind a ridge - low in a valley you are hidden. Off station: picture and bogey dope get "off station, no picture".

# COMBAT CALLS

Shots, kills, ejections, battle damage · on the AWACS or Command · No station name needed - just your number first.

## SHOTS AND KILLS

the AWACS copies · Command copies too

| | |
|---|---|
| 302, Fox 3, 080 for 56, 25,000 | **Raider 302, Darkstar, copy Fox three** |
| 302, splash one | **Raider 302, Darkstar, copy splash one** |
| splash one (no callsign) | **Darkstar, copy splash one** |

## DOWN

you, your wingman, or anyone who sees it

| | |
|---|---|
| 302 ejecting / eject, eject / bailing out | **Raider 302 down, launching CSAR.** |
| Raider 301, 302 is down | **Raider 302 down, launching CSAR.** |

"302 down to angels 5" is not a down call. CSAR is the radio call only - nothing spawns.

## HIT OR DAMAGED

the nearest friendly field

| | |
|---|---|
| Command, Raider 302, I'm hit | **nearest field, bearing, miles** |
| mayday / pan pan / declaring an emergency | **elevation, tower frequency** |
| engine fire / lost an engine / hydraulic failure | **same answer** |
| fuel leak / battle damage / request nearest field | **same answer** |

- **Example:** "Raider 302, Command, copy. Nearest field Kobuleti, bearing zero-eight-three, 18 miles, elevation 59. Kobuleti tower two six two point zero, declare your emergency."
- **Bearing is magnetic, from where Tacview has you.** Not on the scope: "No radar contact, say position, and the nearest field."
- **Foothold never sends you to a red-held field.** Read from the campaign save. None friendly: "No friendly field available, say intentions."
- **Then call that tower with your emergency.** It gives you the runway you name and copies souls and fuel - card 28.
- **Any AWACS name works.** Darkstar, Overlord, Magic or Wizard - the SkyEye AWACS on your frequency answers.

# A FULL SORTIE

Off the boat and back · every SkyEye call, in order · Hornet, Case I, Persian Gulf frequencies.

## OUTBOUND

| | |
|---|---|
| **DECKBOSS 128.6** | request taxi · ready cat N · airborne |
| **MARSHAL 306.3** | clear seven miles |
| **COMMAND 282.0** | checking in · fence in · on station |
| **GCI 264 / 266** | Black Sea / Syria: check in · fence in · picture |

## ON THE JOB

| | |
|---|---|
| **COMMAND 282.0** | state · request tanker · say bullseye |
| **COMMAND 282.0** | off station · fence out · RTB |
| **COMMAND 282.0** | Inside 30 nm: contact Marshal, call marking mom. |

## RECOVERY

| | |
|---|---|
| **MARSHAL 306.3** | marking moms · DME reports · see you at ten |
| **MARSHAL 306.3** | state · established angels N · Charlie |
| **MARSHAL 306.3** | commencing · Case I initial / Case III platform |
| **PADDLES 128.3** | Black Sea + Syria: ball call, fly his calls (card 10). |

- **Syria and Black Sea:** the same frequencies - Marshal 306.300 on COMM 1 CH 3.
- **Vipers:** only the Command calls apply here. Towers are cards 23 - 29.

# AIRFIELD ATC

One AI tower per field · UHF AM · Gulf, Black Sea, Syria · Same calls at every field; only name and frequency change.

## HOW TO BE HEARD — every tower call

- **Open with the field name, then your callsign.** "Minhad Tower, Raider 1, request taxi". "Tower" can be dropped when the field name comes first: "Akrotiri, Raider 1, ...".
- **No field name, no answer.** "Raider 1, request taxi" is ignored. A bare "Tower, Raider 1, ..." does work.
- **Misheard names are forgiven.** A letter or two off still counts. Mafraq also answers to King Hussein, and H4 to H-4.
- **CTAF style works too:** "Senaki traffic, Raider 1, rolling runway 09".

## WHAT THE TOWER KNOWS

- **Runway, wind and altimeter come from the mission weather.** Listen to ATIS first - it gives the same runway.
- **It sees you only through Tacview.** Radar check, traffic holds, go-around and speed calls need the rig's Tacview feed.
- **IMC changes the pattern.** Ceiling under 1,500 ft or visibility under 3 nm: no overhead, straight-in only.

## THE TOWER CALLS YOU — no request needed

| | |
|---|---|
| Over 350 kt inside 10 nm | **speed check** |
| Inside 5 nm while a jet is rolling | **go around** |
| Wind shift changes the runway | **runway in use is now NN** |
| Held short, and the traffic has cleared | **cleared for takeoff** |

Built but switched off: "say intentions" and "report clear of the runway".

# TOWER RADIOS

Gulf and Black Sea · tower, ATIS, COMM 1 preset · Presets read off the squadron Hornet and Viper cards.

| PERSIAN GULF | Hornet / Viper |
|---|---|
| AL DHAFRA TOWER 251.100 · ATIS 248.200 | CH 8 / CH 12 |
| AL MINHAD TOWER 250.100 · ATIS 248.300 | CH 10 / CH 14 |
| AL AIN TOWER 250.700 · ATIS 248.850 | CH 16 / CH 19 |

| BLACK SEA | Hornet / Viper |
|---|---|
| BATUMI TOWER 260.000 · ATIS 230.000 | CH 8 / CH 12 |
| KOBULETI TOWER 262.000 · ATIS 232.000 | CH 10 / CH 14 |
| KUTAISI TOWER 263.000 · ATIS 233.000 | CH 12 / CH 18 |
| SENAKI TOWER 261.000 · ATIS 234.000 | CH 14 / CH 16 |
| TBILISI TOWER 267.000 · ATIS 237.000 | CH 18 / CH 10 |

## THE 7-MILE HANDOFF NAMES A CHANNEL — check it

- **Towers send you to Command on 282.000 and add a channel.** Gulf towers say "channel four"; Black Sea towers say "channel one".
- **That channel is only right for one jet.** Gulf: Viper Command is CH 1, not 4. Black Sea: Hornet Command is CH 4 - Hornet CH 1 is Deckboss.
- **Trust the frequency.** 282.000 is right in every theatre.
- **ATIS is one channel above its tower on every card,** except Viper Gulf CH 20: printed 119.850, but SkyEye's Al Ain ATIS is 248.850.

# SYRIA TOWERS

Eastern Med · Foothold · 5 fields · tower and ATIS · Read from the start scripts - dial the frequency.

## THE TOWERS

tower · ATIS

| | | |
|---|---|---|
| AKROTIRI TOWER | 252.000 | ATIS 249.500 |
| BASSEL AL-ASSAD TOWER | 250.600 | ATIS 249.600 |
| BEIRUT TOWER | 250.650 | ATIS 249.700 |
| INCIRLIK TOWER | 360.100 | ATIS 360.200 |
| RAMAT DAVID TOWER | 251.300 | ATIS 256.150 |

## KNOW BEFORE YOU FLY

Syria

- **Check the frequency, not only the channel.** The Foothold preset cards number the channels per airframe.
- **ATIS speaks English, then a local language** (Akrotiri English only).
- **The DCS F-menu tower is somewhere else.** Except at Incirlik, DCS's own controller is not on SkyEye's frequency.
- **The 7-mile handoff says "channel four"** - Hornet Command, 282.000.

# DEPARTURE

Parking to Command · every SkyEye field · Wait for each reply before the next call.

## THE DEPARTURE — in order

| | |
|---|---|
| **REQUEST TAXI** | Minhad Tower, Raider 1, request taxi. |
| | Reply: taxi to runway NN, altimeter, hold short. |
| **HOLDING SHORT** | Minhad Tower, Raider 1, holding short. |
| | Reply: line up and wait. |
| **+ 5 s** | Reply: wind, runway, cleared for takeoff. |
| **AIRBORNE** | Minhad Tower, Raider 1, airborne. |
| | Reply: angels N, expect handoff at seven DME. |
| **7 MILES** | The tower calls you - you say nothing. |
| | Tower: leaving my airspace, contact command. |
| **COMMAND** | Command, Raider 1, checking in. |

## IF YOU ARE HELD

- **Traffic inside 20 nm holds you.** Inside 15 nm: "hold short, traffic on N mile final". 15 - 20 nm: line up and wait, no takeoff clearance.
- **60 s between departures.** Too soon after the last jet: "hold short, departure spacing N seconds".
- **Stay put - the tower calls you.** When the traffic or the spacing clears you get your takeoff clearance.

## GOOD TO KNOW

- **"ready for takeoff" skips line up and wait:** with no traffic you are cleared at once.
- **"rolling runway NN" (CTAF), "departing" or "clear the active"** after takeoff gets the same reply as airborne.
- **No 7 DME call needed.** The tower calls you at 7 miles (Tacview). Call it anyway and the reply is "copy".
- **Optional:** "pushing command" gets a short good day; "request startup" gets Ground's startup approval.

# ARRIVAL

Overhead or straight in · one call per leg · Give your distance with inbound, initial or final.

## THE OVERHEAD — VMC

| | |
|---|---|
| **INBOUND** | Minhad Tower, Raider 1, 10 mile initial. |
| | Reply: runway, wind, altimeter, report initial. |
| **INITIAL** | Minhad Tower, Raider 1, 3 mile initial. |
| | Reply: left break runway NN, number N, report base. |
| **DOWNWIND** | Optional. Reply: number N, report base. |
| **BASE** | Minhad Tower, Raider 1, base, gear down. |
| | Number one: cleared to land. Otherwise: affirmative. |
| **FINAL** | Minhad Tower, Raider 1, on final. |
| | Reply: runway, wind, cleared to land. |
| **VACATED** | Minhad Tower, Raider 1, clear of the active. |

- **Past 15 nm you hear "continue inbound, report N miles".** Answer "15 miles inbound" or "15 mile initial".
- **Say "gear down" in your base or final call,** or the tower adds "check wheels down".
- **"initial" or "break" on its own is taken as your break** (reply: report downwind). Give the distance: "3 mile initial".
- **"touch and go", "low approach" or "the option"** in the final call gets that clearance instead.

## DISTANCES

- **"15 miles inbound" and "15 mile initial" both work.** So does a bare "15 miles". "7 miles" on its own is the 7 DME departure call.
- **A DME needs "inbound" or "initial".** "12 DME inbound" works; "12 DME" on its own is a departure call.
- **"5 mile final" is a landing call,** the same as "on final".

## STRAIGHT IN, IMC, HUNG ORDNANCE

- **"request straight in", "ILS" or "visual approach":** straight-in runway NN approved, altimeter, report final.
- **IMC: the overhead is refused.** Inbound, initial and break get "straight-in only, report ten mile final". Then call "ten mile final".
- **"hung ordnance":** straight in, no overflight, stop at the end of the runway for dearm.

# TOWER CALLS

Every call a tower answers · lead with the field name · Silent calls are heard but get no reply.

## GROUND AND DEPARTURE

| | tower replies |
|---|---|
| request taxi / ready to taxi | **taxi, hold short** |
| holding short / at the hold / holding | **line up and wait** |
| ready for takeoff / request takeoff | **cleared for takeoff** |
| airborne / departing / rolling | **angels, expect handoff** |
| (at 7 miles the tower calls you) | **contact Command** |
| seven DME / seven miles / request handoff | **copy, or contact Command** |
| pushing command | **good day** |

## ARRIVAL AND LANDING

| | |
|---|---|
| N mile initial / N miles inbound | **field information** |
| 3 mile initial / overhead | **break approved** |
| downwind | **number N, report base** |
| base / on final / N mile final | **cleared to land** |
| request straight in / ILS | **straight-in approved** |
| touch and go / low approach / the option | **cleared touch and go** |
| going around | **report downwind** |
| runway vacated / clear of the active | **taxi to parking** |

## ANY TIME

| | |
|---|---|
| say again | **your last call, 2 min** |
| wind check / say altimeter | **wind and altimeter** |
| radar check | **angels, range, bearing** |
| radio check / checking in / green jet | **loud and clear** |
| hung ordnance | **straight in, dearm** |
| mayday / pan pan / emergency (+ runway NN) | **runway is yours - the one you name** |
| N souls on board, fuel state | **crash crew standing by** |
| tally / no joy / altitude check / roger | **silent** |

Anything else gets "say again your request".

# MULTI-SHIP

Flights of 2 - 6 · one clearance for the whole flight · The lead talks. Name the wingmen on the first call.

## DEPARTURE — the lead calls

| | |
|---|---|
| **HOLDING SHORT** | Senaki Tower, Raider 301, flight of three, |
| | 302 and 303, holding short. |
| | Reply: Raider 301 flight, flight of three, line up, wait. |
| **TAKEOFF** | Raider 301 flight, cleared for takeoff - all three jets. |
| **AIRBORNE** | Senaki Tower, Raider 301 flight, airborne. |
| **7 MILES** | Departure calls the flight once. |

## ARRIVAL

| | |
|---|---|
| **INBOUND** | Senaki Tower, Raider 301, flight of two, 302, |
| | 10 miles east, inbound full stop. |
| | Reply: Raider 301 flight, flight of two, report initial. |
| **BASE / FINAL** | Raider 301 flight, cleared to land - both jets. |
| **VACATED** | Senaki Tower, Raider 301 flight, clear of the active. |
| | Ground: Raider 301 spot 12, Raider 302 spot 13. |

## GOOD TO KNOW

- **Say the size:** "flight of two", "two-ship" or "three FA-18s". Wingmen right after the lead: "302 and 303", "Raider 302, Raider 303" or "1-2 and 1-3".
- **A wingman may call too:** named, or flying within 2 nm of the lead, he is answered as the flight.
- **"Raider 301, flight of two, full stop"** on its own is the landing call: cleared to land for both.
- **Spacing and parking:** the next departure waits 60 s plus 20 s per extra jet. Every jet gets a spot; unnamed wingmen get "spots 12, 13 and 14".

# NO ANSWER?

Work down the list · most misses are the first three · Tell the operator what you said, word for word.

## CHECK — in order

| | |
|---|---|
| 1 | Waited 2 - 3 seconds? |
| 2 | Led with the role or field name - Marshal, Minhad Tower? |
| 3 | Said your full callsign? |
| 4 | Used a trigger word from the calls cards? |
| 5 | Half-second pause after keying - call not clipped? |
| 6 | Frequency? Marshal 306.3, Paddles 128.3, Hitman 61FM. |
| | Texaco 252.1/2/3, Shell 253.1/2. GCI: Darkstar 264.0, Overlord 266.0. |
| 7 | SRS shows your TX light? Radio AM (Hitman FM), encryption off? |

## KNOWN QUIRKS

- **Your callsign may be misheard.** Raider as reader or radar, Venom as vino. SkyEye corrects most; if not, slow down and say the digits one at a time.
- **The same call can get a different reply.** Each answer has two to four versions picked at random - the meaning is the same.
- **Marshal needs the number in your callsign.** "Marshal, Raider 1, ..." - a call with no number gets no answer.
- **Paddles answers only the ball call and a radio check.** Everything else he says is his own call on your pass - no readback.
- **The GCI needs your callsign in your name.** DCS and SRS name "Raider 302 | Name" - no Raider / Venom number, no threat calls.
- **Deckboss uses the DCS AI carrier frequency.** You may hear the AI carrier controller on 128.600 as well.

Built from the SkyeyeATC code, origin/main 9de1eb0, 27 OCT 2026.