vSFG-7

VIRTUAL STRIKE FIGHTER GROUP SEVEN



AI ATC PHRASEOLOGY REFERENCE

SkyEye on SRS · every theatre

VMFA-225 Vikings · 421st FS Black Widows

F/A-18C Hornet · F-16C Viper

v2.3 · 16 OCT 2026

Built from SkyeyeATC 15c969b. Frequencies are read from the start scripts; every call in the tables is tested against SkyEye.

1. Frequency Map

Where SkyEye listens, read from the start scripts. All AM, except Hitman (FM). Mission preset channels differ - check the frequency, not only the channel.

Persian Gulf

Channel	Freq (MHz)	Type	Notes
Al Ain Tower	250.700	Two-way	Callsign: Al Ain Tower
Al Dhafra Tower	251.100	Two-way	Callsign: Al Dhafra Tower
Al Minhad Tower	250.100	Two-way	Callsign: Al Minhad Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command
Deckboss - Carrier	128.600	Two-way	CVN-72 launch ops
Marshal - Carrier	306.300	Two-way	Recovery stack
ATIS - Al Ain	248.850	Listen only	Updates with the weather
ATIS - Al Dhafra	248.200	Listen only	Updates with the weather
ATIS - Al Minhad	248.300	Listen only	Updates with the weather
ATIS - Kish	248.500	Listen only	Updates with the weather
ATIS - Liwa	248.550	Listen only	Updates with the weather

Black Sea (Caucasus)

Channel	Freq (MHz)	Type	Notes
Batumi Tower	260.000	Two-way	Callsign: Batumi Tower
Kobuleti Tower	262.000	Two-way	Callsign: Kobuleti Tower
Kutaisi Tower	263.000	Two-way	Callsign: Kutaisi Tower
Senaki Tower	261.000	Two-way	Callsign: Senaki Tower
Tbilisi Tower	267.000	Two-way	Callsign: Tbilisi Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command
Hitman 1-1 - JTAC	61.000 FM	Two-way	9-line targets 1-3
Hitman 2-1 - JTAC	62.000 FM	Two-way	9-line targets 4-5
Deckboss - Carrier	128.600	Two-way	CVN-72 launch ops
Marshal - Carrier	306.300	Two-way	Recovery stack
ATIS - Batumi	230.000	Listen only	Updates with the weather
ATIS - Kobuleti	232.000	Listen only	Updates with the weather

Channel	Freq (MHz)	Type	Notes
ATIS - Kutaisi	233.000	Listen only	Updates with the weather
ATIS - Senaki	234.000	Listen only	Updates with the weather
ATIS - Tbilisi	237.000	Listen only	Updates with the weather

Syria (Eastern Med)

Channel	Freq (MHz)	Type	Notes
Akrotiri Tower	252.000	Two-way	Callsign: Akrotiri Tower
Bassel Al-Assad Tower	250.600	Two-way	Callsign: Bassel Al-Assad Tower
Beirut Tower	250.650	Two-way	Callsign: Beirut Tower
Incirlik Tower	360.100	Two-way	Callsign: Incirlik Tower
Ramat David Tower	251.300	Two-way	Callsign: Ramat David Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command
Deckboss - Carrier	128.600	Two-way	CVN-72 launch ops
Marshal - Carrier	306.300	Two-way	Recovery stack
ATIS - Akrotiri	249.500	Listen only	Updates with the weather
ATIS - Bassel Al-Assad	249.600	Listen only	Updates with the weather
ATIS - Beirut	249.700	Listen only	Updates with the weather
ATIS - Incirlik	360.200	Listen only	Updates with the weather
ATIS - Ramat David	256.150	Listen only	Updates with the weather

Cold War Germany

Channel	Freq (MHz)	Type	Notes
Cologne Tower	119.700	Two-way	Callsign: Cologne Tower
Dusseldorf Tower	118.300	Two-way	Callsign: Dusseldorf Tower
Frankfurt Tower	127.300	Two-way	Callsign: Frankfurt Tower
Hahn Tower	119.500	Two-way	Callsign: Hahn Tower
Hamburg Tower	126.850	Two-way	Callsign: Hamburg Tower
Hannover Tower	120.200	Two-way	Callsign: Hannover Tower
Ramstein Tower	133.200	Two-way	Callsign: Ramstein Tower
Spangdahlem Tower	122.200	Two-way	Callsign: Spangdahlem Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command

Channel	Freq (MHz)	Type	Notes
ATIS - Cologne	248.650	Listen only	Updates with the weather
ATIS - Dusseldorf	248.700	Listen only	Updates with the weather
ATIS - Frankfurt	248.600	Listen only	Updates with the weather
ATIS - Hahn	248.150	Listen only	Updates with the weather
ATIS - Hamburg	248.800	Listen only	Updates with the weather
ATIS - Hannover	248.850	Listen only	Updates with the weather
ATIS - Ramstein	248.000	Listen only	Updates with the weather
ATIS - Spangdahlem	248.050	Listen only	Updates with the weather

Iraq

Channel	Freq (MHz)	Type	Notes
Al Asad Tower	363.700	Two-way	Callsign: Al Asad Tower
Al Sahra Tower	250.150	Two-way	Callsign: Al Sahra Tower
Al Salam Tower	250.250	Two-way	Callsign: Al Salam Tower
Balad Tower	250.550	Two-way	Callsign: Balad Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command
ATIS - Al Asad	230.100	Listen only	Updates with the weather
ATIS - Al Sahra	230.200	Listen only	Updates with the weather
ATIS - Al Salam	230.300	Listen only	Updates with the weather
ATIS - Balad	230.700	Listen only	Updates with the weather

Kola

Channel	Freq (MHz)	Type	Notes
Bodo Tower	251.150	Two-way	Callsign: Bodo Tower
Command	282.000	Two-way	Callsign: vSFG-7-Command
Deckboss - Carrier	128.600	Two-way	CVN-72 launch ops
Marshal - Carrier	306.300	Two-way	Recovery stack
ATIS - Bodo	249.150	Listen only	Updates with the weather

Carrier presets

Marshal 306.300 is Hornet COMM 1 CH 3 "CVN-72 AI MARSHALL" - that is SkyEye. 306.200 "CVN-72 MARSHAL" is kept for a live human Marshal.

Deckboss 128.600 is shared with the DCS AI carrier controller - you may hear both.

2. Addressing the Tower

The tower only responds when addressed. Any of these forms work:

Format	Example
Field name + Tower	"Batumi Tower, Raider 1-1, ..."
Field name alone	"Batumi, Raider 1-1, ..."
Field name + Traffic (CTAF)	"Senaki Traffic, Raider 1-1, rolling runway 09"
Bare - Tower	"Tower, Raider 1-1, ..."

Whisper mishear auto-corrections
Field names: a letter or two off still counts - helmand, el minhad -> Minhad; ldaf, delta for -> Dhafra; alan, el ain -> Al Ain. Mafraq also answers to King Hussein.
Callsigns: Reader / Radar / Rater -> Raider · Vino / Venue / Demon -> Venom.

3. Tower - Request Phraseology

3.1 Ground & Departure

Intent	Say something like	Response
Comm / Radio check	"...radio check" "...comm check" "...how copy"	Loud and clear
Request startup	"...request startup"	Startup approved
Request taxi	"...request taxi" "...ready to taxi"	Taxi to RWY XX, hold short
Holding short	"...holding short" "...at the hold"	Line up and wait, then cleared for takeoff
Takeoff	"...ready for takeoff" "...request takeoff"	Cleared for takeoff
Airborne	"...airborne" "...departing"	Climb angels N, expect handoff at 7 DME
Rolling (CTAF)	"...rolling runway NN"	Same as airborne
7 DME (optional)	"...seven DME" "...seven miles"	Copy - the tower already handed you off
Pushing Command	"...pushing command"	Good day

```
Pilot:      "Batumi Tower, Raider 1-1, request taxi."
Tower:      "Raider 1-1, Batumi Tower, taxi to runway one three, altimeter two niner niner two, hold short."
Pilot:      "Batumi Tower, Raider 1-1, holding short."
Tower:      "Raider 1-1, runway one three, line up and wait."
Tower:      "Raider 1-1, wind one two zero at eight, runway one three, cleared for takeoff."
Pilot:      "Batumi Tower, Raider 1-1, airborne."
Tower:      "Raider 1-1, Batumi Tower, proceed to angels four, expect handoff at seven DME."
Tower:      "Raider 1-1, Batumi Departure, seven miles, angels four, leaving my airspace. Contact command, two
            eight two point zero, channel one. Good day."
```

If you are held

Traffic inside 20 nm, or less than 60 s since the last departure, holds you. Stay put - the tower clears you when it is clear; you do not need to call again.
"seven miles" on its own is the departure call. Inbound, always say "inbound" or "initial" with a distance.

The 7-mile handoff

At 7 miles the tower calls you from Tacview - "<field> Departure ... leaving my airspace, contact command". You do not need to call 7 DME; if you do, the tower answers "copy". Call before 7 miles and you get the handoff then.
After takeoff "clear the active" counts as your airborne call. Fields with an Australian controller sign off "g'day".

3.2 Arrival & Pattern

Intent	Say something like	Response
Inbound (initial call)	"...N mile initial" "...N miles inbound"	Runway, wind, altimeter, report initial
Overhead	"...3 mile initial" "...overhead"	Break approved, number N, report base
Break	"...break"	Report downwind
Downwind	"...downwind"	Number N, report base
Base	"...base, gear down"	Cleared to land / affirmative
On final	"...on final" "...5 mile final"	Cleared to land, RWY XX
Touch and go	"...on final, touch and go"	Cleared touch and go
Straight-in	"...request straight in" "...ILS approach"	Straight-in approved, report final
Going around	"...going around"	Climb runway heading, report downwind
Runway vacated	"...runway vacated" "...clear of the active"	Taxi to parking

```
Pilot:      "Batumi Tower, Raider 1-1, 10 mile initial."
Tower:      "Raider 1-1, Batumi Tower, runway one three, wind one two zero at eight, report initial."
Pilot:      "Batumi Tower, Raider 1-1, 3 mile initial."
Tower:      "Raider 1-1, left break runway one three, number one, report base."
Pilot:      "Batumi Tower, Raider 1-1, base, gear down."
Tower:      "Raider 1-1, runway one three, cleared to land."
Pilot:      "Batumi Tower, Raider 1-1, clear of the active."
Tower:      "Raider 1-1, taxi to parking."
```

Good to know

Past 15 nm you hear "continue inbound, report N miles".
Say "gear down" in your base or final call, or the tower adds "check wheels down".
IMC (ceiling under 1,500 ft or visibility under 3 nm): no overhead - straight in only.

3.3 Any Time

Intent	Say something like	Response
Say again	"...say again"	Repeats your last call (2 min)
Wind / altimeter	"...wind check" "...say altimeter"	Wind and altimeter
Radar check	"...radar check"	Angels, range, bearing
Hung ordnance	"...hung ordnance"	Straight in, dearm at the end
Emergency	"...mayday mayday mayday" "...pan pan"	The runway is yours

The tower calls you when	Call
Over 350 kt inside 10 nm	Speed check
Inside 5 nm while a jet is rolling	Go around
A wind shift changes the runway	Runway in use is now NN
You were held and the traffic has cleared	Cleared for takeoff

4. Command Channel - 282.000 MHz

The squadron net in every theatre. Lead with "Command" and your callsign.

Intent	Say something like	Example Response
Radio check	"...radio check" "...how copy"	Loud and clear
Check in	"...checking in"	Loud and clear, proceed mission
Fence in	"...fence in, state 6.2"	Copy fence in, cleared hot

Intent	Say something like	Example Response
On station	"...on station"	Copy on station, good hunting
Off station	"...off station"	Proceed to assigned pattern
Fence out	"...fence out"	Copy fence out, safe passage
RTB	"...RTB" "...request recovery"	Expect handoff at 30 nm
State	"...state 5.2"	Copy state; under 2.0 bingo
Bullseye	"...say bullseye"	Bullseye NNN for NN
Tanker	"...request tanker"	Bearing, range, angels
Tasking	"...request tasking"	Black Sea: contact Hitman 1-1 (61.0) or 2-1 (62.0)

```
Pilot:    "Command, Raider 1-1, fence in, state 6.2."
Cmd:      "Raider 1-1, Command, copy fence in, you are cleared hot."
Pilot:    "Command, Raider 1-1, request tasking."
Cmd:      "Raider 1-1, Command, contact Hitman one one on six one point zero zero zero for tasking."
```

The automatic handoff
Once you have talked to Command it watches you on Tacview. Inside 30 nm of your recovery - a field, or the carrier if you launched from it - it calls you once with the tower or Marshal frequency.
Bullseye and tanker need the radar picture; without it you hear "unable". Tasking is Black Sea training only.

5. Range Areas and Overlord Actual - Command

Black Sea training. The lettered areas A - O on the kneeboard's TARGET RANGES card. Tell Command where you are going and it tells you what is there; ask, and Overlord Actual (a second voice on Command's frequency) clears you. The 9-line areas D, H and I go to Hitman.

Intent	Say something like	Response
Going to an area	"...proceeding to Alpha" "...pushing Alpha" "...inbound Alpha"	What is there, threat, bearing; report off target
Asking for an area	"...request Alpha" "...permission to proceed to Alpha" "...request to work Alpha"	Stand by for Overlord Actual
Off target	"...off target" "...off Alpha" "...off and egressing"	Copy off; say intentions
Out of weapons	"...Winchester, RTB"	Copy Winchester, RTB, handoff at 30 nm
Fuel to get home	"...Bingo, RTB"	Copy Bingo, RTB, nearest tanker
Fuel low, still working	"...Joker"	Copy Joker

```
Pilot:    "Command, Raider 1-1, permission to proceed to Alpha."
Cmd:      "Raider 1-1, Command, stand by for Overlord Actual."
Ovrld:    "Raider 1-1, Overlord Actual, you are Irene for Alpha, report copy."
Pilot:    "Raider 1-1, copy Irene."
Cmd:      "Raider 1-1, Command, copy Irene. Alpha, Maykop airfield, SA-6 site and parked aircraft. Threat
           SA-6. Alpha bears three-four-zero for 85. Report off target."
Pilot:    "Command, Raider 1-1, off Alpha, Winchester, RTB."
Cmd:      "Raider 1-1, Command, copy off Alpha, Winchester, RTB. Good work. Expect recovery handoff at three
           zero miles."
```

How the areas work

Overlord comes up about 10 s after Command's stand by. He says "you are Irene" or "you are cleared to engage" - both mean go. "Negative" means another flight is working it: ask for another area.

Command gives the threat from what is actually there: E is an SA-10 site, G an SA-2 site, M the cruiser Moskva's group, K the Kuznetsov with SA-15 corvettes. The kneeboard card under-reports E, G and M.

Another flight on the same area is called out ("be advised, Venom 2-1 working Alpha"). Call off target when done so the area frees up.

Bingo: Command adds the nearest tanker when the rig has Tacview. The bearing needs Tacview too.

6. Hitman 1-1 / 2-1 - 61.000 and 62.000 FM (JTAC)

Black Sea training 9-lines, 100-127 nm north of Senaki past the main ridge. Hitman 1-1 (61.0, Hornet COMM 2 CH 12, Viper COMM 2 CH 8) runs Kuban Valley, targets 1-3; Hitman 2-1 (62.0, dial it - no preset yet) runs Cherkessk, targets 4-5. Command sends you to whichever has a free target. Lead with "Hitman".

Intent	Say something like	Response
Check in	"...checking in" "...request tasking"	target N, <name>, IP <IP>, read back
Readback	"...target N, <IP>" "...copy"	Good readback, report IP inbound
IP inbound	"...IP inbound"	Continue (or where the IP is)
In	"...in from the south" "...in heading 330"	Cleared hot - or abort, abort, abort
Off	"...off" "...off safe"	Egress per line 9
BDA	"...request BDA"	Effects, then re-attack, correction or home
Abort	"...abort"	Copy abort, re-attack from the IP
Radio check	"...radio check"	Loud and clear

```
Pilot:      "Hitman 1-1, Raider 1-1, checking in."
Hitman:     "Raider 1-1, Hitman one one, target 4, Fuel Depot, IP Indigo. Read back."
Pilot:      "Hitman, Raider 1-1, target 4, Indigo."
Hitman:     "Raider 1-1, Hitman one one, good readback. Report IP inbound."
Pilot:      "Hitman, Raider 1-1, IP inbound."
Hitman:     "Raider 1-1, Hitman one one, continue."
Pilot:      "Hitman, Raider 1-1, in from the east."
Hitman:     "Raider 1-1, Hitman one one, cleared hot."
Hitman:     "Raider 1-1, Hitman one one, BDA. Impact on the aim point. Partial effects. Large tanks, 2 of 4
            destroyed. 3 of 14 on target destroyed. Re-attack approved, report IP inbound from Indigo."
```

What Hitman checks (Tacview, against your 9-line card)

IP inbound: within 20 nm of the IP, nose on the target. Off the run-in line you hear "continue, run in heading NNN".
In call: inside the card's final attack heading and 0.5 - 15 nm from the target - otherwise abort, abort, abort.
After cleared hot: a run that swings 10 deg outside the window before release is aborted.
BDA about 15 s after impact, one of four: good effects (go home or ask for more), partial effects (re-attack), no effects (a correction, e.g. "correct south 300", then re-attack), or unable to assess - the bridges - when Hitman asks "say your observed effects": answer "bridge dropped" or "no effects".
No radar picture of you: no checks, and you are still cleared hot. JTAC LIVE 60.000 is a human JTAC.

7. Deckboss - 128.600 MHz (Carrier Launch)

Manages cats 1-4 on CVN-72. If all cats are taken you join the conga line (six). Lead with "Deckboss"; the airborne call needs no address.

Intent	Say something like	What Happens
Check in for launch	"...request taxi" "...green jet"	Cleared to cat N, or the conga line
Ready on cat	"...ready cat N" "...shoot"	Under tension, spin it up
Airborne	"...airborne"	Push Marshal 306.3
BRC	"...say BRC"	Mother's BRC, magnetic
Pushing Marshal	"...pushing Marshal"	Short ack
Radio check	"...radio check"	Loud and clear

```
Pilot:      "Deckboss, Raider 1-1, request taxi."
Deck:       "Raider 1-1, Deckboss, cleared to cat two."
Pilot:      "Deckboss, Raider 1-1, ready cat two."
Deck:       "Raider 1-1, Deckboss, under tension cat two, spin it up, shooter's discretion."
Pilot:      "Raider 1-1, airborne."
Deck:       "Raider 1-1, Deckboss, copy airborne, push Marshal, three zero six point three."
```

8. Marshal - 306.300 MHz (Carrier Recovery)

Manages the recovery stack. Marshal ignores a call that does not start with "Marshal" or has no number in your callsign. The case (I, II or III) is set from time and weather.

Intent	Say something like	Response
Check in	"...checking in"	Range and bearing, say marking moms
Marking moms	"...marking moms, angels 12, state 6.5"	Weather, case, BRC, Marshal at angels N
BRC	"...say BRC"	Mother's BRC, magnetic
DME report	"...20 DME"	Radar contact, continue
Inbound 10 nm	"...see you at ten"	Visual at ten, report altitude and range
Fuel state	"...state 5.2"	Copy state; under 2.0 expedite
Established	"...established angels 2"	Signal Charlie, or hold
Commencing	"...commencing"	Check in three mile initial
Platform (Case III)	"...platform"	Final bearing NNN
Initial	"...initial"	Contact paddles, good luck
Clear (departure)	"...clear seven miles"	Push Command 282.0
Radar check	"...radar check"	Angels, range, bearing from mother
Radio check	"...radio check"	Loud and clear

```
Pilot:      "Marshal, Raider 1-1, marking moms 340 for 30, angels 12, state 6.5."
Marshal:    "Raider 1-1, Union Marshal, radar contact, angels 12, range 30 miles, bearing three four zero from
             mother, expect Case One recovery, BRC 275, altimeter two niner niner two, Marshal at angels two,
             report see me at ten."
Pilot:      "Marshal, Raider 1-1, established angels two."
Marshal:    "Raider 1-1, Union Marshal, signal Charlie."
```

Case III (night, or ceiling under 1,500 ft / visibility under 3 nm)
Marking moms gets a holding radial and a push time: hold on the radial NNN at angels N, commence at MM.
Commencing: descend to platform 5,000, final bearing NNN. Call "platform" passing 5,000 ft - your last call.
Radial = BRC + 180. Final bearing = BRC - 9. All magnetic.

9. General Tips

- **Always say your callsign.** Address first, then your full callsign with its number. Raider and Venom are auto-corrected from common mishearings.
- **Keep transmissions under 20 seconds.** Long calls are cut off. Two short calls beat one long one.

- **Pause half a second after keying,** then speak; wait 2 - 3 seconds for the answer and do not re-key over it.
- **CTAF style works.** "[Field] traffic, [callsign], [intent]" is recognised like a direct tower call.
- **Emergencies bypass sequencing.** "mayday", "pan pan" or "declaring emergency" puts you at the top of the queue.
- **ATIS letters only advance on a weather change.** Information Alpha three broadcasts running is expected.
- **Position calls need Tacview.** Radar check, bullseye, Hitman's checks and the 30 nm handoff need the rig's Tacview feed.

If the ATC doesn't respond

1. Addressed the right controller - field name, Command, Hitman, Deckboss or Marshal?
2. Included your full callsign with its number?
3. Used a call from the tables in this reference?
4. Right frequency (section 1), AM - or FM for Hitman? Encryption off?
5. SRS volume and mic - an open mic blocks reception. Still nothing: post the exact words you said.