ATC PHRASEOLOGY

SkyEye AI controllers on SRS · every theatre
Built from SkyeyeATC 5e97223 · v2.0 · 14 OCT 2026

THE CONTROLLERS — who answers

TOWER - one per airfield, ATIS beside it	page 2 - 3
COMMAND - squadron net	282.000 AM
HITMAN 1-1 - JTAC, Black Sea training	61.000 FM
DECKBOSS - carrier deck	128.600 AM
MARSHAL - carrier stack	306.300 AM

HOW TO BE HEARD — every call

- **Address first, then your full callsign.** "Batumi Tower, Raider 1-1, request taxi." No address, no answer - most silences are a misheard field name.
- **Use the words on these pages.** SkyEye listens for key words, not exact sentences; these are the ones it matches.
- **Pause half a second after keying,** then speak. Keep it under 20 seconds - two short calls beat one long one.
- **Wait 2 - 3 seconds for the answer.** Recognition, reply and voice take that long. Do not re-key over it.
- **Radios AM, encryption off.** Hitman 1-1 is FM (61.000).

SPEECH FIXES — SkyEye corrects these

- **Callsigns:** reader / radar / rater -> Raider; vino / venue / demon -> Venom.
- **Field names:** a letter or two off still counts (helmand -> Minhad, delta for -> Dhafra).

ATIS is listen-only. There is no SkyEye LSO - paddles never answers.

FREQUENCIES 1

What SkyEye listens on · read from the start scripts
Tower + ATIS per field · AM unless marked

PERSIAN GULF

Command 282.000 · Deckboss 128.600 · Marshal 306.300

AL AIN TOWER	250.700	ATIS 248.850
AL DHAFRA TOWER	251.100	ATIS 248.200
AL MINHAD TOWER	250.100	ATIS 248.300
KISH ATIS (no tower)		248.500
LIWA ATIS (no tower)		248.550

BLACK SEA (CAUCASUS)

Command 282.000 · Hitman 61.000 FM · Deckboss 128.600 · Marshal 306.300

BATUMI TOWER	260.000	ATIS 230.000
KOBULETI TOWER	262.000	ATIS 232.000
KUTAISI TOWER	263.000	ATIS 233.000
SENAKI TOWER	261.000	ATIS 234.000
TBILISI TOWER	267.000	ATIS 237.000

SYRIA (EASTERN MED)

Command 282.000 · Deckboss 128.600 · Marshal 306.300

AKROTIRI TOWER	252.000	ATIS 249.500
BASSEL AL-ASSAD TOWER	250.600	ATIS 249.600
BEIRUT TOWER	250.650	ATIS 249.700
INCIRLIK TOWER	360.100	ATIS 360.200
RAMAT DAVID TOWER	251.300	ATIS 256.150

Presets differ per mission - check the frequency, not only the channel number.

FREQUENCIES 2



What SkyEye listens on · read from the start scripts
Tower + ATIS per field · AM unless marked

COLD WAR GERMANY

Command 282.000

COLOGNE TOWER	119.700	ATIS 248.650
DUSSELDORF TOWER	118.300	ATIS 248.700
FRANKFURT TOWER	127.300	ATIS 248.600
HAHN TOWER	119.500	ATIS 248.150
HAMBURG TOWER	126.850	ATIS 248.800
HANNOVER TOWER	120.200	ATIS 248.850
RAMSTEIN TOWER	133.200	ATIS 248.000
SPANGDAHLEM TOWER	122.200	ATIS 248.050

IRAQ

Command 282.000

AL ASAD TOWER	363.700	ATIS 230.100
AL SAHRA TOWER	250.150	ATIS 230.200
AL SALAM TOWER	250.250	ATIS 230.300
BALAD TOWER	250.550	ATIS 230.700

KOLA

Command 282.000 · Deckboss 128.600 · Marshal 306.300

BODO TOWER	251.150	ATIS 249.150

Presets differ per mission - check the frequency, not only the channel number.

DEPARTURE

Parking to Command · same calls at every field

Lead with the field name: "Batumi Tower, Raider 1-1, ..."

YOU SAY

	tower replies
request taxi / ready to taxi	**taxi to runway NN, hold short**
holding short / at the hold	**line up and wait, then cleared**
ready for takeoff / request takeoff	**cleared for takeoff**
airborne / departing	**angels N, call seven DME**
rolling runway NN	**same as airborne (CTAF)**
seven DME / seven miles	**contact Command 282.0**
pushing command	**good day**
request startup	**startup approved**

EXAMPLE

Batumi, runway 13

PILOT	Batumi Tower, Raider 1-1, request taxi.
TOWER	Raider 1-1, Batumi Tower, taxi to runway one three, hold short.
PILOT	Batumi Tower, Raider 1-1, holding short.
TOWER	Raider 1-1, runway one three, line up and wait.
TOWER	Raider 1-1, wind ..., runway one three, cleared for takeoff.
PILOT	Batumi Tower, Raider 1-1, airborne.
TOWER	Raider 1-1, climb angels four, contact tower at seven DME.
PILOT	Batumi Tower, Raider 1-1, seven DME.
TOWER	Raider 1-1, contact Command, two eight two point zero.

IF YOU ARE HELD

- **Traffic inside 20 nm or 60 s spacing holds you.** Stay put - the tower clears you when it is clear. You do not need to call again.
- **"ready for takeoff" skips line up and wait** when there is no traffic.
- **"seven miles" alone is the departure call.** Inbound, say "inbound" or "initial" with it.

ARRIVAL

Overhead or straight in · one call per leg
Give your distance with inbound, initial or final.

YOU SAY	tower replies
N mile initial / N miles inbound	runway, wind, altimeter, pattern
3 mile initial / overhead	break approved, report base
break	report downwind
downwind	number N, report base
base, gear down	cleared to land, or affirmative
on final / 5 mile final	runway, wind, cleared to land
request straight in / ILS approach	straight-in approved, report final
on final, touch and go	cleared touch and go
going around	climb runway heading, report downwind
runway vacated / clear of the active	taxi to parking

EXAMPLE — the overhead

PILOT	Batumi Tower, Raider 1-1, 10 mile initial.
TOWER	Raider 1-1, runway one three, wind ..., altimeter ..., report initial.
PILOT	Batumi Tower, Raider 1-1, 3 mile initial.
TOWER	Raider 1-1, left break runway one three, number one, report base.
PILOT	Batumi Tower, Raider 1-1, base, gear down.
TOWER	Raider 1-1, runway one three, cleared to land.
PILOT	Batumi Tower, Raider 1-1, clear of the active.
TOWER	Raider 1-1, taxi to parking.

- **Past 15 nm:** "continue inbound, report N miles".
- **Say "gear down" in your base or final call,** or the tower adds "check wheels down".
- **IMC (ceiling under 1,500 ft or vis under 3 nm):** no overhead - straight in only.

TOWER CALLS

Calls that work in any phase
and the calls the tower makes to you



YOU SAY — tower replies

say again	your last call, within 2 min
wind check / say altimeter	wind and altimeter
radar check	angels, range, bearing
radio check	loud and clear
hung ordnance	straight in, dearm at the end
mayday mayday mayday / pan pan	the runway is yours

THE TOWER CALLS YOU — no request needed - needs the rig's Tacview

Over 350 kt inside 10 nm	speed check
Inside 5 nm while a jet is rolling	go around
Wind shift changes the runway	runway in use is now NN
Held short, and the traffic has cleared	cleared for takeoff

SILENT BY DESIGN

- **tally / no joy / roger / wilco** are heard and logged, no reply.
- **Anything else** gets "say again your request".

COMMAND

282.000 AM · the squadron net, every theatre
Stern English voice · lead with "Command,"



YOU SAY — Command replies

radio check / how copy	**loud and clear**
checking in	**proceed mission**
fence in, state 6.2	**copy fence in, cleared hot**
on station	**good hunting**
off station	**proceed to assigned pattern**
fence out	**safe passage**
RTB / request recovery	**expect handoff at 30 nm**
state 5.2	**copy state; under 2.0 bingo**
say bullseye	**bullseye NNN for NN**
request tanker	**bearing, range, angels**
request tasking	**Black Sea: contact Hitman 1-1**

THE AUTOMATIC HANDOFF — you do not ask for it

- **Once you have talked to Command it watches you on Tacview.** Inside 30 nm of your recovery - a field, or the carrier if you launched from it - it calls you once with the tower or Marshal.
- **Bullseye and tanker need the radar picture.** No picture: "unable" or "negative tanker on scope".
- **Tasking is Black Sea training only.** Elsewhere: "negative tasking at this time".

HITMAN 1-1

JTAC · 61.000 FM · Hornet COMM 2 CH 12 · Viper COMM 2 CH 8
Black Sea training 9-lines · lead with "Hitman,"

YOU SAY

	Hitman replies
checking in / request tasking	**9-line target N, as fragged**
copy	**good readback, report IP inbound**
IP inbound	**continue**
in from the south / in heading 330	**cleared hot, or abort**
off / off safe	**egress per line 9**
request BDA	**impacts, then kills**
abort	**copy abort, re-attack from the IP**
radio check	**loud and clear**

WHAT HITMAN CHECKS

from Tacview, against your 9-line card

- **He picks the target.** One of the five cards at random - find it in your kneeboard.
- **IP inbound:** within 5 nm of the IP, nose on the target.
- **In call:** inside the card's final attack heading and 0.5 - 15 nm out, or abort, abort, abort.
- **After cleared hot** he aborts a run that swings 10 deg outside the window before release.
- **BDA about 15 s after impact:** impacts against the aim point, then kills, priority targets first. Bridges cannot be assessed.
- **No picture of you:** no checks - you are still cleared hot.

JTAC LIVE 60.000 is for a human JTAC. Hitman never answers there.

DECKBOSS

Carrier deck · 128.600 AM · lead with "Deckboss,"
Shares 128.600 with the DCS AI carrier controller.

YOU SAY — Deckboss replies

request taxi / green jet	**cleared to cat N, or the conga line**
ready cat N / shoot	**under tension, spin it up**
airborne	**push Marshal 306.3**
say BRC	**mother's BRC, magnetic**
pushing Marshal	**short ack**
radio check	**loud and clear**

THE RULES

- **Nobody calls the shot.** Run up on "spin it up" - the shooter fires you.
- **Four cats, then the conga line (six).** Full: "deck is full, hold clear".
- **The airborne call needs no address:** "Raider 1-1, airborne".

MARSHAL

Carrier stack · 306.300 AM · lead with "Marshal,"
Marshal ignores a call without its name or your callsign's number.



YOU SAY	Marshal replies
checking in	range and bearing, marking moms please
marking moms, angels 12, state 6.5	case, BRC, Marshal at angels N
say BRC	mother's BRC, magnetic
20 DME	radar contact, continue
see you at ten	report altitude and range
state 5.2	copy state; under 2.0 expedite
established angels 2	signal Charlie, or hold
commencing	check in three mile initial
platform	final bearing NNN (Case III)
initial	contact paddles
clear seven miles	push Command 282.0
radar check	radar contact, angels, range
radio check	loud and clear

CASE III

night, or ceiling under 1,500 ft / vis under 3 nm

- **Marking moms gets a holding radial and a push time:** hold on the radial NNN at angels N, commence at MM.
- **Commencing:** descend to platform 5,000, final bearing NNN. Call "platform" passing 5,000 ft - that is your last call.
- **Radial = BRC + 180. Final bearing = BRC - 9.** All magnetic.

NO ANSWER?

Work down the list

Tell the operator what you said, word for word.



CHECK in order

1	Waited 2 - 3 seconds?
2	Led with the field or role name?
3	Said your full callsign, with its number?
4	Used a call from these pages?
5	Half-second pause after keying - not clipped?
6	Right frequency (page 2 - 3)? AM - or FM for Hitman?
7	SRS shows your TX light? Encryption off?

KNOWN QUIRKS

- **The same call can get a different reply.** Each answer has two to four wordings.
- **Position calls need Tacview.** Radar check, bullseye, Hitman's checks and the 30 nm handoff go quiet or say "unable" without it.
- **ATIS letter only changes with the weather.** Alpha three times running is normal.