

Clerque — Cashier Guide

Your day at the till, from opening the drawer to counting it at the end.

START HERE

Open the shop page in the browser. The heading reads "Sign in to Clerque Counter". Type the shop code in the box marked "Tenant ID", then your own email and your own password, and press "Sign in to Clerque Counter". Use your own sign-in, never anybody else's — signing in anywhere signs that person out everywhere else. Something not working? Ask the owner first. If the owner is stuck too, email devsupport@hnsCorpPh.com with the shop name, what you were doing, and a photo of what the screen said.

This guide follows a real day, from the first sign-in to the last count. Read it once from the front. After that, find the number you need. Everything in quotes is the exact wording you will see.

1. Sign in at the till

Do this at the start of the day, and again after every shift close. Closing a shift always signs you out, so the next person starts under their own name.

- 1 Open the shop page. The left side reads "Clerque · Counter" and "Sell faster. Close the till."
- 2 Stay on the "Password" tab. Type the shop code in "Tenant ID", your own email, and your password. The small eye shows the password if you need to check it.
- 3 Leave "Remember me on this device" ticked on the shop's own device. Press "Sign in to Clerque Counter".
- 4 Once the owner has given you a number, the "PIN" tab is quicker: shop code, email, then your 4 to 8 digit number on the keypad.

Forgot the password? "Forgot password?" is on the same screen, or ask the owner. Five wrong tries in fifteen minutes locks the account for fifteen minutes — nothing is broken, just wait.

2. Open the shift with the money in the drawer

A shift is your own stretch at the till. It starts with the money already in the drawer and ends when you count it. The box that asks for it cannot be closed, so this is always the first thing.

- 1 The box reads "Open Shift" and "Welcome, {your name}." Enter the opening cash before starting your shift."
- 2 If the shop has more than one till, a row asks "Which terminal are you at?". Choose the one you are standing at.
With only one till this row is not shown.
- 3 Count the money in the drawer. Type it under "Opening cash (₱)", or switch to "Count by denomination" and say how many of each note and coin — it adds up for you.
- 4 Check the big figure, then press "Start Shift". The top now shows "Cash Out" and "Close Shift".
"Notes (optional)" takes a short remark first, like "Drawer A, morning shift". Opening the page again later does not start a second shift — the same one comes back.

3. Ring a sale

- 1 Find the drink: press its picture, or type part of its name in the search box at the top. The same box takes a barcode.

- 2 The round buttons above the pictures are the menu groups. "All" is first, then each group the owner made.
- 3 For several of the same drink, type the number first — "3x latte". A small "x3" shows at the right of the search box, and the next drink you press goes in three times.
The search box clears itself afterwards.
- 4 A scanner works too. Scan and the item drops straight in. If it matches nothing you hear an error and read "No product matches barcode".
- 5 Each line on the right has a minus, the number, a plus, and a bin to take the line off. "Subtotal" and "Total" add up underneath.
- 6 When the customer is ready, press the big "Charge ₱x".

The small tag on each picture is how many are left: "12 left" in green, "LOW · 3" in amber, "OUT" in grey. An "OUT" picture cannot be pressed. When one thing is holding a drink back, the picture says it in one line, like "needs Fresh Milk".

BE CAREFUL

Check the order before you press "Charge". Taking a line off beforehand is free and needs nobody's permission. Once it is charged, only a void or a refund can undo it, and that needs a supervisor.

The bar and the kitchen see nothing until the sale is paid. There is no button to send an order through early — tickets arrive on their screens the moment the payment is confirmed.

4. Sizes and add-ons

- 1 Press the drink. If it needs a choice, a box opens with the drink's name at the top and "Customize your order" under it.
- 2 Each group shows "REQUIRED" or "OPTIONAL" on the right, and "· UP TO 3" where several are allowed.
- 3 Press the options. Each shows "+₱20" or "Included", and a tick appears.
- 4 Press "Add to cart · ₱x". The button stays dim until every "REQUIRED" group has an answer.

The choices then show in small grey words under the drink in the order, and they print on the receipt. If a "3x" count was typed, the choices are asked once and used for all three.

BE CAREFUL

A choice cannot be changed once the line is in the order — there is no "customise" on an order line. Take the line off with the bin and ring it again.

5. Park a sale and bring it back

For the customer who steps away to get money, or the big group still deciding.

- 1 Press "Park". The box reads "Park this sale" and "Save the cart for later — recall it from the same terminal within 24 hours."
- 2 Give it a name, or leave it and it becomes "Park #1". Press "Park sale". The order clears and you can serve the next customer.
- 3 To bring it back, press the purple "N parked" at the top of the order, then "Recall" on the right one. The bin beside it throws a parked sale away.

BE CAREFUL

A parked sale lives on that one device for 24 hours. Park it at this till and it comes back only at this till. If something is already in the order it asks "Replace current cart?" — "Discard & recall" throws away what is on the screen.

6. Senior citizen and PWD discount

This one is always yours. It needs nobody's permission.

- 1 Ring the drinks first, then press "Apply PWD / Senior Citizen Discount", and choose "Senior Citizen" or "PWD".
- 2 Under "Items to discount", tick what this card covers. "All" and "None" are shortcuts.
Nothing is ticked to begin with, on purpose — the card does not cover the whole table. The law gives one of each item, so a line with two lattes reads "1 discounted + 1 full price".
- 3 Type the "Name of ID Holder" and the card number. Both are required. There is no set shape — type the number as printed on the card.
- 4 Press "Apply Discount". Both the name and the number print on the receipt.
- 5 More than one card in the group? Press "Add another PWD / Senior in this order". Up to five, and items already claimed are hidden from the next person.

For this shop the sum is simply 20% off the price. The small print on that screen also mentions VAT — a tax this shop is not registered to charge — so it makes no difference to what the customer pays. Say out loud that you are writing down the name and the card number. The law asks for it, and the customer should hear it from you rather than wonder.

7. A discount that is not senior or PWD

Goodwill, a damaged item, a friend of the shop. You will not see that button at all — it belongs to a Sales Lead, a manager or the owner. The way to do it without losing the order: leave the order on the screen, press "Lock" at the top, and let them take the till over with their own number. They press "Apply manual discount", give the amount and a reason, and apply it. Then press "Lock" again and take the till back with your own number before pressing "Charge".

BE CAREFUL

Whoever is signed in when "Charge" is pressed is the name written on the sale. Always take the till back before charging. And the bin beside a discount is not locked — do not press it by accident.

8. Take the payment

After "Charge ₱x" the whole screen becomes the payment sheet. The heading is "Tendering · Bayad" and the amount is in huge type under "Amount due". The tabs across the top are "Cash · Bayad", "GCash", "PayMaya", "Card" and "Split".

Cash

- 1 Type what the customer hands over on the number pad, or press a quick amount (₱20 up to ₱1,000), or "Exact".
- 2 "Bayad · cash received" and "Sukli · change" show side by side. The change box turns green when it is enough, and red with "Short by ₱x — keep entering." when it is not.
- 3 Press "Confirm payment · ₱x received".

Taking more than the amount due is fine. The books record the sale; the receipt still shows what was handed over and the change.

GCash or Maya

- 1 Press "GCash" or "PayMaya". The customer pays using the shop's own code at the counter — Clerque does not put one on the screen.
- 2 Wait for the customer's "Sent successfully" message. Do not confirm before you have seen it.
- 3 Type the reference number from that message into the box. It takes digits only.
- 4 Press "Confirm GCash · ₱x". The reference prints on the receipt and is how the money is matched later.

DO NOT

Never leave the reference blank and never make one up. Without it the money cannot be traced when it lands in the bank.

Card

Run the card on the bank's own machine as usual — Clerque does not talk to it. Then type the number from the machine's slip into "Authorization / Reference no." and press "Confirm Card · ₱x". "Last 4 digits of card" is optional.

Two ways at once

- 1 Press "Split". The right side shows "Total · Bayaran" and "Remaining".
- 2 Under "Add payment" press how they are paying, type the amount or press "Exact remaining", and add a reference for anything that is not cash.
- 3 Press "+ Add ... payment", and repeat until "Remaining" turns into "Settled". Then press "Confirm split · ₱x".

Only cash may go over the amount due. Anything else is refused.

9. The receipt

- 1 The box reads "Sale complete · #..." with a green "Paid" tag, and shows the slip exactly as it prints.
- 2 Press "Print receipt — Receipt Printer". On a tablet with no named printer the button reads "Print via Bluetooth" instead.
- 3 Press "Start next sale →". To print an older one again, open "Orders" and press the order number.

GOOD TO KNOW

This shop's slip is an "ACKNOWLEDGEMENT RECEIPT" and carries the line "THIS IS NOT A SALES INVOICE OR OFFICIAL RECEIPT." The shop keeps giving out its own registered receipts exactly as before. If a customer asks, that is the whole answer — this slip is for the shop, the registered receipt is theirs.

10. Money leaving the drawer during the day

- 1 Press "Cash Out" at the top.
- 2 Choose "Paid Out" for money really spent, or "Cash Drop" for notes moved to the safe.
- 3 Type the "Amount (₱)". For a paid-out, pick a category — Supplies, Delivery, Fuel, Change fund, Tip, Other.
- 4 Write the reason. It needs at least a short sentence or the button stays dim.
- 5 A cash drop always needs an approving manager chosen from the list, and so does a paid-out over ₱500. Ask them in person first.

- 6 Press "Pay out" or "Drop to safe".

DO NOT

There is no undo on this. Once it is pressed, it is recorded. Get the amount right before you press, and tell the manager straight away if it was wrong.

Both kinds lower what the drawer is expected to hold at closing, so your count still comes out right. Ingredients do not belong here — those go into the shop's stock, not out of the drawer.

11. Count the till partway through the day

About every two hours a blue strip appears across the top: "Time to count the till." Press "Count it now", count the drawer, type the amount and press "Save the count". It answers "spot on" or says what the difference was. "Later" pushes it back fifteen minutes.

TIP

This is not a test. It protects you. A drawer counted every couple of hours narrows any shortage to a couple of hours instead of the whole day. Nothing stops while you do it, and selling carries straight on.

12. Lock the till for a break, or hand it over

- 1 Press "Lock". The screen goes dark: "Till locked" and "The shift stays open."
- 2 Coming back yourself: type your own number and press "Unlock".
- 3 Somebody else taking over: they type their own number, and the screen says "Now ringing as {name}."
A takeover offers a count. It is worth doing — if the drawer is short later, it shows whether it happened before or after the handover.

The order on the screen and the open shift carry straight on. The drawer, the opening money and the closing count stay with whoever opened the shift, whoever is ringing.

13. See what is running low

Press "Buy Now" at the top. The list shows what is "OUT OF STOCK" first, then what is "RUNNING LOW", with how much there is and how much is short. "Print" puts it on the receipt printer so you can hand the slip to whoever is shopping. Things the kitchen makes itself — syrups, sauces — are left off on purpose, because nobody buys those. They are watched on the kitchen and bar screens instead. Only when there is nothing at all to buy does the slip say so and point you there.

14. Cancel a paid sale, or give one item back

A paid sale can only be undone the same day, always with a reason, and a supervisor must type their own number on the screen. That protects you as much as the shop: both names are written down.

The whole sale (void)

- 1 Open "Orders". Search by order number or by cashier if you need to.
- 2 Press "Void" in the "Action" column.
- 3 Read the red warning, then type the reason.
- 4 Hand the screen to the manager. They type their number under "Supervisor authorisation required".
- 5 Press "Confirm Void". The row goes pale and reads "voided by {name}".

One item only (refund)

- 1 Open "Orders" and press the row to open it out. It shows "Sold", "Already refunded" and "Remaining".
- 2 Press "Refund" beside the item. Give the quantity, the reason and how the money goes back.
- 3 Leave "Restock inventory" ticked unless the item is damaged. Hand the screen over for the supervisor number, then press "Confirm Refund".

Hand the money back yourself. Clerque writes it down; it does not pay anything out.

BE CAREFUL

A supervisor cannot approve their own void — the app refuses their own number as the approver. What this means for the bar: a drink they had not yet marked ready was never made, so nothing of it is used; a drink already made is written down as waste. A cash refund takes money out of the drawer, and the closing count already expects that.

15. When the internet drops

- 1 An amber strip appears: "You're offline — orders are saved locally and will sync automatically when you reconnect."
- 2 Keep selling. Ring the order exactly as normal.
- 3 On the payment sheet only "Cash · Bayad" and "Split" work. The heading reads "Offline · Cash only".
- 4 The receipt prints with an amber band, "OFFLINE ORDER — PENDING SYNC", and a temporary number starting "LOCAL-".
- 5 When the connection comes back the sales send themselves. If any are stuck, open "Pending Sync" and press "Sync Now".

BE CAREFUL

A shift cannot be opened or closed while the connection is down — both of those need the system. If it drops right at opening time, wait for it to come back before starting the shift.

Every saved sale carries its own tag, so it can never be counted twice, even if it is sent twice.

16. Close the shift and print the Z-read

- 1 Press "Close Shift". The top shows "Orders", "Total Sales", "Cash Sales" and "Digital".
- 2 If anything was paid by phone, check the "Digital breakdown" against the shop's GCash and Maya before going further.
- 3 The blue block does the sum for you: opening money, plus cash sales, less refunds, paid-outs and cash drops, ending in "Expected in drawer".
- 4 Count the drawer for real and type it into "Actual cash in drawer (₱)". "Variance" appears as you type: "Balanced", "Overage" or "Shortage".
- 5 "Notes (optional)" is where an explanation goes. Press "Close Shift".
- 6 The "Z-read" opens. Press "Print Z-read", then "Close shift & sign out".

DO NOT

Type the real count, even when it is short. Never adjust it to fit. The difference is recorded with your name and the manager looks at it — an honest short count is a small thing, a changed one is not.

Trying to sign out with the shift still open brings up "Shift Still Open". Choose "Close Shift First, then Sign Out". Only the person who opened the drawer can close it, though a manager or the owner can close it for

you if you had to go home.

17. Before this works — ask the owner

A few things in this guide need the owner to set them up once. Hand this page to the owner on the first day.

- Each person needs their own sign-in with the role "Cashier" AND a branch. Without a branch the till shows "This account has no branch" and nothing else.
- Each person needs a number of their own, set on the "Staff" page. Without it, the "PIN" tab and the "Lock" button cannot be used at all.
- A supervisor needs a Supervisor number, set in Settings under "Security". Until that exists, no void and no refund can be finished by anyone.
- Every drink needs a group, and every group must be pointed at the Bar or the Kitchen screen. A drink in a group pointed nowhere reaches nobody.
- Sizes and add-ons are set up by the owner on the Products page. They cannot come in from a spreadsheet.
- The shop needs a printer named as the receipt printer, or the till prints wherever the tablet happens to be pointing.
- Each ingredient needs an alert level, or "Buy Now" comes back saying nothing is below its alert level — even on a day the shelf is bare.

18. If something goes wrong

Q: I rang the wrong drink.

A: Not charged yet? Press the bin on that line, or the minus to drop one. Already charged? It has to be a void or a refund on the "Orders" page, same day, with a supervisor.

Q: The customer paid GCash and I did not get the reference.

A: Ask them to open their GCash and read it out. It is on their confirmation message. Do not invent one.

Q: The drawer is short and I cannot find it.

A: Type the true count anyway and write what you know in the notes. Tell the manager tonight, not tomorrow — a same-day shortage is usually findable.

Q: The printer has stopped.

A: The printer button at the top is there at every screen size for exactly this. Press it, then print the receipt again from "Orders".

Q: I pressed "Pay out" with the wrong amount.

A: Nothing on the till can take it back. Tell the manager right away so it can be sorted before the count.

Q: A whole section of the menu on the left is grey with a small lock.

A: That is normal. Those parts belong to the owner. They are shown so you can see what the shop uses, not so you can open them.

Q: The help page inside the app says something different from this guide.

A: Trust this guide. The built-in help is older than the app: the shift button is "Start Shift" not "Open Shift", the "Lock" button really does hand the till to another person without closing the shift, and a cashier's end-of-day slip shows the drawer only.

19. What the till cannot do for you, and why

None of these is a fault, and none of them is about trust in you. They are the shop's safety rails, and most of them protect the person at the till more than anyone else.

You cannot...	Why, and what to do instead
Give a plain discount	The button is not yours. A Sales Lead, manager or the owner takes the till over with "Lock", applies it, and hands it back. Their name is on the discount, not yours.
Cancel a paid sale, or give an item back, on your own	You can start it on the "Orders" page, but a supervisor must type their number. Both names are recorded, which is what clears you if it is ever questioned. And a supervisor cannot approve their own, so it is always two people.
Undo yesterday's sale	Nobody can. Voids are same-day only. After that it is a refund, or a word with the owner.
Move money to the safe on your own, or take back a cash-out	A cash drop always names an approving manager, and so does a paid-out over ₱500. Once either is pressed there is no button anywhere to take it back — speak to the manager.
Close somebody else's shift	The drawer belongs to whoever opened it. A manager or the owner can close it if that person has gone.
See the day's takings on your slip	Your end-of-day slip shows the drawer only — money in, money out, what should be there. The sales figures are the owner's.
See what the shop paid for anything	Supplier prices are stripped out before they ever reach the till, and the "Buy Now" slip shows amounts only. There is nothing to look up.
Open the Dashboard, Products, Staff or Settings	Grey with a small lock, and the words "Your role doesn't have access to this section".
Take a phone or card payment while offline	Those need the connection. Cash only until it is back.
Send an order to the bar before it is paid	There is no button for it. The kitchen and bar pick the ticket up the moment payment is confirmed.

This guide describes Clerque as it works today. If a screen says something different from this page, trust the screen and tell the owner so the guide can be corrected.