## **Ubuntu IP Configuration**

Author: Hope Tan, LU NCAE Cybergames Team Captain '24-25

- display network configuration: ip a
- ens18 is the typical network interface for ubuntu
- edit network configuration file: sudo nano /etc/netplan/01-network-manager-all.yaml
- use the below syntax, replacing the ens 18 address and gateway as appropriate:

```
root@T2-Ubuntu-Desktop: /etc/netplan
 JŦI
 GNU nano 6.2
                                           01-network-manager-all.yaml
# Let NetworkManager manage all devices on this system
 version: 2
 renderer: NetworkManager
 ethernets:
   ens18:
     addresses:
        - 192.168.9.5/24
     gateway4:
         192.168.9.1
     nameservers:
        addresses:
          - 8.8.8.8
          - 8.8.4.4
```

- note: the indentations are all done with 2 spaces
- note: for ubuntu server, use renderer: networkd
- apply changes: sudo netplan apply
- make sure the ip address has updated: ip a
- test internet connectivity: curl google.com
- harden file permissions: sudo chmod 600 /etc/netplan/\*.yaml
- note: you can usually ignore the "gateway4 depreciated" error. if it's a problem, then replace gateway4 with routes using the following syntax:

```
GNU nano 6.2
                                   /etc/netplan/01-network-manager-all.yaml
Let NetworkManager manage all devices on this system network:
 version: 2
  renderer: NetworkManager
                                      Ţ
  ethernets:
    ens18:
      addresses:
        - 192.168.9.5/24
      routes:
        - to: 0.0.0.0/0
          via: 192.168.9.1
      nameservers:
        addresses:
          - 8.8.8.8
         - 8.8.4.4
          - 1.1.1.1
```