


Computer Organization

Lab4 MIPS(3)

Subroutines,
Memory,Assembler(Directive)






- **Subroutines**
 - Caller, Callee
 - jal, jr, \$ra (P1-1:Page6)
 - Stack
 - Recursion (P1-2:Pge7)
- Memory
 - **Static vs Dynamic**
 - **Dynamic Storage**
 - Stack vs Heap (P1-3:Page9)

Assembler - Directives

- - .macro, .endmacro (optional)
 - **Procedure call vs Assembler replace**
- .align (0,1,2)
 - why, how (P2-1:Page15)
- .globl vs .extern
 - .globl main
 - (P2-2:Page18)

Subroutines

- jal function_lable #jump and link
 - Save the address of the next instruction in register \$ra
 - Unconditionally jump to the instruction at function_lable.
 - Used in caller while calling the function
- jr \$ra
 - Read the value in register \$ra
 - Unconditionally jump to the instruction according the value in register \$ra
 - Used in **callee** while returning to the caller
- lw / sw with \$sp
 - Protects register data by using stack in memory






Stack Segment

Stack segment: The portion of memory used by a program to hold procedure call frames.

The program *stack segment*, resides at the top of the virtual address space (starting at address $7fffffff_{hex}$).

Like dynamic data, the maximum size of a program's stack is not known in advance.

As the program **pushes values on the stack**, the operating system **expands** the stack segment **down, toward the data segment**.





Demo #1(1)


.data #piece 1/3 tdata: .space 6 str1: .asciiz "the orignal string is: " str2: .asciiz "\nthe last two character of the string is: " .text la \$a0,tdata \$a0 = address of input buffer addi \$a1,\$zero,6 8 \$a1 = maximum number of read string addi \$v0,\$zero,8 characters to read syscall

la \$a0,str1 #piece 2/3 jal print_string la \$a0,tdata jal **print_string** rea la \$a0,str2 jal print_string la \$a0,tdata+3 jal print string addi \$v0,\$zero,10 syscall

print string #piece 3/3 addi \$sp,\$sp,-8 sw \$a0,4(\$sp) sw \$v0,0(\$sp) addi \$v0,\$zero,4 syscall Iw \$v0,0(\$sp) lw \$a0,4(\$sp) addi \$sp,\$sp,8

Q1. Is it ok to remove the push and pop processing of \$a0 on the stack in "print string"?

Q2. Is it ok to remove the push and pop processing of \$v0 on the stack in "print_string"?





Demo #1(2)


P1-1: What's the value of \$ra while jumping and linking to the print_string (at line 12,15,18,21)?

print_string:
addi \$sp,\$sp,-8
sw \$a0,4(\$sp)
sw \$v0,0(\$sp)

addi \$v0,\$zero,4 syscall

lw \$v0,0(\$sp) lw \$a0,4(\$sp) addi \$sp,\$sp,8

jr **\$ra**



pay attention to the value of \$pc



Recursion

"fact" is a function to calculate the Calculate the factorial.

Code in C:

int fact(int n) {
 if(n<1)
 return 1;
 else
 return (n*fact(n-1));
}</pre>

dynamic 5 m & 19)

P1-2. While calculate **fact(6)**, how many times does push and pop processing on stack happend? How does the value of \$a0 change when calculate **fact(6)**?

Code in MIPS

43/3 L. 2/13

fact:

addi \$sp,\$sp, 8 #adjust stack for 2 items
sw \$ra, 4(\$sp) #save the return address
sw \$a0, 0(\$sp) #save the argument n

slti \$t0,\$a0,1 #test for n<1 beq \$t0,\$zero,**L1** #if n>=1,go to L1

addi \$v0,\$zero,1 #return 1
addi \$sp,\$sp,8 #pop 2 items off stac
jr \$ra #return to caller

L1: addi \$a0,\$a0,-1 #n>=1; argument gets(r jal fact #call fact with(n-1)

lw \$a0,0(\$sp) lw \$ra,4(\$sp) addi \$sp,\$sp,8

ul \$v0,\$a0,\$v0


jr \$ra

#return from jal: restore argument n #restore the return address #adjust stack pointer to pop 2 items

#return n*fact(n-1)

#return to the calle





a->b->c m/200185.


bo;
jal h()->(()
h1.

2 jav usage -) dynamic stack.

在中的多. \$V.1613 用其a、\$V.13.

是用利果是以及使用、包支用stack。 维护data


12) Myerape







Memory: Stack vs Heap

- > Stack: used to store the local variable, usually used in calle.
- > Heap: The heap is reserved for sbrk and break system calls, and it not always present.











The following demo(composed of 4 pieces on this page and the next) is supposed to get and store the data from input device, get the minimal value among the data, the number of input data is determined by user.

.include "macro_print_str.asm"
.data
 min_value: .word 0
.text

print_string("please input the number:")

li \$v0,5
 syscall
 move \$s0,\$v0 #s0 is the number of integers

sll \$a0,\$s0,2
 li \$v0,9
 syscall
 move \$s1,\$v0
 move \$s2,\$v0 #\$s1 is the start of the heap
 move \$s2,\$v0 #\$s2 is the point

print string("please input the array\n") #piece 2/4 add \$t0,\$0,\$0 loop read: li \$v0.5 syscall sw \$v0,(\$s2) addi \$s2,\$s2,4 addi \$t0,\$t0,1 bne \$t0,\$s0,loop read

P1-3: What's the value of \$v0 after finish executing the syscall with yellow background? Is it same with the value of \$sp?

While the 1st input number is 0 or 1, what will happen? why? Modify this demo to make it better



Af min

```
#piece 3/4
     lw $t0,($s1)
     sw $t0,min value
     li $t0,1
     addi $s2,$s1,4 #$s1 is the start of the heap
loop find min:
     lw $a0,min value
     lw $a1,($s2)
     jal find min
     sw $v0,min value
     addi $s2,$s2,4
     addi $t0,$t0,1
     bne $t0,$s0 loop find min #s0 is the number of integers
     print string("the min value : ")
     li $v0,1
     lw $a0,min value
     syscall
     end
```

```
#piece 4/4
find_min:


move $v0,$a0
blt $a0,$a1,not_update
move $v0,$a1

not_update:
jr $ra
```

```
please input the number:3
please input the array
-1
0
1
the min value : -1
-- program is finished running --
```



Derectives in Mars





Derective: .macro, .endmacro

Macros:

A pattern-matching and replacement fatility that provide a simple mechanism to name a frequently used sequence of instructions.

- **Programmer invokes** the macro.
- Assembler replaces the macro call with the corresponding sequence of instructions.

Macros vs Subroutines:

- **Same:** permit a programmer to create and name a new abstraction for a common operation.
- **Difference:** Unlike subroutines, macros do not cause a subroutine call and return when the program runs since a macro call is replaced by the macro's body when the program is assembled.



Demo #3

.text print_string: addi \$sp,\$sp,-4 sw \$v0,(\$sp)

> li \$v0,4 syscall

lw \$v0,(\$sp) addi \$sp,\$sp,4

jr \$ra

Assembler replaces the macro call with the corresponding sequence of instructions.

Q1: What's the **difference** between macro and procedue?

Q2: While save the macro's defination(on the right hand in this slides) in an asm file, and assamble it, what's the assembly result?

Is the macro's defination file runable?

Q3: While save the procedure's defination(on the left hand in this slides) in an asm file, and assemble it, what's the assembly result?

Is the procedure defination file runable?

```
.macro print string(%str)
.data
    pstr: .asciiz %str
.text
    addi $sp,$sp,-8
    sw $a0,4($sp)
    sw $v0,($sp)
    la $a0,pstr
    li $v0,4
    syscall
    lw $v0,($sp)
    lw $a0,4($sp)
    addi $sp,$sp,8
end macro
```



li \$v0,10

syscall

Derective: .align(Demo #4-1)

```
.data
             #A
str1: .ascii "Welcome"
str2: .ascii "to"
str3: .asciiz "MIPS32World"
.text
la $t0, str2
lb $t1,($t0)
addi $t1,$t1,-32
sw $t1,($t0)
la $a0,str1
li $v0,4
syscall
```

```
#B
.data
str1: .ascii "Welcome"
str2: .ascii "to"
str3: .asciiz "MIPS32World"
.text
la $t0, str2
lw $t1,($t0)
addi $t1,$t1,-32
sb $t1,($t0)
la $a0,str1
li $v0,4
syscall
li $v0,10
syscall
```

Which demo(s) would invoke an exception "fetch address not aligned on word boundary 0x10010007"?

Which instruction would invoke the exception? Ib, sw, lw, sb?

Tips:

While transfering data, the address of data in memory is required to be aligned according to the bit width of data.



Derective: .align(Demo #4-2)

.align: align next data item on specified byte boundary(0=byte, 1=half, 2=word, 3=double)

P2-1: Which demo(s) would run without exception? Which demo(s) would get the output "WelcomeToMIPS32World"?

.data #A

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

Ih \$t1,(\$t0)

addi \$t1,\$t1,-32

sh \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

.data

#B

str1: .ascii "Welcome"

.align 2

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

lw \$t1,(\$t0)

addi \$t1,\$t1,-32

sw \$t1,(\$t0)

la \$a0.str1

li \$v0,4

syscall

li \$v0,10

syscall

.data

align 2

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

#C

.text

la \$t0, **str2**

lw \$t1,(\$t0)

addi \$t1,\$t1,-32

sw \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

#D .data

str1: .ascii "Welcome"

str2: .ascii "to"

str3: .asciiz "MIPS32World"

.text

la \$t0, **str2**

Ib \$t1,(\$t0)

addi \$t1,\$t1,-32

sb \$t1,(\$t0)

la \$a0,str1

li \$v0,4

syscall

li \$v0,10

syscall

syscall



Derective: .globl vs .extern

- **include:** insert the contents of the specified **file**, put filename in quotes
- .globl : declare the listed label(s) as global to enable referencing from other files
- .extern: declare the listed label and byte length to be a global data field

Local label

A label referring to an object that can be used ONLY within the FILE in which it is defined.

External label

A label referring to an object that can be referenced from FILE other than the one in which it is defined.

Find the usage of ".extern" and ".globl" on Demo 5-1 and 5-2 What's the relationship between globl main and the entrance of program? What will happen if an external data have the same name with a local data?



Demo #5-1

it's in print callee.it's the default_str it's in print caller.it's the default_str

- Q1. Is the running result same as the sample snap?
- Q2. How many "default_str" are defined in "print_callee.asm" ?
- Q3. While executing the instruction "la \$a0,default_str" in these two files, which "default_str" is used?

```
.include "print callee.asm"
.data
  str caller:
                .asciiz "it's in print caller."
.text
.globl main
main:
     jal print callee
     addi $v0,$zero,4
     la $a0,str caller
     syscall
     la $a0, default str ###which one?
     syscall
     li $v0,10
     syscall
```

```
.extern default str 20
.data
     default str:
                      .asciiz "it's the default str\n"
     str callee:
                      .asciiz "it's in print callee."
.text
                addi $sp,$sp,-4
print callee:
                sw $v0,($sp)
                addi $v0,$zero,4
                la $a0,str callee
                syscall
                la $a0, default str
                syscall
                lw $v0,($sp)
                addi $sp,$sp,4
                jr $ra
```



Demo #5-2

In Mars, set "Assemble all files in directory", put the following files in the same directory, then run it. Answer the questions on last page again.

Find the value of globl lable "main", "print_callee" and the initial value of \$PC

```
.data
                                                                       .data
   str caller:
                                  "it's in print caller."
                                                                                             defaulte str 20
                    .asciiz
                                                                              .extern
                                                                              str callee:
                                                                                                   .asciiz
                                                                                                                 "it's in print callee."
.text
.globl main
                                                                              defaulte str:
                                                                                                   .asciiz
                                                                                                                 "ABC\n"
                                                                       .text
main:
                                                                       .globl print_callee
      jal print callee
                                                                       print callee:
                                                                                            addi $sp,$sp,-4
      addi $v0,$0,0x0a636261
                                                                                            sw $v0,($sp)
      sw $v0, defaulte str
                                              Settings Tools Help
                                                                                            addi $v0,$zero,4

☑ Show Labels Window (symbol table)

      addi $v0,$zero,4
                                                                                            la $a0,str callee
                                              □ Program arguments provided to MIPS program
      la $a0,str caller
                                                                                            syscall
                                              Popup dialog for input syscalls (5,6,7,8,12)
      syscall
                                                                                            la $a0, defaulte str

☑ Addresses displayed in hexadecimal

       la $a0, defaulte str
                                                                                            syscall

☑ Values displayed in hexadecimal

       syscall


☑ Assemble file upon opening

                                                                                            lw $v0,($sp)
                                              Assemble all files in directory
      li $v0,10
                                                                                            addi $sp,$sp,4
                                              Assembler warnings are considered errors
                                              ✓ Initialize Program Counter to global 'main' if defined
      syscall
                                                                                            jr $ra
```

CS202 wangw6@sustech.edu.cn



Tips on Mars



To make the instruction labled by 'global main' as the 1st instruction to run, do the following settings.

In **Mars** 'manual:

Settings -> Initialize Program Counter to global 'main' if defined

| | t Segment | | | | | • |
|------|------------|------------|-----------------------------|-----|-----------------------|---|
| Bkpt | Address | Code | Basic | | Source | |
| | 0x00400030 | 0x23bd0008 | addi \$29, \$29, 0x00000008 | 20: | addi \$sp,\$sp,8 | |
| | 0x00400034 | 0x03e00008 | ir \$31 | 21: | ir \$ra | |
| | 0x00400038 | 0x0c100000 | jal 0x00400000 | 7: | jal print_callee | |
| | 0x0040003c | 0x20020004 | addi \$2,\$0,0x00000004 | 9: | addi \$v0,\$zero,4 | |
| | 0x00400040 | 0x3c011001 | lui \$1,0x00001001 | 10: | la \$a0, str_caller | ì |
| | 0x00400044 | 0x3424002c | ori \$4,\$1,0x0000002c | | | |
| | 0x00400048 | 0x0000000c | syscall | 11: | syscall | |
| | 0x0040004c | 0x3c011001 | lui \$1,0x00001001 | 12: | la \$a0, defaulte_str | Î |
| | 0x00400050 | 0x34240000 | ori \$4,\$1,0x00000000 | | | |
| | 0x00400054 | 0x0000000c | syscall | 13: | syscall | Î |
| | 0x00400058 | 0x2402000a | addiu \$2, \$0, 0x0000000a | 15: | li \$v0,10 | |
| | 0x0040005c | 0x0000000c | syscall | 16: | syscall | 1 |

| Label | Address ▲ | | |
|--------------|------------|--|--|
| (global) | | | |
| print_callee | 0x0040000 | | |
| main | 0x0040003 | | |
| defaulte_str | 0x1000000 | | |
| defaulte_str | | | |
| pc | 0x00400038 | | |



Tips: macro_print_str.asm

```
.macro print_string(%str)
   .data
   pstr: .asciiz %str
   .text
   la $a0,pstr
   li $v0,4
   syscall
.end macro
.macro end
   li $v0,10
   syscall
.end macro
```

Define and use macro, get help form help page of Mars