Pivotal Cloud Foundry 2.0 ORG/SPACE/USER 관리 Lab


SDS Workshop 2018-02-01

참석자 별 접속 정보

수강자	Ops Manager	Apps Manager	CF API endpoint
SDS1	https://pcf.sds1.cfpush.net	https://apps.sys.sds1.cfpush.net	https://api.sys.sds1.cfpush.net
SDS2	https://pcf.sds2.cfpush.net	https://apps.sys.sds2.cfpush.net	https://api.sys.sds2.cfpush.net
SDS3	https://pcf.sds3.cfpush.net	https://apps.sys.sds3.cfpush.net	https://api.sys.sds3.cfpush.net
SDS4	https://pcf.sds4.cfpush.net	https://apps.sys.sds4.cfpush.net	https://api.sys.sds4.cfpush.net
SDS5	https://pcf.sds5.cfpush.net	https://apps.sys.sds5.cfpush.net	https://api.sys.sds5.cfpush.net
SDS6	https://pcf.sds6.cfpush.net	https://apps.sys.sds6.cfpush.net	https://api.sys.sds6.cfpush.net
SDS7	https://pcf.sds7.cfpush.net	https://apps.sys.sds7.cfpush.net	https://api.sys.sds7.cfpush.net

Ops Manager 에서 PCF 'admin' 암호 확인

Ops Manager 에 접속하여, "PCF Small Footprint" tile 에 들어가면 Credentials 에서 'admin' 계정의 암호를 확인할 수 있다.



CF CLI Login

1. CF API endpoint 설정

\$ cf api https://api.sys.sds61.cfpush.net --skip-ssl-validation

\$ cf api https://api.sys.sds61.cfpush.net --skip-ssl-validation

Setting api endpoint to https://api.sys.sds61.cfpush.net...

OK

api endpoint: https://api.sys.sds61.cfpush.net

api version: 2.98.0

2. CF login

설치 후 별도 Org/Space 를 생성하지 않아서 초기 login 은 system space 로 target 을 잡는다.

\$ cf login

\$ cf login

API endpoint: https://api.sys.sds61.cfpush.net

Email> admin

Password>

Authenticating...

OK

Targeted org system

Select a space (or press enter to skip):

- 1. autoscaling
- 2. healthwatch
- 3. nfs
- 4. notifications-with-ui
- 5. pivotal-account-space
- 6. system

Space > 6

Targeted space system

API endpoint: https://api.sys.sds61.cfpush.net (API version: 2.98.0)

User: admin
Org: system
Space: system

Org 만들기

할당된 id 에 -org 를 붙여서 생성한다.

\$ cf create-org sds[x]-org

\$ cf create-org sds61-org

Creating org sds61-org as admin...

OK

Assigning role OrgManager to user admin in org sds61-org ...

OK

TIP: Use 'cf target -o sds61-org' to target new org

\$ cf org sds61-org

Getting info for org sds61-org as admin...

name: sds61-org

domains: apps.sds61.cfpush.net

quota: default

spaces:

isolation segments:

Space 만들기

이전에 만든 Org 로 Target 변경

\$ cf target -o sds[x]-org

\$ cf target -o sds61-org

api endpoint: https://api.sys.sds61.cfpush.net

api version: 2.98.0 user: admin org: sds61-org

No space targeted, use 'cf target -s SPACE'

Dev 스페이스 생성

\$ cf create-space dev

\$ cf create-space dev

Creating space dev in org sds61-org as admin...

OK

Assigning role RoleSpaceManager to user admin in org sds61-org / space dev as admin...

OK

Assigning role RoleSpaceDeveloper to user admin in org sds61-org / space dev as admin...

OK

TIP: Use 'cf target -o "sds61-org" -s "dev" to target new space

Dev 스페이스로 Target 변경

\$ cf target -o sds[x]-org -s dev

\$ cf target -o "sds61-org" -s "dev"

api endpoint: https://api.sys.sds61.cfpush.net

api version: 2.98.0 user: admin org: sds61-org space: dev

User 만들기

\$ cf create-user sds[x] <password>

\$ cf create-user sds61 sds61

Creating user sds61...

OK

TIP: Assign roles with 'cf set-org-role' and 'cf set-space-role'.

Org Role 할당

'set-org-role'을 syntax 에 사용 가능한 Role 이름이 나타남.

\$ cf set-org-role

\$ cf set-org-role

Incorrect Usage: the required arguments 'USERNAME', 'ORG' and 'ROLE' were not provided

NAME:

set-org-role - Assign an org role to a user

USAGE:

cf set-org-role USERNAME ORG ROLE

ROLES:

'OrgManager' - Invite and manage users, select and change plans, and set spending limits 'BillingManager' - Create and manage the billing account and payment info 'OrgAuditor' - Read-only access to org info and reports

SEE ALSO:

org-users, set-space-role

\$ cf set-org-role sds[x] sds[x]-org OrgManager

\$ cf set-org-role sds61 sds61-org OrgManager

Assigning role OrgManager to user sds61 in org sds61-org as admin... OK

Space Role 할당

'set-space-role'을 syntax 에 사용 가능한 Role 이름이 나타남.

\$ cf set-space-role

\$ cf set-space-role

Incorrect Usage: the required arguments 'USERNAME', 'ORG', 'ORG' and 'ROLE' were not provided

NAME:

set-space-role - Assign a space role to a user

USAGE:

cf set-space-role USERNAME ORG SPACE ROLE

ROLES:

'SpaceManager' - Invite and manage users, and enable features for a given space 'SpaceDeveloper' - Create and manage apps and services, and see logs and reports 'SpaceAuditor' - View logs, reports, and settings on this space

SEE ALSO:

space-users

\$ cf set-space-role sds[x] sds[x]-org dev SpaceManager

\$ cf set- space -role sds61 sds61-org dev SpaceManager

Assigning role RoleSpaceManager to user sds61 in org sds61-org / space dev as admin... OK

신규 User 로 Login 하기

사용자에게 할당된 Org, Space 가 한 개이면 자동으로 Target 이 설정됨.

\$ cf login

\$ cf login

API endpoint: https://api.sys.sds61.cfpush.net

Email> sds61

Password>

Authenticating...

OK

Targeted org sds61-org

Targeted space dev

API endpoint: https://api.sys.sds61.cfpush.net (API version: 2.98.0)

User: sds61 Org: sds61-org Space: dev

Apps Manager 로그인

Apps Manager 가 admin 으로 로그인 되어 있으면, 로그 아웃 후 접속.

