Troff Formatting With The Memorandum Macro Set

Blake McBride (blake@mcbride.name)

Processing a document with groff

Processing a document with heirloom troff

Page Header & Footer

INPUT	PRODUCES
.PH "'L'C'R'"	set page header Left, Center, and Right text
.PF "'L'C'R'"	-n- set page footer Left, Center, and Right text (blank)
\\\\nP	current page number

Page headers default to about 6 lines. Change operation of page headers with:

```
.de TP
.SP .75i
```

Page Layout

INPUT	PRODUCES
.po 1i	sets left margin (page offset) to one inch
.ll 6.5i	sets the line length to 6.5 inches

Fonts

INPUT	PRODUCES
.S n	set font point size to n (default 10)
.B ["text"]	bold text (if text missing, stay in bold until .R)
.I ["text"]	italics text (if text missing, stay in italics until .R)
.R	roman
.ft CW	use constant width font
.ft P	return to previous font
\s(NN	use font size NN
\s±N	increment or decrement font by N points
\s0	return to previous font size

Special Characters

INPUT	PRODUCES
\e	
\E	\ (copy mode)
`abc´	'abc'
``abc´´	"abc"
"abc"	"abc"
abc-def	abc-def
abc\-def	abc-def
abc\(emdef	abc—def
\&	zero width space

A line that ends with a period, question mark, or exclamation point gets extra intersentence space added. Inter-word spaces are retained, so you can also produce extra space after an end of sentence with two spaces.

End a line with \& if that line should not end a sentence.

Comment lines begin with .\"

In-line comments begin with \"

Paragraphs

The .P macro introduces a new paragraph. Each paragraph should begin with .P

INPUT	PRODUCES
.P	new paragraph — default style
.P 0	new paragraph — left justified
.P 1	new paragraph — indented
.nr Pt 0	set paragraph default to left justified (default)
.nr Pt 1	set paragraph default to indented
.nr Pt 2	set paragraph default to indented except after a header
.nr Ps n	set number of blank lines between a paragraph (default 1)
.nr Hy 1	turn hyphenation on (default off)
.SA 0	no adjust right margin
.SA 1	adjust right margins (default)

Miscellaneous

INPUT	PRODUCES
.SP [n]	n blank lines (or .SP .2i means .2 inches)
.OP	start next line on new odd page
.br	break — end line
.bp	break page
.ce n	center n lines
.nf	no fill
.fi	fill
.so file	include file
.ti n	temporary indent for next line only
.in n	indent n
.in	return to previous indent
.ls lspace	line spacing
.ls	return to previous line spacing

Lists

INPUT	PRODUCES
.AL [t]	numbered list (t=type)
.BL	bullet list
.DL	dash list
.ML	marked list
.RL	reference list
.VL i	variable list (i=width of label passed to .LI)
.LI [label] .LE .nr Ls n .nr Li n	list item (the actual item appears on the following line) list end list level that stops adding blank lines between elements list indent level
.111 121 11	nst macht level

TYPE	PRODUCES
1	Arabic number (default for all levels)
A	upper-case letter
a	lower-case letter
I	upper-case roman
i	lower-case roman

Sections

INPUT	PRODUCES
.H level "heading"	header at level (1–7)
.nr Ej 1	make H1 appear at top of new page

Table of Contents

INPUT	PRODUCES
.nr Cl x	save headers to level x
.TC	produce toc (used at end of doc)

Foot Notes

INPUT	PRODUCES
*F	footnote reference number (used before footnote)
.FS	footnote start
.FE	footnote end

Definitions

INPUT	PRODUCES
.de name	define macro name
••	end macro definition
\\\$n	access macro argument n (1-9)
.ds name value	define string
.nr name value	set numbered register
$\$ X	display value of string named X
$\setminus *(XY$	display value of string named XY
$\n X$	display value of numbered register named X
$\n(XY)$	display value of numbered register named XY
*(DT	display today's date
.nr X 1+\ $*X$	add 1 to register X

Macro arguments that have spaces in them should be surrounded with double-quotes.

Displays

Keeps blocks of text on the same page.

PRODUCES
display start
fmt:
L = left justify (default)
I = indent
C = center each line
CB = center entire block
fill:
N = no fill (default)
F = fill
rindent = right indent
display end

Rev 1/18/15 5