

ORACLE
NetSuite

Fixed Assets Management



2025.2

December 17, 2025



Copyright © 2005, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

If this document is in public or private pre-General Availability status:

This documentation is in pre-General Availability status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

If this document is in private pre-General Availability status:

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your pre-General Availability trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, timing, and pricing of any features or functionality described in this document may change and remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Master Agreement, Oracle License and Services Agreement, Oracle PartnerNetwork Agreement, Oracle distribution agreement, or other license agreement which has been executed by you and Oracle and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <https://www.oracle.com/corporate/accessibility>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Sample Code

Oracle may provide sample code in SuiteAnswers, the Help Center, User Guides, or elsewhere through help links. All such sample code is provided "as is" and "as available", for use only with an authorized NetSuite Service account, and is made available as a SuiteCloud Technology subject to the SuiteCloud Terms of Service at www.netsuite.com/tos.

Oracle may modify or remove sample code at any time without notice.

No Excessive Use of the Service

As the Service is a multi-tenant service offering on shared databases, Customer may not use the Service in excess of limits or thresholds that Oracle considers commercially reasonable for the Service. If Oracle reasonably concludes that a Customer's use is excessive and/or will cause immediate or ongoing performance issues for one or more of Oracle's other customers, Oracle may slow down or throttle Customer's excess use until such time that Customer's use stays within reasonable limits. If Customer's particular usage pattern requires a higher limit or threshold, then the Customer should procure a subscription to the Service that accommodates a higher limit and/or threshold that more effectively aligns with the Customer's actual usage pattern.

Beta Features

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

This documentation is in pre-General Availability status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your pre-General Availability trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, and timing of any features or functionality described in this document remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Master Agreement, Oracle License and Services Agreement, Oracle PartnerNetwork Agreement, Oracle distribution agreement, or other license agreement which has been executed by you and Oracle and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

Table of Contents

Fixed Assets Management Overview	1
Installing the Fixed Assets Management SuiteApp	3
Fixed Assets Management SuiteApp Prerequisites	3
Fixed Assets Management SuiteApp Installation	3
Making the Fixed Assets Tab Available to Custom Roles	4
Setting Fixed Assets Management Permission Levels	4
Record Permissions for Fixed Assets Management	4
Form Permissions for Fixed Assets Management	6
Setting Up the Fixed Assets Management System	9
General Ledger Accounts for Fixed Assets Management	9
Setting Up General Ledger Accounts to be Included in Fixed Assets Management	9
Verifying Successful Account Definition in Asset Type and Asset Records	10
Fixed Assets General Preferences	10
FAM Asset Setup Subtab	11
FAM Asset Management Subtab	12
FAM Lease Setup Subtab	13
Summarizing Journal Entries	13
Fixed Assets Report Preferences	14
Fixed Assets Country Specific Preferences	15
FAM Diagnostics Portlet	16
Setting Up FAM Diagnostics	17
Adding or Deleting Asset Values Using the Review Assistant	18
Deleting DHRs Using the Review Assistant	19
Scheduling a Diagnostic Scan	20
Asset Transfer Accounts	20
FAM Asset Types	21
Asset Type General Subtab	21
Asset Type Accounts Subtab	22
Asset Type Maintenance Subtab	23
Asset Type Other Methods Subtab	23
Asset Type Lifetimes Subtab	24
Depreciation Methods	24
Preconfigured Depreciation Methods	25
Japan Depreciation	30
French Degressive Depreciation	32
French Derogatory Depreciation	32
Creating a New Depreciation Method	34
Depreciation Formula	35
Alternate Methods (Tax Depreciation Methods)	38
Creating Alternate Methods (Tax Depreciation Methods)	38
Viewing or Editing Alternate Methods (Tax Depreciation Methods)	39
Adding Tax Depreciation Methods to an Asset	39
Using Tax Depreciation Methods	39
Custom Segments and Custom Fields in Fixed Assets Management Records and Transactions	40
Applying Custom Segments to Fixed Asset Management Records and Transactions	40
Mapping Custom Segments and Custom Fields to Fixed Assets Management Records	41
Creating Fixed Assets Management Records	44
Creating Asset Records from Transactions	44
Asset Proposal and Generation	45
Asset Creation	49
Multiple Asset Proposal	50
Creating Asset Records through CSV Import	52
Setting CSV Import Preferences	53

General Guidelines for Importing Fixed Asset Records	53
Guidelines for Importing Mid-life Asset Records	54
Guidelines for Importing Fully Depreciated or Disposed Asset Records	54
Importing Fixed Asset Records	55
Importing Asset Depreciation History Records (DHRs)	57
Updating Tax Methods	59
Importing Tax Method DHRs	61
Setting Default Values and Reference Types	63
Creating Asset Records Manually	65
Asset Values Record	67
Compound Assets	68
General Subtab	69
Accounts Subtab	71
Lease Subtab	71
Insurance Subtab	71
Maintenance Subtab	71
Components Subtab	72
Asset Sale/Disposal Tab	72
Depreciation History Subtab	72
Asset Usage Subtab	75
Sub-Assets Subtab	75
Income/Expense Subtab	76
Notes Subtab	76
Files Subtab	76
Updating Fixed Assets Management Records	77
Updating Asset Records Using CSV Import	77
Adding Alternate Depreciation Methods Using CSV Import	78
Triggering the Asset Reset Process	80
Field Changes That Trigger an Asset Reset	80
Asset Reset Process Stages	81
Manually Editing Asset Records	82
Restricting the Editing of Asset Values	82
Managing Assets	84
Asset Depreciation	84
Depreciating Assets for the Period	84
Generating Depreciation Schedule Values	86
Depreciation of Compound Assets	86
Depreciation of Assets with Zero and Negative Costs	88
Asset Disposal by Sale or Write-Off	89
Selling an Asset	89
Disposing or Writing-Off an Asset	90
Bulk Asset Disposal through CSV Import	91
Partial Disposal of an Asset	93
Asset Revaluation	93
Single Asset Revaluation	93
Multiple Asset Revaluation	95
Asset Split	96
Splitting an Asset	96
Splitting Assets in Bulk	97
Creating a Saved Search for Asset Split User Notes	98
Asset Transfer	99
Transferring an Asset	99
Transferring Multiple Assets through CSV Import	101
Transferring Assets Across Subsidiaries	102
Transferring Assets Across Classes, Departments, or Locations	103

Transferring Assets Across Asset Types	103
Deleting Assets	104
Group Tax Depreciation	104
Create an Alternate Depreciation Method for Group Tax Depreciation	105
Define Assets for Group Tax Depreciation	105
Create a Group Master Record for Group Tax Depreciation	105
Viewing and Approving Custom Journal Entries	106
Asset Reports	107
Asset Register Report	107
Asset Summary Report	108
Depreciation Schedule Report (Net Book Value and Period Depreciation)	109
Depreciation Monthly Report	110
Asset Listing Report (Anlagenspiegel)	110
Schedule 16 Reports	111
Asset Report Generation	111
Generating Fixed Asset Reports	112
Exporting Asset Reports to an Excel File	114
Fixed Assets Report Template	114
Customizing the Fixed Assets Report Template through the User Interface (UI)	114
Customizing the Fixed Assets Report XML Template	116
Viewing Fixed Asset Reports	121
Fixed Assets Saved Searches	122
Standard Fixed Asset Saved Searches	122
Additional Fixed Asset Saved Searches	122
Lease Accounting Reports	123
Lease Liability Detail Report	123
Right-of-Use Asset Listing Report	123
Short Term Lease Liability Report	124
Long Term Lease Liability Report	124
Managing Fixed Assets Scripts	125
Fixed Assets Management Script Priority	125
Prerequisites for Prioritizing FAM Scripts	125
Setting a Priority for FAM Scripts	125
Changing the Scheduled Script Runtime	126
Updating Script Deployment Settings for Suitelets Available Without Login	126
Running the Migration Script to Update the Fixed Assets Management SuiteApp	127
Fixed Asset Error Recovery Script	127
Modifying the Script Deployment to Create Summary Records	127
Modifying the Script Deployment to Update Asset Values	128
Background Processing of Fixed Assets	128
Process Status Page	128
Process Stage Details	130
Process List	130
Fixed Assets Custom Plug-In	131
Scheduled Server Scripts for Controlling Asset Transactions	131
Viewing Script Error Notification Settings for Fixed Assets Management	131
Multi-Book Accounting for Fixed Assets Management	132
Setting Up Multi-Book Accounting for Fixed Assets Management	132
Prerequisites for Fixed Assets Multi-Book Accounting	132
Roles and Permissions for Fixed Assets Multi-Book Accounting	133
Updating Depreciation History Records	133
Managing Assets in Multiple Books	134
Defining Asset Accounts and Values for Multiple Books	135
Assets and Accounting Books in Multi-Book Accounting	136
Asset Proposal	137

Running Depreciation on an Accounting Book	138
Transferring Fixed Assets Within Multi-Book Accounting	138
Revaluing an Asset in Multiple Books	139
Disposing an Asset in Multiple Books	139
Splitting an Asset in Multiple Books	140
Fixed Assets Lease Accounting	141
FAM Lease Accounting Prerequisites	141
Setting up Permissions for Lease Accounting	141
Setting Up General Ledger Accounts for Lease Accounting	142
Creating a Lease Record	142
Creating a Lease Record Manually	143
Importing Lease Records	145
Posting Reference Subtab (Lease Accounting)	146
Accounting Books Subtab (Lease Accounting)	146
Lease Amortization Schedule Subtab	146
Adding Lease Payments	147
Adding Lease Payments through the Lease Amortization Schedule Subtab	147
Adding or Updating Lease Payments through CSV Import	148
Generating the Lease Amortization Schedule	150
Lease Journal Entries	150
Creating a Lease Journal Entry	150
Reversing a Lease Journal	150
Recording Lease Interest	151
Lease Asset Proposal and Generation	152
Initial Measurement of the Right-of-Use Asset	152
Re-measurement of the Right-of-Use Asset	152
Migrating Existing Lease Details	153
Lease Record Modification	153
Modifying Lease Records	154
Processes Triggered by Lease Modifications	154
Calculating the Lease Modification Adjustment	155
Viewing Lease Modification Details	156

Fixed Assets Management Overview

The NetSuite Fixed Assets Management SuiteApp provides automated management of fixed assets acquisition, depreciation, revaluation, and retirement, as well as maintenance schedules and insurance. You can import new and mid-life assets into NetSuite to track their depreciation, including the depreciation history of mid-life assets. New asset records can also be created manually or from purchases, expenses, and inventory transfers in NetSuite.

Watch the following video for a brief overview of the features available in the Fixed Assets Management SuiteApp:



Fixed assets, as opposed to current assets, are assets with a remaining useful life of over a year. Following the accruals principal, fixed assets are shown on the balance sheet, but their value is depreciated and treated as an expense in the P&L (profit and loss) account for each year of their life.

An asset is any equipment or resource that needs depreciation, or one that requires insurance, leasing, maintenance, or custom details to be recorded. Businesses require accurate tracking, control, and depreciation of assets. The Fixed Assets Management SuiteApp provides a single source of information for everything relating to that asset.

Because of its flexibility, the Fixed Assets Management SuiteApp can be used by many types of businesses, and support a various assets and depreciation methods. Aside from supporting the standard depreciation methods—Straight Line, Fixed Declining, Sum of Years Digits, and Asset Usage—the SuiteApp also supports user-defined depreciation methods which can be linked together.

The ability to categorize assets into asset types in setup, and to provide defaults for the assets, makes asset creation, depreciation, and retirement manageable.

After defining the asset ledger accounts, you can automatically propose or create fixed assets by posting the originating document. For example, posting a purchase bill for a new asset will automatically ensure that asset is proposed for creation within the Fixed Assets Management system, along with all the applicable information from that bill.

The system enables you to manage non depreciating assets such as mobile phones, software, and hired plant or machinery. This is useful for tracking employee ownership of items, and for tracking insurance and maintenance schedules of assets.

The Fixed Assets Management SuiteApp automatically updates your account whenever bug fixes, new features, and other improvements in the bundle become available. For more information, see [Installing the Fixed Assets Management SuiteApp](#).

After installing the NetSuite Fixed Assets Management SuiteApp, read the following topics to complete additional setup tasks:

- [Making the Fixed Assets Tab Available to Custom Roles](#)
- [Setting Fixed Assets Management Permission Levels](#)
- [Setting Up the Fixed Assets Management System](#)
- See [General Ledger Accounts for Fixed Assets Management](#) for details on defining accounts to be used.
- See [Asset Transfer Accounts](#) for details on setting up asset transfer accounts.
- See [Depreciation Methods](#) for details on setting up depreciation methods.
- See [Alternate Methods \(Tax Depreciation Methods\)](#) for details on setting up alternate methods.
- See [FAM Asset Types](#) for details on creating asset types.

To migrate fixed asset data from your previous system to NetSuite, see [Creating Asset Records through CSV Import](#).

To learn how you can create and update asset records, read the following topics:

- [Creating Asset Records Manually](#)
- [Creating Asset Records from Transactions](#)

To learn how to manage depreciation, read the following topics in [Managing Assets](#):

- [Asset Depreciation](#)
- [Asset Disposal by Sale or Write-Off](#)
- [Partial Disposal of an Asset](#)
- [Asset Revaluation](#)
- [Asset Split](#)
- [Asset Transfer](#)
- [Fixed Asset Error Recovery Script](#)

To use saved searches and reporting features for fixed assets, read the following topics:

- [Fixed Assets Saved Searches](#)
- [Asset Reports](#)

To understand fixed asset background processing and error messages, see [Background Processing of Fixed Assets](#).

Installing the Fixed Assets Management SuiteApp

To successfully install and setup Fixed Assets Management for your business needs, first prepare your NetSuite account by enabling the required features and then proceeding with the SuiteApp installation. Read the following topics for detailed instructions:

- [Fixed Assets Management Overview](#)
- [Fixed Assets Management SuiteApp Prerequisites](#)
- [Fixed Assets Management SuiteApp Installation](#)

Note: For best results, consider having SuiteConsulting Professional Services implement and customize NetSuite for your unique business requirements. Contact your NetSuite sales representative for more information.

Fixed Assets Management SuiteApp Prerequisites

Before you install the Fixed Assets Management SuiteApp, you'll need to enable additional features in your NetSuite account.

To enable required features:

1. Go to Setup > Company > Enable Features.
2. On the SuiteCloud subtab, check the box for the following features:
 - Custom Records
 - Custom Transactions
 - Client SuiteScript
 - Server SuiteScript
3. On the CRM subtab, under Marketing, check the **Online Forms** box.
4. Click **Save**.

Fixed Assets Management SuiteApp Installation

For information about installing SuiteApps, see the help topic [Installing a Bundle](#).

Use the following information to install the Fixed Assets Management SuiteApp:

- **Bundle Name:** Fixed Assets Management
- **Bundle ID:** 508242

Note: If the Install button isn't available, this SuiteApp may not have been shared with your account. To get access to the SuiteApp, contact NetSuite Customer Support.

The Fixed Assets Management SuiteApp supports all the languages that NetSuite offers. For more information, see the help topic [Choosing a Language for Your NetSuite User Interface](#).

Making the Fixed Assets Tab Available to Custom Roles

The Fixed Assets Management SuiteApp creates a custom center tab named Fixed Assets that contains links to all Fixed Asset custom records and suitelets (custom pages). The Fixed Assets tab is applied to the Classic Center and Accounting Center.

To view the Fixed Assets tab:

1. Go to Customization > Centers and Tabs > Center Tabs and click the **Fixed Assets** link to view the setup of this custom tab.
2. Use one of these options to make the Fixed Assets tab visible to custom roles:
 - Go to Home > Set Preferences > Appearance tab. Check **Use Classic Interface** to see the tabs in NetSuite shown as the Administrator role displays them.
When users enable this option, they see the tabs that are relevant to their role and can access the application like an administrator.
 - Create a new custom Center tab for the Accounting Center (or other center). On this tab, you can provide the desired links for each role to the Fixed Asset custom records and pages. For example, you might want to remove the set up links for most roles and use them only for Administrators.

Setting Fixed Assets Management Permission Levels

If you have custom roles, ensure they have the necessary permissions to access the Fixed Assets Management SuiteApp and its custom record entries. For information about customizing roles, see the help topic [Customizing or Creating NetSuite Roles](#).

The Fixed Assets Management SuiteApp provides a default role, called Fixed Assets Management, which has all the permissions required to use the SuiteApp. You can use this role as a template when creating or modifying existing roles for Fixed Assets Management access.

If you want to add permissions to custom roles that you're using, compare them to the Fixed Assets Management role. Edit your custom role as needed to match the permissions of the Fixed Assets Management role. Go to Setup > Users/Roles > Show Role Differences to open the Show Permission Differences Between Roles page. For more information, see the help topic [Showing Role Permission Differences](#).

Record Permissions for Fixed Assets Management

To set permissions for a role, go to the Permissions subtab in Setup > Users/Roles > Manage Roles.

Permissions are divided into four subtabs: Transactions, Reports, Lists, Setup, and Custom Record.

- To add a permission, do one of the following:
 - Click a line in the list, select a permission, and then click **Insert**.
 - Click **Add Row** at the bottom of the list, select a permission, and then click **Add**.
- To remove a permission, select it from the list, and then click **Remove**.
- To set the level of access for a permission, click a line in the list, and then select the level of access from the Level column. For information about these access levels, see the help topic [Access Levels for Permissions](#).

- You can limit a role's access to custom records by selecting value in the Restrict column. Each custom record permission provides access to a custom record type.
 - **Viewing and Editing** — Restricts the role to view or edit only the records (of this type) that they or their subordinates created.
 - **Editing Only** — Restricts the role to edit only the records (of this type) that they or their subordinates created. They can view all records of this type.

Leave this column blank to give the role view and edit access to all records of this type.

You can use a mass update to add, remove, or change the level of a permission for multiple roles at the same time. For more information, see the help topic [Mass Updating a Permission on Custom Roles](#).

The following table lists the record permissions required to use the Fixed Assets Management features.

Subtab	Permission	Level	Notes
Transactions	Make Journal Entry	Full	Processes such as Depreciation, Revaluation and Disposal run with client user permissions and need to create Journals
Transactions	Bill	View	
Transactions	Find Transaction	Full	
Transactions	Invoice	Full	
Custom Record	FAM Alternate Depreciation	Full	
Custom Record	FAM Alternate Methods	Full	
Custom Record	FAM Asset	Full	
Custom Record	FAM Asset Proposal	Full	
Custom Record	FAM Asset Reset Data	Create	
Custom Record	FAM Asset Transfer Accounts	Full	
Custom Record	FAM Asset Type	Full	
Custom Record	FAM Asset Usage	Full	
Custom Record	FAM Asset Values	Full	
Custom Record	FAM Default Alt Depreciation	Full	
Custom Record	FAM Depreciation History	Full	
Custom Record	FAM Depreciation Method	Full	
Custom Record	FAM Last Proposal Dates	Full	
Custom Record	FAM Lifetimes	Full	
Custom Record	FAM Process	Full	

Subtab	Permission	Level	Notes
Custom Record	FAM Proposal Alt Depreciation	Full	
Custom Record	FAM Repair & Maint Category	Full	
Custom Record	FAM Repair & Maint Sub A	Full	
Custom Record	FAM Repair & Maint Sub B	Full	
Custom Record	FAM System Setup	Full	
Custom Record	FAM Transaction Field Map	Full	
Custom Record	BG Process Instance	Full	
Custom Record	BG Summary Record	Full	
Lists	Accounts	View	
Lists	Classes	View	
Lists	Currency	View	
Lists	Customers	View	
Lists	Departments	View	
Lists	Documents and Files	View	You must have read access to the FAM resource folder (src/resource) so that Suitelets load without issue. If you still encounter issues even with the Documents and Files permission, check that your role complies with the restrictions (SCDL or group restrictions) applied on the FAM resource folder.
Lists	Items	View	
Lists	Locations	View	
Lists	Perform Search	View	
Lists	Projects	View	
Lists	Subsidiaries	View	
Lists	Tax Items	Create	
Setup	Accounting Book	View	
Setup	Manage Accounting Periods	View	
Setup	Setup Company	View	

Form Permissions for Fixed Assets Management

On the Role record, click the **Forms** subtab, and then click **Custom Record**. Ensure the required Fixed Assets Management forms are enabled. Check the box in the Enabled column next to the forms you want

to make available to users with this role. The following table lists the form permissions required to use the Fixed Assets Management features.

Type	Name	Notes
FAM Alternate Depreciation	Standard FAM Alternate Depreciation Form	
FAM Default Alt Depreciation	Standard FAM Default Alt Depreciation Form	
FAM Alternate Depreciation	Standard FAM Alternate Depreciation Form	
FAM Alternate Methods	Standard FAM Alternate Methods Form	
FAM Asset	FAM Asset Form	Make preferred form for all roles except administrators.
FAM Asset	Standard FAM Asset Form	Only required for Administrators or users who will import asset records
FAM Asset Proposal	FAM Asset Proposal	Make preferred form for all roles except administrators.
FAM Asset Proposal	Standard FAM Asset Proposal Form	
FAM Asset Transfer Accounts	Standard FAM Asset Transfer Accounts Form	
FAM Asset Type	Standard FAM Asset Type Form	
FAM Asset Usage	Standard FAM Asset Usage Form	
FAM Asset Values	Standard FAM Asset Values Form	
FAM Depreciation History	Custom FAM Depreciation History Form	Make preferred form for all roles except administrators.
FAM Depreciation History	Standard FAM Depreciation History Form	
FAM Depreciation Method	FAM Depreciation Method	Make preferred form for all roles except administrators.
FAM Depreciation Method	Standard FAM Depreciation Method Form	
FAM Last Proposal Dates	Standard FAM Last Proposal Dates Form	
FAM Lifetimes	Standard FAM Lifetimes Form	
FAM Process	Standard FAM Process Form	
FAM Proposal Alt Depreciation	Standard FAM Proposal Alt Depreciation Form	
FAM Recent Diagnosis	Standard FAM Recent Diagnosis Form	This permission enables you to view the FAM Diagnostics portlet.
FAM Repair & Maint Category	Standard FAM Repair & Maint Category Form	

Type	Name	Notes
FAM Repair & Maint Sub A	Standard FAM Repair & Maint Sub A Form	
FAM Repair & Maint Sub B	Standard FAM Repair & Maint Sub B Form	
FAM System Setup	Standard FAM System Setup Form	
FAM Transaction Field Map	Standard FAM Transaction Field Map Form	
BG Process Instance	Standard BG Process Instance Form	
BG Summary Records	Standard BG Summary Records Form	

Setting Up the Fixed Assets Management System

After installing the Fixed Assets Management SuiteApp, complete the following setup tasks:

- Set up the [General Ledger Accounts for Fixed Assets Management](#).
- Set up [Fixed Assets General Preferences](#), [Fixed Assets Report Preferences](#), [Fixed Assets Country Specific Preferences](#).
- Set up the [Asset Transfer Accounts](#).
- Set up the [FAM Diagnostics Portlet](#) to monitor the health of your FAM bundle, from your dashboard.
- Assign [Depreciation Methods](#) to an asset.
- Set up [Alternate Methods \(Tax Depreciation Methods\)](#).
- Define [FAM Asset Types](#).
- Migrate fixed asset data from your previous system. See [Creating Asset Records through CSV Import](#).
- If you want to apply custom segments to your FAM records, see [Custom Segments and Custom Fields in Fixed Assets Management Records and Transactions](#).

General Ledger Accounts for Fixed Assets Management

The Fixed Assets Management SuiteApp provides predefined general ledger accounts for fixed assets, but you can set up your existing general ledger accounts to be used with the SuiteApp.

When you install the Fixed Assets Management SuiteApp, the following accounts are already defined:

FAM Account Field (for Assets, Asset Types, and Asset Proposals)	Account Types
Asset Account	Fixed Asset
Depreciation Account	Fixed Asset
Depreciation Charge Account	Deferred Expense, Expense, Other Expense
Write Off Account	Fixed Asset, Deferred Expense, Expense, Other Expense
Write Down Account	Fixed Asset, Deferred Expense, Expense, Other Expense
Disposal Cost Account	Expense, Income, Other Expense, Other Income

Setting Up General Ledger Accounts to be Included in Fixed Assets Management

If you have existing general ledger accounts, you can edit your accounts to make them available for selection on Assets, Asset Types, and Asset Proposals.

To set up general ledger accounts to be included in Fixed Assets Management:

1. Go to Lists > Accounting > Accounts.
2. Click the **Edit** link of the account that you want to set up.
3. In the **Show in Fixed Assets Management** field, select the Fixed Assets Management accounts. To select multiple accounts, hold down the CTRL key and click on the accounts.
 - Asset Account
 - Depreciation Account
 - Depreciation Charge Account
 - Write Off Account
 - Write Down Account
 - Disposal Cost Account
4. Click **Save**.

Verifying Successful Account Definition in Asset Type and Asset Records

To verify successful account definition in Asset Type and Asset records:

1. Go to Fixed Assets > Setup > Asset Types > New.
2. On the **Accounts** subtab, verify that the account you defined is available in the dropdown menu of the following fields (if applicable to the account you defined):
 - Asset Type Asset Account
 - Asset Type Depreciation Account
 - Asset Type Depreciation Charge Account
 - Asset Type Write Off Account
 - Asset Type Write Down Account
 - Asset Type Disposal Cost Account
3. Go to Fixed Assets > Lists > Assets > New.
4. On the **Accounts** subtab, verify that the account you defined is available in the dropdown menu of the following fields (if applicable to the account you defined):
 - Asset Account
 - Depreciation Account
 - Depreciation Charge Account
 - Write Off Account
 - Write Down Account
 - Disposal Cost Account

Fixed Assets General Preferences

You can customize Fixed Assets Management to ensure that fixed assets are managed according to your business requirements..

To set up Fixed Assets Management general preferences:

1. Go to Fixed Assets > Setup > System Setup.

Note: If the system detects that a reset is needed, you can click **Reset Asset Values** to start the process. For more information, see [Triggering the Asset Reset Process](#). If you want to trigger the precompute process, click **Precompute Depreciation Values**. For more information, see [Generating Depreciation Schedule Values](#).

2. To configure asset and account period preferences, click the **Asset Setup** subtab. For more information, see [FAM Asset Setup Subtab](#).
3. To set preferences for asset depreciation, proposal and creation, transfer, disposal, and revaluation, click the **Asset Management** subtab. For more information, see [FAM Asset Management Subtab](#).
4. To set up lease preferences, click the **Lease Setup** subtab. For more information, see [FAM Lease Setup Subtab](#).
5. Click **Save**.

FAM Asset Setup Subtab

The Asset Setup subtab lets you configure essential asset and accounting period preferences for Fixed Assets Management. The following table describes the available preferences for this subtab:

Asset	
Run Server Scripts on CSV Import	Clear this box if you are importing records of mid-life assets. Important: Selecting this preference can enable the overriding of some values from the import file depending on the setting for a CSV import preference. See Creating Asset Records through CSV Import for the import guidelines.
Allow Asset Value Editing	Check this box to give administrators full permission to edit values in asset records. Note: Asset records cannot be edited if this box isn't checked. See Restricting the Editing of Asset Values for a list of fields that cannot be edited.
Allow Negative Asset Cost	Check this box to enable administrators (and other roles with permission to edit asset values) to enter negative values—for original cost, current cost, and residual value—in asset records. Important: You must check the Allow Asset Value Editing box before you can select Allow Negative Asset Cost. When you enter negative values in asset records, you cannot clear the Allow Asset Value Editing or Allow Negative Asset Cost box to disable either preference. The SuiteApp only supports asset depreciation for assets with negative costs. Running Depreciation Schedule Reports for assets with negative costs returns incorrect data.
User Roles	Select additional roles from this field to enable other users to edit asset values.

Asset	
	 Note: Checking the Allow Asset Value Editing box enables the User Roles list. To select two or more roles, press and hold down the CTRL key and click each role.

Accounting Period	
Post to Next Open Period if AP is Locked	Check this box to post to the next open period if AP is locked. Clear this box to post to the current period if AP is locked.
Post to Next Open Period if AR is Locked	Check this box to post to the next open period if AR is locked. Clear this box to post to the current period if AR is locked.

FAM Asset Management Subtab

The Asset Management subtab provides options for managing the lifecycle of assets, from proposal and creation through depreciation, transfer, disposal, and revaluation. The following table describes the available preferences for this subtab:

Proposal / Creation	
Restrict Ability to Reject Proposals	Check this box to display the Reject Proposals button on the Asset Proposal page only for the Administrator role.
Propose Approved Transactions Only	Check this box to propose assets only from approved transactions. Clear this box to enable automatic proposal of assets from all new transactions posted against the fixed asset general ledger accounts regardless of transaction status (for example, approved or pending approval).
Use Lease Term as Asset Life	For assets generated from a lease, check this box to set the lease term as the asset life (AL).

Depreciation	
Summarize Journals By	Choose any of the following options: ■ Parent—Roll up values of sub-assets to parent and create one journal entry to include parent and child values per period. ■ Sub-Category—Roll up values to sub-category and create one journal entry per sub-category per period. ■ Asset Type—Roll up values by asset type.  Note: Changing this preference will delete any existing forecasts. The depreciation scheduled script will automatically create new forecast values. The updated values will be effective only after each asset's Last Depreciation Date. The system creates another journal entry to group assets in the following instances: ■ If the parent and child values, Repair & Maintenance categories, and subcategories for an asset are not properly set up ■ If summarization for the asset is not defined
Allow Future-dated Depreciation	Check this box to allow depreciation of assets up to a depreciation period date beyond that of the current period. Clear this box to depreciate assets to the current period only.

Depreciation	
Use Accounting Period Dates for Depreciation	Check this box to use accounting period dates for the depreciation journal entry. This preference is applicable if you're not using calendar months for the Period Format. When not enabled, the depreciation uses calendar months.  Note: The Fixed Assets Management SuiteApp does not support the Multiple Calendar feature and relies on the standard calendar to process depreciation. Using a custom fiscal calendar with FAM processes may result in data inaccuracies.
Transfer	
Post on Location Change Post on Class Change Post on Department Change	To transfer the entire asset—by disposing it under the old field value and posting current values under the new one—when the location, class, or department changes, check any of these boxes. Clear these boxes to apply these preferences to future transactions. Changing the subsidiary always transfers the asset and generates postings. For more information, see Asset Transfer Accounts.  Note: The system doesn't create a journal entry for transfers to a class, department, or location, if the original transfer value is null.
Disposal	
Write-down using Depreciation Account	Check this box to post write-down amounts to the depreciation account. Clear the box to post write-down amounts to the asset account.
Revaluation	
Asset Disposal Invoice Form (internal id)	Enter the Internal ID of the preferred invoice form to use when creating a sales invoice for an asset sale. Leave the field blank to use the default preferred form.

FAM Lease Setup Subtab

The Lease Setup subtab lets you manage options and permissions for maintaining and modifying lease records within Fixed Assets Management. The following table describes the available preferences for this subtab:

Lease	
Allow Lease Modifications	Check this box to edit lease records with an Asset Created status.
User Roles	Select which roles can edit lease records.  Note: You can select user roles when you check the Allow Lease Modification box. To select multiple roles, hold down the CTRL key while clicking on each role.

Summarizing Journal Entries

The Summarize Journals feature speeds up journal writing and improves asset depreciation performance. You can summarize journal entries using these options:

- **Parent** – Roll up sub-asset values to the parent, creating one journal entry per period with both parent and child values.
- **Sub-Category** – Roll up values to the sub-category, creating one journal entry per sub-category per period.
- **Asset Type** – Roll up values by asset type.

If parent and child values, Repair & Maintenance categories, and Subcategories aren't properly set up for an asset, or if the summarization isn't defined, the system creates a separate journal entry to group these assets.



Important: FAM 3.0 no longer supports summarizing journal entries by **None**. Records that used this option in earlier versions will now use **Asset Type** when you update the SuiteApp.

Summary Record

The summary record totals the depreciation amount and is stored with the journal entry. The selected option for summarizing journal entries defines the asset's category in the summary record.

A journal entry can hold up to 250 summary records. If you have over 250 summary records, another journal entry is created to hold the rest.

Depreciation Posting Reference

Previously, journal entries were sourced from the depreciation history record, with a link stored in the **Posting Reference** field. Starting with FAM 3.0, journal entries are generated from the summary record, with the journal entry information stored in the **Depreciation Posting Reference** field on the Depreciation History Record.

For compatibility, existing depreciation histories will continue to use the **Posting Reference** field.



Note: The system searches for depreciation history records (DHR) to record in the next open period. For example, if the current period is December, the system retrieves DHRs for December and prior closed periods. These DHRs are then written into journal entries in any order.



Important: When you run depreciation after upgrading to FAM 3.0, the SuiteApp uses the **Depreciation Posting Reference** field to store the depreciation journal entry.

Fixed Assets Report Preferences

To set up Fixed Assets Management report preferences:

1. Go to Fixed Assets > Setup > System Setup.
2. On the Reports tab, set the report preferences for the Fixed Assets Management system:

Setting	Description
Folder to Use for Reporting (Internal id)	Enter the internal ID of the file cabinet folder where reports are saved.

Setting	Description
	 Note: To display internal IDs, check the Show Internal IDs box under the General subtab at Home > Set Preferences.
Allow Administrators to View All Reports	Check this box to let administrators view reports generated by other users.
Preferred Asset Register Template	Select a report template for Asset Register, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_AR_ prefix.
Preferred Asset Summary Template	Select a report template for Asset Summary, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_AS_ prefix.
Preferred Depreciation Schedule NBV Template	Select a report template for Depreciation Schedule NBV, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_DS_ prefix.
Preferred Depreciation Schedule PD Template	Select a report template for Depreciation Schedule PD, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_DS_ prefix.
Preferred Depreciation Monthly Template	Select a report template for Depreciation Monthly, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_DM_ prefix.
Preferred Asset Listing Template	Select a report template for Asset Listing, or leave blank to use the default template.  Note: The list only shows report templates with the FAM_AL_ prefix.

3. Click **Save**.

Fixed Assets Country Specific Preferences

To set up Fixed Assets Management country specific preferences:

1. Go to Fixed Assets > Setup > System Setup.

2. On the Country Specific tab, set up preferences for Japan and France:

- In the Japan section, set the rounding method for Japanese currency with decimal values. Leave blank to use the round-off method.
 - **Round Off** - This option rounds down the decimal value to 0 if the value is 0.499 or less, and rounds up to 1 if the value is 0.5 or more.
 - **Round Down** - This option rounds down the decimal number to 0.
 - **Round Up** - This option rounds up the decimal number to 1.

The rounding method applies to both annual and monthly depreciation amounts.

This setting applies to assets using the Japanese currency in multicurrency accounts. For non-multicurrency accounts, this setting applies to all assets where the **Currency Locale** is **Japan (Japanese)**.



Note: Changing this preference resets all pre-computed depreciation history records in JPY currency.

- In the France section, set the following preferences for French accounts or subsidiaries:
 - **Enable Derogatory Depreciation** - check this box to enable derogatory depreciation for FAM Alternate Methods.
 - **Populate Memo Field on Journal Header** - Check this box to automatically populate the header memo on journal entries.

This preference is enabled by default.

3. Click **Save**.

FAM Diagnostics Portlet

The FAM Diagnostics portlet gives you an overview of your FAM bundle's health from the dashboard. It shows processes that need action, how to fix them, when they were last resolved, and who made the changes. You can also scan processes to check for issues that need fixing. The following processes are available in FAM Diagnostics:

- **Precompute Depreciation Values** — This process generates depreciation schedule values to optimize depreciation. Depreciation values are automatically generated for assets created from an asset proposal, but not for assets created manually or through CSV import.
- **Reset Asset Values** — Changes to the asset that affect the depreciation formula, such as changes to the asset life or cost, causes inaccuracies in the depreciation values. Run Asset Reset to delete outdated depreciation histories.
- **Check Missing Summaries** — A BG Summary record tracks depreciation histories with the same subsidiary, department, class, location, and currency. Depreciation won't proceed if the depreciation histories are missing a BG Summary record.
- **Check Missing Asset Values Record** — Depreciation values won't be generated for assets without an Asset Values record. This can happen in the following cases:
 - Assets are added through CSV import when server scripts aren't running.
 - Assets are modified to remove the associated Asset Values record.
 - The Asset Values record is deleted.
- **Check Missing Lease Contracts** — Lease payments may have missing contracts if they're added through CSV import when server scripts aren't running.

- **Check Missing DHRs without Associated Records** — Depreciation history records (DHRs) that aren't linked to an Asset or Asset Values record can cause issues during depreciation. DHRs may be orphaned in these scenarios:
 - Users manually delete the Asset or Asset Values record.
 - The DHR is modified outside of FAM transactions.

Note: FAM Diagnostics is available to the Administrator and Fixed Assets Manager roles by default. Other roles need the **FAM Recent Diagnosis** permission to view the FAM Diagnostics portlet. For more information, see [Form Permissions for Fixed Assets Management](#).

Setting Up FAM Diagnostics

To set up and use FAM Diagnostics

1. Add the FAM Diagnostics portlet to your dashboard:
 - a. From the NetSuite Home page, go to Personalize > SuiteApps.
 - b. Click or drag and drop **FAM Diagnostics** to your dashboard.
2. Click **Run Scan** to see which processes need your attention. The recommended actions are shown as links.

Process	Run Scan	Action
Precompute Depreciation Values	Checks for assets without depreciation schedule values.	Clicking Run Precompute generates depreciation schedule values for affected assets.
Reset Asset Values	Checks for assets that require a reset.	Clicking Run Asset Reset deletes stale depreciation histories.
Check Missing Summaries	Checks for depreciation histories without a BG Summary Record.	Clicking Check Missing Summaries creates a BG Summary Record for orphaned depreciation histories.
Check Missing Asset Values Record	Checks for assets without an Asset Values record.	Clicking Review Assets opens the Review Assistant where you can view, edit, or delete the assets. For more information, see Adding or Deleting Asset Values Using the Review Assistant .
Check Missing Lease Contracts	Checks for lease payment records without contracts.	Clicking Create Lease Contracts attaches a contract to lease payment records that don't have one.
Check DHRs without Associated Records	Checks for DHRs without associated records.	Clicking Resolve DHRs deletes the orphaned DHRs. If the DHRs are linked to a journal or summary record, the system opens the Review Assistant. You can review the DHR list, make changes if needed, and then delete the DHRs.

Note: The FAM Diagnostics portlet follows the date format set in the User Preferences page.

3. Click the link under the Action column to fix the issue.

Refresh the portlet to display the latest information. You can click **Run Scan** again to check for issues with the processes. Note that running the scan clears the **Last Remedied**, **On**, and **Last Remedied By** details. You can also schedule scans for each process. For more information, see [Scheduling a Diagnostic Scan](#).

Adding or Deleting Asset Values Using the Review Assistant

The FAM Diagnostics portlet checks for assets without an Asset Values record. Click **Review Assets** to open the Review Assistant and download a CSV file with the asset details. You can review and modify the assets in the file as needed. After uploading the file back to the Review Assistant, you can choose to delete or add asset values.

Review these guidelines before uploading your CSV file:

- If you are adding asset values, fill out all the columns in the CSV file. If you are deleting asset values, only the **Internal ID** column is required.
- Ensure that the dates and numbers in the CSV file match the format specified in the General Preferences page. Check the system date and number format in Setup > Company > General Preferences.
- If the CSV file has multiple entries with the same asset internal ID, the system processes them as follows:
 - Entries that fail the validation process are skipped.
 - If only one entry passes the validation process, it's processed normally. Otherwise, the system displays a duplicate error.
- If an asset in the CSV file already has an Asset Values record, the system doesn't process it.
- Ensure that your CSV file does not exceed 10 MB.

To add or delete asset values:

1. From the FAM Diagnostics portlet, click **Review Assets**.
2. On the Review Assistant — Step 1 screen, do the following:
 - a. Click **Download CSV** to save the list of assets with no asset values record.
 - b. Click **Next**.
3. On your computer, open the CSV file that you downloaded, and enter values in the following columns:
 - **Internal ID** — If this field is blank, enter the internal ID of the asset.
To display internal IDs, check the **Show Internal IDs** box under the General subtab at Home > Set Preferences.
 - **Current Net Book Value** — Enter the current net book value (NBV). The current NBV is calculated as the original cost minus accumulated depreciation and write-down amounts.
 - **Last Depreciation Period** — Enter the period number (within the asset's useful life) in which the asset was most recently depreciated.
 - **Last Depreciation Amount** — Enter the amount of the asset's most recent depreciation.
 - **Last Depreciation Date** — Enter the date of the asset's most recent depreciation.
 - **Prior Year NBV** — Enter the asset original cost if the transaction date is within the asset's acquisition year. Otherwise, enter the net book value as of the end of that year.
4. On the Review Assistant — Step 2 screen, do the following:
 - a. Click **Choose File**.
 - b. Select the CSV file that you updated in the previous step.
 - c. Click **Next**.
5. On the Review Assistant — Step 3 screen, do the following:

- a. Select the action to apply to the assets in the CSV file:
 - **Delete Assets** — Select this option to delete the assets.
 - **Add Asset Values** — Select this option to add asset values.
- b. Click **Finish**.
A popup window displays a confirmation message. Click **OK** to continue.

Deleting DHRs Using the Review Assistant

The FAM Diagnostics portlet can scan for depreciation history records (DHR) without Asset or Asset Values record. The system does not automatically delete DHRs if they are associated with a journal entry or BG summary record. Click **Resolve DHRs** in the portlet to open the Review Assistant and download a CSV file with details about these DHRs. You can review and modify the DHRs in the file before deleting them.

 **Note:** If the DHRs aren't linked to a journal entry or BG summary record, clicking **Resolve DHRs** triggers the process to delete them.

Before you upload the CSV file, review the following import guidelines:

- If you are modifying the downloaded CSV file, ensure that the **DHR Internal ID** field is included.
- If the DHR shouldn't be deleted, make sure its **Asset** or **Parent Asset Value** fields are populated. Don't populate the **Parent Asset Value** field if the DHR name is **dhr-default-name** or an internal ID.
- If you are deleting the DHR:
 - Make sure that the DHR with journals are accounted for. Deleting them can affect your FAM reports and cause inaccuracies when compared against non-FAM reports.
 - Check if journal adjustments are needed.
- Ensure that the dates you enter in the CSV file follow the format specified in the General Preferences page. Check the system date format in Setup > Company > General Preferences.
- Make sure that your CSV file does not exceed 10 MB.

To delete DHRs:

1. From the FAM Diagnostics portlet, click **Resolve DHRs**.
2. On the Review Assistant — Step 1 screen, do the following:
 - a. Click **Download CSV** to save the list of DHRs with a journal entry or BG summary record.
 - b. Click **Next**.
3. On your computer, open the CSV file that you downloaded in the previous step.
4. Review the DHR list, and remove the DHRs that shouldn't be deleted. Read the import guidelines above for more information.
5. On the Review Assistant — Step 2 screen, do the following:
 - a. Click **Choose File**.
 - b. Select the CSV file that you updated in the previous step.
 - c. Click **Finish**.
A popup window displays a notification message. Click **OK** to continue.

Scheduling a Diagnostic Scan

You can schedule a scan for each process in the FAM Diagnostic portlet. The system will automatically scan each process based on the schedule that you set.

To schedule a diagnostic scan:

1. Go to Fixed Assets > Setup > System Setup.
2. On the Diagnostics tab, set the schedule for running scans on each process.
 - **Daily** — Runs a scan at 3:00 AM everyday.
 - **Weekly** — Runs a scan at 3:00 AM every Wednesday.
 - **Monthly** — Runs a scan at 3:00 AM every 2nd day of the month.

The default schedule of each process is as follows:

- Precompute Depreciation Values: Weekly
- Reset Asset Values: Daily
- Check Missing Summaries: Weekly
- Check Missing Asset Values Record: Daily
- Check Missing Lease Contracts: Weekly
- Check DHRs without Associated Records: Monthly

3. Click **Save**.

Asset Transfer Accounts

The Fixed Assets Management SuiteApp supports multiple subsidiaries and lets you transfer assets between them.

To enable this intercompany functionality, you must define intercompany accounts on the Asset Transfer page. For each pair of subsidiaries involved in transfers, set up the transfer accounts for both the origin and destination subsidiaries.

When the subsidiary in an asset record is changed, the system creates journal entries to move the asset and its accumulated depreciation out of the balance sheet and into the origin transfer account. In the destination subsidiary, the asset's value is posted from the destination transfer account into the appropriate asset account. Previous depreciation amounts are not transferred to the destination subsidiary's ledger.

To set up an asset transfer account:

1. Go to Fixed Assets > Setup > Asset Transfer Accounts > New.
2. Enter values for the following fields:
 - **Origin Subsidiary** — Select the subsidiary transferring the asset.
 - **Destination Subsidiary** — Select the subsidiary receiving the asset.
 - **Origin Transfer Account** — Select the transfer (GL) account for the originating subsidiary.
 - **Destination Transfer Account** — Select the transfer (GL) account for the destination subsidiary.
3. Click **Save**.

FAM Asset Types

Before creating an asset record, you must first set up asset types. Each asset must be assigned an asset type, which defaults some of the asset variables (on creation of new assets) and groups assets in reports and during processing.

To create an asset type:

1. Go to Fixed Assets > Setup > Asset Types > New.
2. Provide values for the following fields:
 - **Name** – Enter a name for the asset type. For example, Furniture & Fixtures.
 - **Description** – Enter a general description for the asset type.
 - **Accounting Method** – Select the default depreciation method (formula) to use when creating assets of this type. This method determines how values are calculated before they're recorded in the accounting system.
 - **Residual Percentage** – Enter the percentage of the original cost which the asset will be worth, at the end of its lifetime. For example, if you buy an asset for \$1,000.00 and it's worth \$100.00 at the end of its life, the residual value percentage is 10%. Entering a residual value will always override the default value calculated from the percentage.
 - **Asset Lifetime** – Enter the expected lifetime of the asset, in multiples of the depreciation period.
 - **Operating Lease** – Check this box if you'll use this asset type for assets generated from an operating lease. Clear this box if you're setting up an asset type for a finance lease.



Note: When you set the asset type to operating lease, you can't change it back to a normal asset type. Other Methods will also be tagged as Operating Lease.
Setting the asset type to **Operating Lease** will auto-compute the Residual Value Percentage.

3. Enter values in the fields on each of the subtabs:
 - [Asset Type General Subtab](#)
 - [Asset Type Accounts Subtab](#)
 - [Asset Type Maintenance Subtab](#)
 - [Asset Type Other Methods Subtab](#)
4. Click **Save**.
After saving the record, the **Lifetimes** subtab becomes available.
5. Enter values in the [Asset Type Lifetimes Subtab](#).
6. Click **Save**.

Asset Type General Subtab

On the General subtab, enter values for the following fields:

- **Depreciation Active** – Select from the following options:
 - ☐ **True** — Select this option to make this asset type active and include it in depreciation.

- ❑ **False** — Select this option if you don't want to include this asset type in depreciation.
- ❑ **On Project Completion** — For assets related to a project, this option starts depreciation when the project is completed.

 **Note:** The Depreciation Start Date and the Acquisition History record become available only when the project is closed.

- **Include in Reports** – Check this box to include the asset type in the Asset Summary Report. All assets are included by default.
- **Revision Rules** – Controls how revisions (revaluation) affect the asset:
 - ❑ **Current Period** — The depreciation to date is recalculated using the new values, and the difference between the calculated and previously posted depreciation is posted in the current period.
 - ❑ **Remaining Life** — The revision only affects future depreciation calculations from this point on.
- **Depreciation Rules** – Select from the following options:
 - ❑ **Acquisition** – The asset is depreciated in the same period it's made active.
 - ❑ **Disposal** – The asset is depreciated in its final period.
 - ❑ **Pro-rata** – The asset depreciates for a partial month in both the acquisition and disposal periods, based on a 30-day month.

For example, if depreciation starts on June 18, 2011 and ends on September 17, 2011, you'll record 13 days of depreciation in the first depreciation period, and 17 days in the final depreciation period.

The following are examples of pro-rata depreciation when it starts on the last day of the month:

- If depreciation starts on the last day of a 30-day month (April 30) or of a 31-day month (January 31), depreciation is recorded for 1 day in the acquisition period, and 29 days in the disposal period.
- If depreciation starts on the last day of February, depreciation in the acquisition period is calculated for 1 day plus the number of days to make 30 days. The asset depreciates for the corresponding partial month in the disposal period. For example, if depreciation starts on February 28, 3 days (the 28th plus 2 days to make 30) of depreciation is recorded for the first depreciation period, and 27 days in the final depreciation period.
- ❑ **Mid-month** – If the Depreciation Start Date is in the first half of the month (for example, July 11), depreciation starts on the same month of the asset acquisition (July). If the Depreciation Start Date is in the second half of the month (for example, June 18), depreciation starts after the month of asset acquisition (July).
- **Depreciation Period** – Select whether the asset will be depreciated monthly or annually.
- **Custodian** – Select the default employee responsible for this asset type.
- **Supplier** – Enter the vendor that assets of this type are purchased from.
- **Disposal Item** – Select a non inventory item (for sale), to use on the sales invoice, when the asset is sold.

Asset Type Accounts Subtab

 **Note:** You must enter account values if the tax method is linked to an accounting book. For more information, see [Assets and Accounting Books in Multi-Book Accounting](#).

On the Accounts subtab, select accounts to post to for this asset type:

- **Asset Account** – Select the main asset cost account (balance sheet). When proposing new assets, the system searches for new transactions in this account.
- **Depreciation Account** – Select the account that tracks the accumulated depreciation (balance sheet).
- **Depreciation Charge Account** – Select the expense account for depreciation charges (period depreciation amount).
- **Write Off Account** – Select the account for the asset write-off expense.

 **Note:** This account can't be the same as the Inventory Asset account selected for an item.

- **Write Down Account** – Select the account for the asset write-down expense.
- **Disposal Cost Account** – Select the account for the asset disposal (sale) expenses.

The following account fields are available only if your account subsidiary is set to France.

- **Appropriations to Derogation Provisions Account** – Select the expense account for recording derogatory depreciation. This account will be used if the tax method amount is higher than the accounting method amount.
- **Derogation Provisions Written Back Account** – Select the income account for recording derogatory depreciation. This account will be used if the tax method amount is lower than the accounting method amount.
- **Derogation Provisions Account** – Select the account that tracks the accumulated depreciation.

Asset Type Maintenance Subtab

On the Maintenance subtab, enter maintenance information for this asset type:

- **Inspection** – Check this box if assets assigned to this asset type need inspections.
- **Inspection Period** – If assets need inspections, specify how often they should be inspected (in months).
- **Warranty** – Check this box if the assets are covered by a warranty agreement.
- **Warranty Period** – If the assets are under warranty, enter the warranty period for the assets in months.

Asset Type Other Methods Subtab

 **Note:** The Other Methods subtab is available on the Asset Type record when the asset type has been created.

On the Other Methods subtab, you can assign default alternate depreciation (for analysis only) to the asset, with different asset lifetimes and residual values. This lets you track tax or corporate reporting methods on the asset. These values are calculated automatically during asset depreciation but don't generate financial transactions.

To add an alternate depreciation method to an asset type:

1. Go to Fixed Assets > Setup > Asset Type.
2. Click the **View** or **Edit** link next to the asset type.
3. On the Other Methods subtab, click **New FAM Default Alt Depreciation**.

4. On the FAM Default Alt Depreciation page, select an **Accounting Book** and **Alternate Method**. The available methods include only those that you've set up in Fixed Assets > Setup > Alternate Methods.

When you select an Alternate Method, the other fields are automatically populated:

- **Depreciation Method** – Sourced from Alternate Method record.
- **Convention** – Sourced from Alternate Method record.

Averaging conventions determine how depreciation is handled in the first year of an asset's depreciation. You can only use conventions with alternate methods, and by default, it's set to None. If you depreciate monthly, you can use the **Mid-Month** convention. If you depreciate annually, you can use the **Half Year** and **Mid-Quarter** convention. If the convention is set to Mid-Quarter, the asset starts depreciating for half of the first quarter, regardless of when it came into service during that period.

 **Note:** If the Convention value is set to None, depreciation follows the depreciation rule selected in the parent asset record. For details on the depreciation rules, see [Asset Type General Subtab](#).

- **Asset Life** – Sourced from Alternate Method record.
- **Financial Year Start** – Sourced from Alternate Method record.
- **Period Convention** – Sourced from Alternate Method record.
- **Depreciation Period** – Sourced from Depreciation Method record.
- **Subsidiary** – Sourced from the Alternate Method record.
- **Residual Percentage** – Must be entered in the Other Methods of the Asset Type.

5. Click **Save**.

Asset Type Lifetimes Subtab

On the Lifetimes subtab, click **New FAM Lifetimes** to add location-specific defaults for the asset type. This sets the Asset Lifetimes for the main (accounting) method based on the asset location.

Depreciation Methods

In the Fixed Assets Management SuiteApp, each asset must be assigned a depreciation method so that NetSuite can calculate its depreciation. You can link depreciation methods, so an asset uses one method for the first part of its life and then switches to a different method for the remaining lifetime.

The Fixed Assets Management SuiteApp lets you keep separate book depreciation and tax depreciation calculations. Book (accounting) depreciation of fixed assets is linked to journal postings and transactions in NetSuite. You can use any preconfigured depreciation method or create a new one.

 **Note:** The Fixed Assets Management SuiteApp doesn't support the **Multiple Calendar** feature and uses the standard calendar for depreciation. Using a custom fiscal calendar with FAM processes can cause data inaccuracies.

For more information, read the following topics:

- [Preconfigured Depreciation Methods](#)
- [Creating a New Depreciation Method](#)

■ Depreciation Formula

For information about creating and using tax depreciation methods, see [Alternate Methods \(Tax Depreciation Methods\)](#).

Preconfigured Depreciation Methods

The Fixed Assets Management SuiteApp automatically sets up some of the most common depreciation methods upon installation.

To view the preconfigured depreciation methods, go to Fixed Assets > Setup > Depreciation Methods. The Depreciation Method List shows the depreciation method name, description, and formula. The following depreciation methods are available:

- 150DB
- 200DB
- 250DB
- 25% Reducing Balance
- 4–4–5 Calendar Depreciation
- Asset Usage
- Capital Allowance Year 1
- Capital Allowance Year N
- Fixed Declining
- Straight Line
- Straight Line Remaining
- Sum of Years/Straight Line
- Sum of Years Digits
- Zero Depreciation

Nordic Countries and Benelux Methods

The following depreciation methods, specific for Nordic countries and Benelux, are also available:

- 30% Declining Balance
- 25% Declining Balance
- 24% Declining Balance
- 20% Declining Balance to 12% Declining Balance
- 20% Declining Balance
- 15% Declining Balance
- 14% Declining Balance
- 12% Declining Balance
- 10% Declining Balance
- 6% Declining Balance
- 4% Declining Balance

- 2% Declining Balance

Japan Depreciation Methods

The following depreciation methods, specific for Japan, are also available:

Note: The Final Period Convention for Japan depreciation methods is set to **Value Based** to extend the depreciation beyond the asset's life. Assets are marked **Fully Depreciated** if the Current Net Book Value equals 1 JPY. This doesn't apply to Japan Special Depreciation.

- Japan Straight Line
- Japan 250% Declining Balance
- Japan 200% Declining Balance
- Japan Old Straight Line
- Japan Old Declining Balance
- Japan Special Depreciation

For Japan depreciation methods, you must set the Residual Value to 1 JPY on your asset record to ensure the depreciation amount is calculated correctly. When calculating depreciation, the residual value is deducted from the last year's depreciation amount. If the Depreciation Rule is set to **Pro-rata**, asset's won't depreciate until the end of their life. Instead, the asset continues to depreciate until it reaches its residual value.

Note: You can use annual depreciation methods, like 150DB and 200DB, to generate depreciation journal entries. For example, you can create asset types with 150DB and 200DB as the default accounting method, which will be carried over when an asset is created.

Some of these methods are described in more detail in the following topics.

Asset Usage (Asset Activity) Depreciation Method

Usage-based depreciation methods aren't based on time, but on a level of activity. This could be miles driven for a vehicle, or a cycle count for a machine. When the asset is acquired, you estimate its life based on this activity level. Assume a vehicle is expected to go 50,000 miles in its lifetime. You'd calculate the per-mile depreciation rate as:

$$(\$17,000 \text{ cost} - \$2,000 \text{ salvage value}) / 50,000 \text{ miles} = \$0.30 \text{ per mile}$$

Each period, the depreciation expense is then calculated by multiplying the rate by the actual activity level.

Calculating Units-of-Activity Depletion:

- **Depreciable Cost divided by Units in Useful Life = Per Unit Depreciation**
- **Per-Unit Depreciation x Units During Period = Period Depreciation Expense**

If a truck with a depreciable cost of \$80,000 (\$90,000 cost, less \$10,000 estimated salvage value) and is expected to go 400,000 miles during its service life, the truck depreciates \$0.20 each mile (\$80,000 ÷ 400,000 miles = \$0.20 per mile). The following table shows how depreciation expense is assigned to the truck based on the miles driven each year.

Cost							\$90,000
------	--	--	--	--	--	--	----------

Year 1	110,000	×	\$0.20	=	\$22,000	\$22,000	68,000
Year 2	70,000	×	0.20	=	14,000	36,000	54,000
Year 3	90,000	×	0.20	=	18,000	54,000	36,000
Year 4	80,000	×	0.20	=	16,000	70,000	20,000
Year 5	50,000	×	0.20	=	10,000	80,000	10,000

Fixed Declining (Declining Balance) Depreciation Method

Accelerated depreciation methods applies a higher depreciation charge in the first year of an asset's life, with decreasing charges in the following years. This may better reflect the asset's expected benefit over its useful life. Many assets are most useful when they're new. One popular accelerated method is the fixed declining method.

For example, a business has an asset with \$1,000 original cost, \$100 salvage value, and five years (60 months) of useful life. The following table shows the fixed declining method of depreciation. Book Value at the start of the first year is the Original Cost of the asset. At any time, Book Value equals Original Cost minus Accumulated Depreciation.

Book Value = Original Cost - Accumulated Depreciation

The asset is depreciated until the Book Value equals the Salvage (or Scrap) Value.

Book Value	Depreciation Expense	Cumulative Depreciation	Period
\$1,000.00	0	0	0
\$962.35	\$37.65	\$37.65	1
\$926.12	\$36.23	\$73.88	2
\$891.25	\$34.87	\$108.75	3
\$857.69	\$33.56	\$142.31	4
\$825.40	\$32.29	\$174.60	5

Straight Line Depreciation Method

Straight-line depreciation is the simplest and most often used method. In straight-line depreciation, you estimate the asset's salvage value at the end of its useful life (the period during which it is used to generate revenues), then expense a portion of the original cost in equal amounts over that period. The residual value (or scrap value) is an estimate of the asset's value when you sell or dispose it. The residual value may be zero.

Annual Depreciation Expense = (Cost of Fixed Asset - Scrap Value) divided by Life span

For example, a vehicle that depreciates over five years, is purchased at a cost of US\$17,000, with a residual value of US\$2,000, will depreciate at US\$3,000 per year: $(\$17,000 - \$2,000) / 5 \text{ years} = \$3,000$ or $(\$17,000 - \$2,000) / 60 \text{ months} = \250 . In other words, you divide the depreciable cost of the asset by the number of years or months of its useful life.

Book Value - Beginning of Year	Depreciation Expense	Accumulated Depreciation	Book Value - End of Year
--------------------------------	----------------------	--------------------------	--------------------------

\$17,000 (Original Cost)	\$3,000	\$3,000	\$14,000
\$14,000	\$3,000	\$6,000	\$11,000
\$11,000	\$3,000	\$9,000	\$8,000
\$8,000	\$3,000	\$12,000	\$5,000
\$5,000	\$3,000	\$15,000	\$2,000 (Scrap Value)

Sum of Years' Digits Depreciation Method

Sum-of-Years' Digits is a depreciation method that results in a more accelerated write-off than straight line, but less than declining-balance method. With this method, annual depreciation is determined by multiplying the depreciable cost by a set of fractions.

- **Depreciable Cost = Original Cost - Salvage Value**
- **Book Value = Original Cost - Accumulated Depreciation**

Example: If an asset has original cost \$1,000, a useful life of five years and a salvage value of \$100, to calculate its depreciation schedule:

1. Determine Years' digits. Because the asset has a useful life of five years, the Years' digits are: 5, 4, 3, 2, and 1.
2. Calculate the sum of the digits. $5+4+3+2+1=15$

Depreciation rates are as follows:

- 5/15 for the 1st year
- 4/15 for the 2nd year
- 3/15 for the 3rd year
- 2/15 for the 4th year
- 1/15 for the 5th year

Book Value - Beg. of Year	Total Depreciable Cost	Depreciation Rate	Depreciation Expense	Accumulated Depreciation	Book Value - End of Year
\$1,000 (Original Cost)	\$900	5/15	\$300 (\$900 * 5/15)	\$300	\$700
\$700	\$900	4/15	\$240 (\$900 * 4/15)	\$540	\$460
\$460	\$900	3/15	\$180 (\$900 * 3/15)	\$720	\$280
\$280	\$900	2/15	\$120 (\$900 * 2/15)	\$840	\$160
\$160	\$900	1/15	\$60 (\$900 * 1/15)	\$900	\$100 (Scrap Value)

Straight Line Remaining Depreciation Method

This method works like the standard Straight Line method, but calculates depreciation based on the asset's value at the start of the method instead of its original cost. This method is used as a linked method following another method.

Sum of Years/Straight Line Depreciation Method

This method uses the Sum of Years' Digits for the first year, then switches to Straight Line for the rest of the depreciation lifetime.

150DB and 200DB Depreciation Method

These are standard Modified Accelerated Cost Recovery System (MACRS) methods defined for U.S. tax purposes.

Both methods use two calculations and applies the one with the higher value. The results in faster depreciation early in the asset's life. About one-third of the way through (for 150 DB), the system switches to the second method, transitioning from a curve depreciation pattern to a straight line method.

The formula for the 150DB method is:

$$((NB-RV)*(1.5/AL)) \sim ((NB-RV)/(AL-CP+1))$$

200DB is the same basic formula but will depreciate faster before switching to straight line:

$$((NB-RV)*(2/AL)) \sim ((NB-RV)/(AL-CP+1))$$

4-4-5 Calendar Depreciation Method

The 4-4-5 Calendar Depreciation method computes depreciation daily. When you enable the **Use Accounting Period Dates for Depreciation** preference in the Fixed Assets Setup page, the generated depreciation history record and journal entry will use the base period's end date.

Formula: $12*((CC-RV)/AL)*(DP/FY)$

DP/FY is a pro-rated calculation based on the number of days in a period. In a 4-4-5 calendar, this equals to 28 days for 4 weeks, 35 days for 5 weeks, and 36 days for the last period of the year.

Note: When using the 4-4-5 calendar depreciation method, make sure the asset's depreciation rule isn't set to pro-rata. The pro-rata rule computes depreciation based on a 30-day month. In a 4-4-5 calendar, the difference between the estimated days and the real period length changes the depreciation amount.

Period	Start Date	End Date	DP	YTD No. of Days
1	1/1/2015	1/28/2015	28	28
2	1/29/2015	2/25/2015	28	56
3	2/26/2015	4/1/2015	35	91
4	4/2/2015	4/29/2015	28	119
5	4/30/2015	5/27/2015	28	147
6	5/28/2015	7/1/2015	35	182
7	7/2/2015	7/29/2015	28	210
8	7/30/2015	8/26/2015	28	238
9	8/27/2015	9/30/2015	35	273

Period	Start Date	End Date	DP	YTD No. of Days
10	10/1/2015	10/28/2015	28	301
11	10/29/2015	11/25/2015	28	329
12	11/26/2015	12/31/2015	36	365

If you have an asset with a cost of 60,000, to be depreciated in 24 months, the following table shows the depreciation using the formula $12 * ((CC - RV) / AL) * (DP / FY)$. Note that FY is equivalent to 365.

Transaction Type	Date	Transaction Amount	Computation	Net Book Value
Depreciation	12/31/2018	2,958.90	$12 * ((60000 - 0) / 24) * (36 / 365)$	30,000.01
Depreciation	11/25/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	32,958.91
Depreciation	10/28/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	35,260.28
Depreciation	9/30/2018	2,876.71	$12 * ((60000 - 0) / 24) * (35 / 365)$	37,561.65
Depreciation	8/26/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	40,438.36
Depreciation	7/29/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	42,739.73
Depreciation	7/1/2018	2,876.71	$12 * ((60000 - 0) / 24) * (35 / 365)$	45,041.10
Depreciation	5/27/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	47,917.81
Depreciation	4/29/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	50,219.18
Depreciation	4/1/2018	2,876.71	$12 * ((60000 - 0) / 24) * (35 / 365)$	52,520.55
Depreciation	2/25/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	55,397.26
Depreciation	1/28/2018	2,301.37	$12 * ((60000 - 0) / 24) * (28 / 365)$	57,698.63
Acquisition	1/1/2018	60,000.00	$12 * ((60000 - 0) / 24) * (28 / 365)$	60,000.00

If your accounting period is set to **Calendar Months**, using the 4-4-5 Calendar Depreciation method will compute the monthly depreciation based on the number of days for a specific month.

Note: The 4-4-5 calendar depreciation doesn't support irregular accounting periods. If you want to create monthly depreciation history records and journal entries for an irregular accounting period, you must disable the **Use Accounting Period Date for Depreciation** preference in the FAM System Setup page. Also, when you turn off this preference, the depreciation uses calendar months. In the 4-4-5 depreciation formula, your DP should match the number of days in a specific month.

Japan Depreciation

The **Japan Old Straight Line** and **Japan Old Declining Balance** depreciation methods are used for assets purchased before April 1, 2007. When the asset value equals 5% of the original cost, it will be depreciated using the Straight Line method over 5 years (60 months) until the residual value equals 1 JPY.

The Japan Old Straight Line yearly depreciation limit is calculated as 90% of acquisition cost, multiplied by the depreciation rate.

Japan Special Depreciation



Important: If you are using the Japan Special Depreciation, you must enable Custom Transactions in your account. Go to Setup > Company > Enable Features > SuiteCloud. Under the SuiteGL section, check the **Custom Transactions** box.

Companies that meet the Japanese tax authority's requirements may apply a special depreciation to their assets. This method is an accelerated depreciation that's applied in addition to the asset's regular depreciation.

The special depreciation lets customers complete the depreciation process early and calculate their taxable income. Customers can apply the special depreciation to an asset within the first 3 years of its life.



Note: The special depreciation can be applied only to assets that use the Japan Straight Line, Japan 200 Declining Balance, and Japan 250 Declining Balance methods.

Adding Japan Special Depreciation Details

If your asset uses the Japan Straight Line or Japan Declining Balance depreciation methods, you can apply special depreciation. You can enter the special depreciation information from the Asset record page.



Note: Make sure that the **Custom Transactions** feature is enabled on your account.

To enter special depreciation details:

1. Go to Fixed Assets > Lists > Assets.
2. On the FAM Asset List page, click **Edit** next to the asset record where you want to add a special depreciation.



Note: Make sure the asset uses the Japan Straight Line, Japan 200 DB, or Japan 250 DB depreciation method.

3. On the Asset record, click **Special Depreciation**.
4. On the Special Depreciation page, enter values for the following fields:
 - **Date** - Enter the date of the special depreciation.
 - **Special Depreciation Rate** - Enter the percentage of acquisition cost allowed for the special depreciation limit.
 - **Special Depreciation Limit** - Enter the maximum special depreciation amount you can apply to the asset.
 - **Special Depreciation Amount** - Enter the special depreciation amount applied for the year.
 - **Applied Term 1** - Enter the article where the special depreciation is documented.
 - **Applied Term 2** - Enter the term where the special depreciation is documented.
 - **Special Depreciation Shortage** - This field shows the Special Depreciation Limit minus the Special Depreciation Amount. This field is available if you're entering special depreciation for the succeeding years.
5. Click **Save**.

The system uses the same account to record the special depreciation and regular depreciation. The special depreciation amount reduces the net book value.

A new DHR type called Special Depreciation is created, and the FAM Special Depreciation Entry is attached to it.

French Degressive Depreciation

Use degressive depreciation to calculate the French tax depreciation. The French Degressive depreciation method is similar to the declining balance method. This method uses Acquisition/Pro-rata as its depreciation rule. The first year's depreciation amount is prorated based on the number of months left for the fiscal year.

Formula: $PB * ((FC_RATE / AL) - (1 / (AL - CEIL(CP) + 1)))$

Depreciation Period: Annually

FC_RATE is the Fiscal Coefficient Rate set by the French government. You must manually enter the rate and convert it to decimal format. A new Degressive depreciation method must be created for each new rate.

In the Tax Method, set the values in these fields as follows:

- **Depreciation Rules:** Pro-rata
- **Depreciation Start Date:** 1st day of the Month

The annual depreciation is computed as:

$PB * \text{MAX}(\text{Degrassive Rate}, \text{Linear Rate})$

The following sample shows the expected depreciation values using the formula for degressive depreciation, with a Fiscal Coefficient Rate of 1.75.

Depreciation History •						
Edit	Transaction Type	Date	Transaction Amount	Net Book Value	Quantity	Posting Reference ^
Edit	Depreciation	12/31/2023	1,104.00	0.00	1	
Edit	Depreciation	12/31/2022	8,640.00	1,104.00	1	
Edit	Depreciation	12/31/2021	8,640.00	9,744.00	1	
Edit	Depreciation	12/31/2020	8,640.00	18,384.00	1	
Edit	Write-down	5/21/2020	4,800.00	43,200.00	1	
Edit	Depreciation	12/31/2019	8,640.00	27,024.00	1	
Edit	Depreciation	12/31/2018	7,536.00	35,664.00	1	
Edit	Acquisition	2/17/2018	48,000.00	48,000.00	1	

French Derogatory Depreciation

Derogatory depreciation is calculated from the difference between the tax and accounting depreciation amount over the asset's useful life. You can review the depreciation amount on the Review Derogatory Depreciation page. When the depreciation amount is finalized, the system generates the Derogatory Depreciation Histories. Corresponding derogatory depreciation journals are created to record the difference between the Accounting and Derogatory Tax methods.

Setting Up and Using the French Derogatory Depreciation Method

Before setting up your account to use the derogatory depreciation method, note the following prerequisites:

- Depreciation profiles for both the accounting and tax value models must have the same period frequency.
- The Depreciation Start Date for both Accounting and Tax Methods must be the same.

Note: Derogatory depreciation isn't available for mid-life assets.

Reviewing French Derogatory Depreciation

Important: You must run the precompute process to generate depreciation values for the derogatory depreciation.

You can review the derogatory depreciation amount from the Review Derogatory Depreciation page. This page displays information about the asset's tax method and the precomputed derogatory depreciation values based on the tax method.

To review the derogatory depreciation amount:

1. Go to Fixed Assets > Lists > Assets.
2. From the FAM Asset List page, click **View** or **Edit** next to the Asset record that you want to review.
3. On the Asset Record page, click the **Depreciation Histories** subtab, and then click the **Derogatory Depreciation** link.

Note: The Derogatory Depreciation link is only available for new assets.

4. On the Review Derogatory Depreciation page, you can compare the difference between the derogatory tax method and accounting method. The Depreciation Amount sublist shows the depreciation date, tax amount, asset amount, and the difference of the tax and accounting method.

Review Derogatory Depreciation History

More

Generate Derogatory Histories

Asset

FAM000296

Tax Method

Derogatory Depreciation

Appropriations to Derogatory Provisions

Dotations aux provisions réglementées (immobilisations)

Derogation Provisions Written Back

Reprises sur provisions réglementées (immobilisations)

Derogation Provisions Account

Acc. Dep-Machinery & Equipment

Depreciation Amount

Date	Tax Amount	Asset Amount	^ Difference
12/31/2024	0.00	102,222.22	-102,222.22
12/31/2023	0.00	200,000.00	-200,000.00
12/31/2022	170,370.38	200,000.00	-29,629.62
12/31/2021	333,333.33	200,000.00	133,333.33
12/31/2020	333,333.33	200,000.00	133,333.33
12/31/2019	162,962.96	97,777.78	65,185.18

5. Make sure to set the values for the following accounts:

- Appropriations to Derogation Provisions Account
- Derogation Provisions Written Back Account
- Derogation Provisions Account

These accounts record the derogatory depreciation amount. The derogatory histories can't be created if these accounts aren't set up. You can set up these accounts in the Default Alternate Method of the Asset Type or in the Accounts tab of the Tax Method.

6. Click **Generate Derogatory DHRs**.

You'll be redirected to the Process Status page where you can view the status of the Generate Derogatory DHRs process.

The derogatory journal entry is created together with the regular depreciation entries during asset depreciation. The system summarizes journal entries based on the **Summarize By** option in the FAM System Setup page.

The journal entry is linked to the Derogatory Depreciation DHR. When the depreciation is completed, you should have two journal entries:

- Regular depreciation – This entry is linked to the depreciation DHR for the accounting method.
- Derogatory journal – This entry is linked to the derogatory DHR for the tax method.

Depreciation History

More

Asset

FAM000296

Accounting Book

Primary Accounting Book

Method

Derogatory Depreciation

GL Posting

No

Depreciation Method

Straight Line Annual

Schedule

Depreciation History

Edit	Transaction Type	Date	Transaction Amount	Net Book Value	Quantity	Posting Reference
Edit	Depreciation	12/31/2022	170,370.38	0.00	1	
Edit	Derogatory Depreciation	12/31/2022	-29,629.62	0.00	1	
Edit	Derogatory Depreciation	12/31/2021	133,333.33	170,370.38	1	
Edit	Depreciation	12/31/2021	333,333.33	170,370.38	1	
Edit	Depreciation	12/31/2020	333,333.33	503,703.71	1	
Edit	Derogatory Depreciation	12/31/2020	133,333.33	503,703.71	1	
Edit	Depreciation	12/31/2019	162,962.96	837,037.04	1	
Edit	Derogatory Depreciation	12/31/2019	65,185.18	837,037.04	1	
Edit	Acquisition	7/5/2019	1,000,000.00	1,000,000.00	1	

Creating a New Depreciation Method

In the Fixed Assets Management SuiteApp, you can create depreciation methods such as Units-of-Production Depreciation Method, or Units of Time Depreciation.

To create a new depreciation method:

1. Go to Fixed Assets > Setup > Depreciation Methods > New.
2. On the New FAM Depreciation Method page, enter the following details:
 - **Name** – Enter a name for the depreciation method.
 - **Depreciation Method Description** – Enter a brief description of the depreciation method.
 - **Depreciation Period** – Select the period units for depreciation calculation. You can select Monthly or Annually for Other Methods, but only Monthly for the Accounting Method
 - **Monthly** – This option computes depreciation amounts monthly.
 - **Annually** – This option computes depreciation amounts annually.
 - **Annual Depreciation, Monthly Posting** – This option computes the depreciation annually, divides the amount into 12, and posts it to the depreciation journal every month.

The Japanese National Tax Authority requires a different calculation to determine the depreciation amount for months 1-11 and for month 12. For month 12, the depreciation value is calculated as the difference between the total annual depreciation and the sum

of the first 11 months. For example, if an asset is valued at \$1,000,000 and should be depreciated by \$500,000 on Year 1, depreciation amount is calculated as follows:

Depreciation for Months 1-11:

- $\$500,000 / 12 = \$41,666.66$
- Round up = **\$41,667**

Depreciation for Month 12:

- $\$500,000 - \text{Sum of depreciation for Months 1-11}$
- $\$500,000 - (\$41,667 * 11)$
- $\$500,000 - 458,337 = \mathbf{\$41,663}$

 **Note:** For this depreciation period, the asset lifetime reflects the number of fiscal years for the asset. Selecting this depreciation method adjusts the asset's depreciation end date to the end of the last fiscal year. This depreciation period is only available for Japan.

- **End Period Number** – If this depreciation method covers a limited period (for example, only the first 12 months of the asset's life), enter the number of periods that the depreciation method can be used for. If left blank, depreciation continues until the asset is fully depreciated or retired.
- **Next Depreciation Method** – This feature lets you link depreciation methods. If the current depreciation method covers a limited period (for example, only the first 12 months of the asset's life), select the next depreciation method to use after the current method's end period.
- **Depreciation Rate Table** – Select the depreciation table that the system uses to set the depreciation rates to this method. These options are currently only applicable to Japan depreciation.

See  [FAM 20.2 Japan Depreciation Rate Table](#) to check the rates used to compute depreciation for each rate table.

- **Depreciation Formula** – Use the terms on the screen to enter a formula expression for this depreciation method. The formula will display with underline to show how terms are grouped with operators. This visual guide helps you determine if extra parentheses are needed to change the evaluation order.
- Select from the following **Final Period Convention** options:

 **Note:** This field is relevant only to accruals.
If left blank, **Fully Depreciate** is assigned by default.

- **Fully Depreciate** – Includes the remaining balance in the final period calculation so the remaining value becomes zero.
- **Retain Balance** – Calculates the final period using the relevant accrual convention without including any remaining balance. The remaining value doesn't become zero.
- **Value Based** – Extends asset depreciation beyond its useful life until the net book value equals the residual value.

3. Click **Save**.

Depreciation Formula

In the Fixed Assets Management SuiteApp, each depreciation method uses a formula to show how the monthly or annual depreciation is calculated.

The Depreciation Method page shows a list of available operators and constants that you can use:

- ^ (to the power of, e.g., $5^2 = 5$ squared)
- () * / +
- any number with decimals (e.g., 12345.67)

 **Note:** When creating a custom depreciation formula, you cannot use a comma for decimal places (e.g., 12345,67).

- IF condition THEN value if true ELSE value if true ENDIF
 - comparison operators (<=, <, ==, !=, >, >=)
- ~ (maximum of two values, e.g., $2 \sim 5 = 5$)
- Original Asset Cost (OC) – The original cost of the asset or purchase price.
- Current Asset Cost (CC) – The current asset cost is typically the same as the original cost, but provides an additional cost value to track changes when the cost differs. Write downs affect this value.
- Net Book Value (NB) – The current depreciated value of the asset.
- Residual Value (RV) – The lowest value the asset is reduced to. This is usually zero, unless you set a residual value for the asset.
- Asset Lifetime (AL) – The number of periods an asset is depreciated for (asset effective life for tax).
- Current Period or Age (CP) – The current age of the asset.
- Total Depreciation Amount (TD) – The total amount of depreciation applied to the asset.
- Current Usage (CU) – The current recorded usage of the asset.
- Lifetime Usage (LU) – The total usage lifetime configured against the asset.
- Last Depreciation Amount (LD) – The last depreciation amount.
- Days held in current period (DH) – The number of days between the asset acquisition date or start of the current period (whichever is later) and the disposal date or the end of the current period (whichever is earlier).
- Prior year net book value (PB) – The closing net book value at the end of the last financial year, as stored on the asset record. The **Financial Year Start** field sets the start and end of the year for the method. The Prior Year NBV updates when the month being depreciated matches the Financial Year Start month. This captures the NBV value as it was for the financial year that ended.
- Depreciation Period (DP) — The number of days in a period.
- Fiscal Year (FY) — The number of days in a fiscal year.
- R1..Rn — A placeholder for values used in the depreciation rate table.
- ROUND — If the asset's currency is Japanese Yen, this function rounds values based on the rounding preference specified in the FAM System Setup page. Otherwise, it rounds values based on the asset's currency precision.

Formula Example: Straight Line Depreciation

Straight line depreciation formula:

$(CC - RV) / AL$

$(\text{Current Asset Cost} - \text{Residual Value}) / \text{Asset Lifetime}$

Example:

Current Asset Cost: 20,000

Residual Value: 2,000

Asset Lifetime: 60 months

$$(20,000 - 2,000) / 60 = 300$$

As it is a straight line depreciation this will be the same depreciation amount every month.

Formula Example: Maximum of Two Values

The formula can perform two separate depreciation calculations, and then apply the one that results in the higher depreciation amount. To use this functionality, separate the two formulas by the ~ character.

For example, the formula for the 150DB method is:

$$((NB-RV)*(1.5/AL)) \sim ((NB-RV)/(AL-CP+1))$$

Fixed Assets Management calculates the results of both expressions individually and then uses the higher amount for the depreciation. In this case, the first formula returns the highest value for the first part of the asset's life before switching to the second.

Month 1

Net book value: 20,000

Residual value: 2,000

Asset lifetime: 60 (5 years)

Current period: 1

$$((20,000 - 2,000)*(1.5/60)) = 450$$

$$((20,000 - 2,000)/(60 - 1 + 1)) = 300$$

Therefore the first formula (450) is used.

Month 30

Net book value: 10,409

Residual value: 2,000

Asset lifetime: 60 (5 years)

Current period: 30

$$((10,409 - 2,000)*(1.5/60)) = 210$$

$$((10,409 - 2,000)/(60 - 30 + 1)) = 271$$

Now the second formula (271) is used, and that same amount applies for the rest of the asset's life because the second is a straight line depreciation method. In this example, the formula switches a third of the way through, around period 20.

Formula Example: Diminishing Value Method for Tax

You can create a diminishing value method to calculate tax depreciation using a reduced rate in the initial period (year of acquisition). For example:

Formula: $(NB)*(DH/365)*(200/(AL/12)/100)$

Depreciation Period: Monthly

Net book value is the depreciated value for tax purposes at the end of the prior period. The Prior Year Net Book Value is the depreciated value for tax purposes at the end of the prior year.

Alternate Methods (Tax Depreciation Methods)

The Fixed Assets Management SuiteApp lets you set up multiple alternate methods of asset depreciation for tax reporting. Alternate methods aren't linked to NetSuite journal postings. You can apply more than one tax depreciation method to an asset and view a Depreciation Schedule Report based on the asset type. You can also create a group tax depreciation method for a pool of assets.

To set up and use tax depreciation methods, read the following topics:

- [Creating Alternate Methods \(Tax Depreciation Methods\)](#)
- [Viewing or Editing Alternate Methods \(Tax Depreciation Methods\)](#)
- [Adding Tax Depreciation Methods to an Asset](#)
- [Using Tax Depreciation Methods](#)

Creating Alternate Methods (Tax Depreciation Methods)

You can create multiple alternate methods of asset depreciation for tax reporting. You can also create a group tax depreciation method for a pool of assets.

To create a tax depreciation method:

1. Go to Fixed Assets > Setup > Alternate Methods > New.
2. On the New FAM Alternate Methods record, provide values for the following fields:
 - **Name** – Enter a name for this alternate method.
 - **Description** – Enter a description for this alternate method.
 - **Depreciation Method** – Select a depreciation method. You can create a new depreciation method if it's not available in the list. For more information, see [Depreciation Methods](#).
 - **Convention** – Select the averaging convention to determine how depreciation is handled in the first year of an asset's depreciation. You can only use conventions with alternate methods, and by default, it's set to **None**. If you depreciate monthly, you can use the **Mid-Month** convention. If you depreciate annually, you can use the **Half Year** and **Mid-Quarter** convention. If the convention is set to **Mid-Quarter**, the asset starts depreciating for half of the first quarter, regardless of when it came into service during that period.

 **Note:** If the Convention is set to **None**, depreciation processing follows the depreciation rule in the parent asset record. For details on the depreciation rules, see [General Subtab](#).

- **Asset Life** – Enter the asset's lifetime. Units are determined by the value of the Depreciation Period (monthly or annual) on the Depreciation Method.
- **Financial Year Start** – Select the first month of the financial year.
- **Subsidiary** – Select the subsidiaries for this alternate method. To select multiple subsidiaries, press and hold the Ctrl key while clicking each subsidiary.

 **Important:** To avoid issues with depreciation schedules, you must set a value for the subsidiary. Add any new subsidiary to applicable Alternate Depreciation Method and to the asset type's Other Method records.

- **Pool Flag** – Check this box to use this method to depreciate a group of assets. For more information, see [Group Tax Depreciation](#).

- **Override Flag** – Check this box to make the Depreciation Method, Convention, Asset Life, Financial Year Start, and Period Convention fields editable when this tax method is added to an asset record.
- **Derogatory Depreciation** — Check this box to use method to recognize the French Derogatory Depreciation method.

 **Note:** This option is available if the **Enable Derogatory Depreciation** preference is checked in the FAM System Setup page, and if the country or subsidiary of the tax method is set to France.

- **Period Convention** – Select the convention that is used to define a year:
 - **12 months of 30 days each** – This convention is generally used in North America and Europe, and produces a more uniform monthly depreciation.
 - **Exact number of days in a month, year has 365 days** – This convention is generally used in Australia and New Zealand and produces uneven depreciations within the year.

3. Click **Save**.

The tax method that you created becomes available for selection in the **Alternate Method** field on the asset record's **Depreciation History** subtab.

For information about using group tax depreciation methods, see [Using Tax Depreciation Methods](#).

Viewing or Editing Alternate Methods (Tax Depreciation Methods)

In the Fixed Assets Management SuiteApp, you can edit any tax depreciation method that you create

To view or edit a tax depreciation method:

1. Go to Fixed Assets > Setup > Alternate Methods.
2. On the **Alternate Methods** List, click **View** next to the alternate method record that you want to open.
3. Click **Edit** to modify the record.
4. Make the necessary changes, and then click **Save**.

Adding Tax Depreciation Methods to an Asset

You can assign tax depreciation methods to an asset from the asset record's Depreciation History subtab. These assignments let you track tax or corporate reporting methods for the asset.

To manually add tax methods to an asset, read the [Depreciation History Subtab](#) topic.

To add alternate depreciation methods to asset records using CSV import, read [Adding Alternate Depreciation Methods Using CSV Import](#).

Using Tax Depreciation Methods

To use a tax depreciation method:

1. Add a tax method on the asset record's **Depreciation History** subtab. For information, see [Depreciation History Subtab](#).
2. Run a Depreciation Schedule report for the asset type of the asset record. For information, see [Generating Asset Reports](#).

 **Note:** See also [Asset Depreciation](#).

Custom Segments and Custom Fields in Fixed Assets Management Records and Transactions

The Fixed Assets Management SuiteApp lets you extend the custom segments functionality to your fixed assets records. This feature makes your custom segments available in the following records:

- Asset proposal record
- Asset record
- Acquisition depreciation history record
- Depreciation journal entries
- Transfer depreciation history record and associated journal entries
- Revaluation history record and associated journal entries
- Disposal history record and associated journal entries and invoices

To take advantage of this feature, you must enable the **Custom Segments** feature (see the help topic [Enabling the Custom Segments Feature](#)). You must also apply the custom segment to the FAM record where you want it to appear. For more information, see the help topic [Applying a Custom Segment to Record Types](#).

In FAM journals, the custom segment appears on the main body or the line item, depending on how you mapped the fields. You can also show the custom segments in fixed assets reports by customizing the XML report template. For more information, see [Fixed Assets Report Template](#).

 **Note:** If custom segment is mandatory, an error may appear during a depreciation run. To process the depreciation, you must remove **FAM Depreciation History** from the Custom Segment Restriction. Go to Customization > Lists, Records & Fields > Custom Segments.

You can't currently filter FAM reports by custom segments.

Read the following topics for more information:

- [Applying Custom Segments to Fixed Asset Management Records and Transactions](#)
- [Mapping Custom Segments and Custom Fields to Fixed Assets Management Records](#)

Applying Custom Segments to Fixed Asset Management Records and Transactions

To apply custom segments to FAM records and transactions:

1. Create or edit a custom segment. For more information, see the help topics [Creating a Custom Segment](#) and [Editing Custom Segments](#).

2. Apply the custom segment to your preferred transactions and to the following FAM records and transactions. For more information, see the help topic [Applying a Custom Segment to Record Types](#).
 - In the **Application & Sourcing** subtab, go to Custom Record Types, and specify the source list for the following FAM records:

Record Type	Source List
FAM Asset	
FAM Asset Proposal	Source Transaction (Transaction)
FAM Depreciation History	Asset (FAM Asset)



Note: You can't set the Source List if the custom segment is of the Multiple Select type.

- In the Application & Sourcing subtab, go to the corresponding subtab to select the following:
Select these transactions only if the **Custom Transactions** feature is enabled in your account. If you select these transactions when the feature is turned off, your selections won't be saved. To enable Custom Transactions, see the help topic [Enabling the Custom Transactions Feature](#).

Subtab	Transaction
Transactions	Fixed Asset Depreciation Entry
Transactions	Fixed Asset Disposal Entry
Transactions	Fixed Asset Revaluation Entry
Transactions	Fixed Asset Transfer Entry

Select the following transactions if the **Custom Transactions** feature is turned off in your account. If the feature is enabled, the system ignores journal entries if it's selected.

Subtab	Transaction	Notes
Transactions	Sales Transactions	For disposal invoice
Transactions	Journal Entry	For all journals
Transaction Columns	Sale Item	For invoice column or line field
Transaction Columns	Journal Entry	For journal column or line field

3. Click **Save**.

Take note of the field IDs for Transactions, Transaction Columns, and Custom Record Types. To find the Field ID, open the Custom Segment record, click **Application & Sourcing > Transactions, Transaction Columns, or Custom Record Types**.

Mapping Custom Segments and Custom Fields to Fixed Assets Management Records

You can map custom segments and custom fields in a transaction to your fixed assets management records. Mapping these fields ensures that the value from the original transaction is accurately copied to your FAM records.

A custom segment or custom field in a transaction needs a matching field in your FAM records. For more information, see the help topics [Creating a Custom Field](#) and [Creating a Custom Segment](#).

 **Note:** You can't change the field mapping through inline editing.

To map custom segments and custom fields to FAM records:

1. Go to Fixed Assets > Setup > Transaction Field Map > New.

2. In the FAM Transaction Field Map page, select a value for **Asset Field ID Type**.

This field determines the field type of the **Asset Field ID** and controls the restrictions on the **Asset Field ID** and **Transaction Field ID**.

 **Note:** When you edit a Transaction Field Map record created before version 22.2, you're prompted to set the **Asset Field ID Type**. If you don't set a value for the field, you can't update the record.

■ To map custom segments, in the **Asset Field ID Type**, select **Custom Segment** and enter values for the following fields:

□ **Source Transaction Field ID** – Enter the Transaction or Transaction Column Field ID of the custom segment that you want to map to your FAM records.

If you're mapping a custom segment on a transaction line, you must add a 'line' prefix to the field ID. For example, **line.cseg_field**.

□ **Proposal Field ID** – Enter the Field ID of the FAM Asset Proposal record type.

□ **Asset Field ID** – Enter the Field ID of the FAM Asset record type.

□ **Transaction Field ID** – Enter the Transaction or Transaction Column Field ID of the custom segment that you created in the transaction record. This field appears in both FAM journals and disposal invoices.

To show the custom segment on the transaction line item, enter the Field ID of the Transaction Column and check the **Transaction Line Field** box.

 **Note:** When entering values in the Transaction Field ID, follow these guidelines:

- You shouldn't enter custom field IDs in this field.
- For newer segments, the **Asset Field ID** and **Transaction Field ID** must be the same.
- For older segments, the **Asset Field ID** and **Transaction Field ID** must have the same segment suffix. For example, **custbody_cseg_segment1** and **custcol_cseg_segment1**.

□ **Transaction Line Field** – Check this box if the custom segment is added to the line item on the journal or disposal invoice.

 **Note:** To find the field ID, open the Custom Segment record, and then click **Application & Sourcing**. Depending on the custom segment type, go to **Transactions**, **Transaction Columns**, or **Custom Record Types**.

■ To map custom transaction fields, in the **Asset Field ID Type**, select **Custom Field** and enter values for the following fields:

□ **Source Transaction Field ID** – Enter the internal ID of the custom field you created in the transaction record.

- **Proposal Field ID** – Enter the internal ID of the custom transaction field you created in the proposal record.
- **Asset Field ID** – Enter the internal ID of the custom transaction field you created in the asset record.

 **Note:** To find the internal ID of a specific field, see the help topic [Finding Internal IDs of Record Fields](#).

To properly map custom fields and custom segments to FAM records, you must enter values for at least 2 adjacent fields. For example, to map a custom field or custom segment to the asset record, enter values for **Source Transaction Field ID** and **Proposal Field ID**. If you also want the field available in the asset record, add a value in the **Asset Field ID**. However, you can't map the **Source Transaction Field ID** directly to the **Asset Field ID**. You must always use adjacent fields to map your custom segments and custom fields to FAM records.

3. Click **Save**.

 **Note:** During the precompute process, the system flags records that don't meet the validation rules. Transaction Field Map records created before version 22.2 are still processed when the system generates a depreciation schedule.

Creating Fixed Assets Management Records

The Fixed Assets Management SuiteApp lets you create asset records in several ways. You can create asset records manually or from transactions entered in the system. If you have an existing system and want to migrate your assets to NetSuite, you can create asset records with the CSV Import Assistant. Read the following help topics to learn more:

- [Creating Asset Records from Transactions](#)
- [Creating Asset Records through CSV Import](#)
- [Creating Asset Records Manually](#)

Creating Asset Records from Transactions

The Fixed Assets Management SuiteApp lets you create new assets from transactions entered in the system. By default, the SuiteApp looks for new assets from the following transaction types with accounts that post to a fixed asset account:

- Assembly Build
- Vendor Bill
- Inventory Adjustment
- Inventory Transfer
- Item Receipt
- Journal
- Credit Card
- Check
- Expense Report

On the invoice, journal entry, and vendor bill forms, you can add a related asset to a transaction line in the Items sublist. The system then creates a custom record, attaches it to the asset, and makes it available in the asset record's Income/Expense subtab. The related asset only serves as a reference; the system doesn't perform any further computation or revaluation.

You can create asset records from transactions in the following pages:

- [Asset Proposal](#)
- [Asset Creation](#)

You can use both pages, but you'll typically use only one for each period of asset creation.

Both the Asset Proposal and Asset Creation pages run background processes to create assets. If you're creating plenty of assets, this may take some time.

For details about creating asset records from transactions, read the following topics:

- [Asset Proposal and Generation](#)
- [Asset Creation](#)
- [Multiple Asset Proposal](#)

To monitor the status of the asset creation process, go to Fixed Assets > Background Processing > Status.

Asset Proposal and Generation

The Asset Proposal feature in the Fixed Assets Management SuiteApp lets you capture the original transaction (such as a purchase, expense, or inventory transfer) that shows a new asset has been recorded in the general ledger. This posting gives an original cost for the asset, and can include other information such as the purchase date and supplier (if the original posting came from a payable ledger transaction). Capturing transactions this way helps prevent assets from being overlooked, and saves re-entering some of the asset details.

Read the following topics for more information on proposing and generating assets:

- [Proposing New Assets](#)
- [Managing Asset Proposals](#)
- [Customizing the Asset Proposal Sublist](#)
- [Editing Asset Proposal Records](#)
- [Splitting Asset Proposal Records](#)
- [Rejecting Asset Proposals](#)
- [Changing the Status of a Rejected Proposal](#)

Proposing New Assets

You can create proposals for transactions posted to the fixed asset general ledger accounts on the Asset Proposal page. You then review the proposed assets and select which ones to turn into asset records.

Note: Asset Proposal no longer captures assets created from transactions that transfer assets across asset types. For more information, see [Transferring Assets Across Asset Types](#).

Note: If you encounter a permission violation when viewing the Asset Proposal page, make sure your role has sufficient permission. For more information, see [Setting Fixed Assets Management Permission Levels](#). If you have the right permissions but still see an error, ask an administrator to view the page first. Doing so initialized the settings so other users can view the page.

Proposing New Assets

1. Go to Fixed Assets > Transactions > Asset Proposal.
2. On the Asset Proposal page, enter values for the following fields:
 - **Date Range** — Select a date range value. The system calculates the start date of the transactions that you want to propose based on the selected range and end date.

Note: The system sets the date range to **Custom** if you change the values for the Start Date or End Date.

- **Start Date** and **End Date** — Enter the date of the transactions that you want to propose. The search retrieves transactions dated within the specified range.
- **Subsidiary** - Select the subsidiary of the transactions that you want to propose.
- **Include Children** - Check this box to search transactions in the child subsidiaries of the selected subsidiaries.

- **Asset Types** - In the Asset Types sublist, select one or more asset types.

You can't add an asset type that has the same operating lease and account name as another asset type that's already on the list.

 **Note:** The system proposes lease journals for operating lease only for asset types that are tagged as **Operating Lease**.

3. Click **Propose New Assets** to check for new transactions and create proposals. The system searches for new assets dated within the specified start and end dates, and creates an Asset Proposal record for them. The proposal records are listed on the Manage Proposals page.

 **Important:** If **Propose Approved Transactions Only** is turned off, the system proposes assets from all transactions posted to the fixed asset general ledger accounts regardless of transaction status. To enable the setting, go to Fixed Assets > Setup > System Setup.

You'll be redirected to the Process Status page where you can track the progress of the asset proposal.

 **Note:** For Operating Lease asset types, the Residual Value equals the negative total interest.
There's no limit to the number of assets that the SuiteApp can handle from a single journal entry.

4. On the Proposed Assets sublist, select or clear asset proposal records as needed.

Managing Asset Proposals

Managing Asset Proposals

1. Go to Fixed Assets > Transactions > Manage Asset Proposal.
2. On the Proposed Assets Filters, enter filter values for the filters to limit the results based on the specified criteria.
 - **Asset Type** - Select one or more asset types to filter the proposals.
 - **Subsidiary** - Select one or more subsidiaries to filter the proposals.
 - **Include Children** - Check this box to include child subsidiaries in the filter.
3. On the Proposed Assets sublist, select or clear asset proposal records as needed.

 **Note:** The search only retrieves asset proposal records with **New** status.

4. Edit proposals if necessary.
For more information, see [Editing Asset Proposal Records](#).
5. Click **Generate Assets** to create assets from the marked Asset Proposal records.

 **Important:** Make sure you click **Generate Assets** before leaving the page. The system shows an error if you leave a page with marked records without running asset creation or rejection (see [Rejecting Asset Proposals](#)).

You'll be redirected to the Process Status page, where you can track the asset proposal's status. For more information, see the help topic [Asset Proposal and Generation Process Stages](#).

Customizing the Asset Proposal Sublist

You can customize the asset proposal sublist to add or remove FAM or transaction fields. Add any fields you need to review the proposal records. You can also remove the fields that aren't relevant to you.

Customizing the Asset Proposal Sublist

1. Go to Fixed Assets > Transactions > Manage Asset Proposal.
2. In the Proposed Asset sublist, click **Customize** to open the Customize Sublist window.
3. The Customize sublist window lists all fields, including custom fields, that you can add to the proposal sublist. Check the boxes for the fields you want to add to the Proposed Asset sublist. Clear the boxes for the fields you want to remove from the sublist.



Important: If you want to delete or inactivate a field record, first clear the box for that field in the Customize sublist.



Note: You can't remove the ID, Transaction, Quantity, and Process fields.

4. Click **Submit**.

You'll be redirected to the Manage Asset Proposal page, where you can view the changes you made to the sublist.

Editing Asset Proposal Records

Editing Asset Proposal Records

1. Go to Fixed Assets > Transactions > Manage Asset Proposal.
2. On the Manage Proposals page, click **Edit** next to the asset proposal.
3. On the FAM Asset Proposal page, edit the asset proposal record as needed.
4. On the Other Methods subtab, click **New FAM Proposal Alt Depreciation** to add an alternate depreciation method to the proposal.

Available alternate methods in the dropdown list are filtered by the asset proposal's **Subsidiary** field in the **General** subtab. Click **Edit** to modify existing Alternate Depreciation records.



Note: The **Alternate Method** and **Residual Value Percentage** fields are required.

5. Click **Save**.

Splitting Asset Proposal Records

You can split an asset proposal record to process some assets separately from the original record. If the proposal record multiple quantities of an asset, the Proposed Asset sublist shows a link to split the asset proposal.

Splitting Asset Proposal Records

1. Go to Fixed Assets > Transactions > Manage Asset Proposal.
2. In the Proposed Assets sublist, click **Split** next to the proposal record that you want to split.

You'll be redirected to the Proposal Split page.

 **Note:** The **Split** link appears only if the proposal has multiple quantities of an asset.

3. In the Split Details sublist, enter values on the following columns:
 - **Cost** – Enter the total cost for the quantity you're allocating to this proposal record.
 - **Quantity** – Enter the number of assets you're allocating to this proposal.
 - **New Item Description** – Enter a description for the asset. This serves as the asset record's name and description.

4. Click **Add**.

The **Remaining Quantity** and **Remaining Cost** field in the Primary Information will be updated to show the quantity and cost left to split.

5. In the Primary Information field group, check the **Split Remaining** box to divide the remaining quantity and cost equally into individual proposal records.

 **Note:** You can split both the remaining quantity and cost only if their value is greater than zero.

6. Click **Split** to split the original proposal record.

You'll be redirected to the Process Status page, where you can track the asset proposal split's status. For more information, see [Asset Split Process Stages](#).

Asset Split Process Stages

The Process Status page queues the following processes for the asset proposal split. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Asset Proposal Split	Split Asset Proposals	Splits asset proposal records according to specified details.
	Update Related Records	If the split fails, the system reverts changes from the previous stage. If it's successful, the original proposal's status is set to Split .

Rejecting Asset Proposals

On the Manage Asset Proposal page, select the proposed assets you want to reject, then click **Reject Proposals**. Make sure you click **Reject Proposals** before moving to a another page of proposals.

Unless you have Administrator access, the **Reject Proposals** box won't appear if the **Restrict Ability to Reject Proposals** box is checked in the System Setup page (Fixed Assets > Setup > System Setup).

Changing the Status of a Rejected Proposal

Rejecting the proposal doesn't delete it from the system. Its status only changes to **Rejected**. If you want to retrieve a rejected proposal, manually change its status to **New**.

To change the status of a rejected proposal:

1. Create a saved search for the rejected proposal:
 - a. Go to Fixed Assets > Searches > Proposal History > Customize.

- b. On the FAM Asset Proposal Search page, click **Edit this Search**.
 - c. On the Criteria subtab, click the existing filter, then click **Remove**.
 - d. In the Filter column, select **Proposal Status**.
 - e. In the popup window, set the Proposal Status to **any of**, then click **Rejected**.
 - f. Click **Set**.
 - g. In the **Search Title** field, enter a unique name for the search, then click **Save**.
2. Run the saved search you created for rejected proposals. For more information about saved searches, see the help topic [Saved Searches](#).
 3. In the results page, click **Edit** beside the rejected proposal you want to update.

 **Note:** If the **Show List When Only One Result** preference isn't checked in the Set Preferences page, the search opens the rejected proposal automatically when there's only one result.

4. On the FAM Asset Proposal page, from the **Proposal Status** list, select **New**.
The proposal record is now available in the Manage Proposals page.

Asset Creation

The Asset Creation feature in the Fixed Assets Management SuiteApp lets you create assets without proposing them first.

When you use Asset Creation, you can specify the start and end dates of the transactions for which you want to create an asset. However, you won't be able to select individual transactions to generate asset records.

To create asset records:

1. Go to Fixed Assets > Transaction > Asset Creation.
2. On the Asset Creation page, enter values for the following fields:
 - **Date Range** — Select a date range. The system calculates the start date based on the selected range and end date.

 **Note:** The system sets the date range to **Custom** if you change the Start Date or End Date.

- **Start Date** and **End Date** — Enter the date of the transactions for which you want to create an asset record. The search retrieves transactions dated within the specified range.
- **Subsidiary** - Select the subsidiary of the transactions that you want to create assets for.
- **Include Children** - Check this box to search transactions within the child subsidiaries of the selected subsidiary.
- **Asset Types** - In the Asset Types sublist, select one or more asset types.

You can't add an asset type that has the same operating lease and account name as another asset type on the list.

 **Note:** The system proposes operating lease journals only for asset types tagged as **Operating Lease**.

3. Click **Create Assets**.

The system automatically creates asset records for every transaction that matches the filters and posts to the fixed asset general ledger accounts.

You'll be redirected to the Process Status page, where you can track the asset creation's status. For more information, see [Asset Creation Process Stages](#).

Asset Creation doesn't process assets that are already proposed. To create asset records for proposed assets, use the Generate Assets option (Fixed Assets > Transactions > Asset Proposal). For more information, see [Asset Proposal and Generation](#).

You can combine assets to create parent-child relationships between asset proposal records and to track them as a single asset. For more information, see [Multiple Asset Proposal](#).

 **Note:** Asset Creation no longer captures assets created from transactions that transfer assets across asset types. For more information, see [Restricting the Editing of Asset Values](#).

Asset Creation Process Stages

The Process Status page queues the following processes for asset creation. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Asset Creation	Prepare data to Generate Assets	Prepare data from transactions posted to the fixed asset general ledger accounts.
	Generate Asset Records	Create asset records.
Generate Depreciation Schedule	Generate Depreciation Schedule Values	Create depreciation history records for generated assets and tax methods.

Multiple Asset Proposal

Within the Fixed Assets Management SuiteApp, the asset proposal process searches for new transactions and identifies potential assets. Sometimes, multiple components need to be combined and tracked as a single asset.

You can edit an asset proposal and select a parent proposal to create a parent-child relationship between proposal records.

To add a parent proposal to an asset proposal record:

1. Go to Fixed Assets > Transactions > Manage Asset Proposal.
Note the ID of the proposal record that you want to set as the parent.
2. In the Proposed Assets sublist, click **Edit** next to the proposal you want to set as the child.
3. In the **Parent Proposal** field, select the ID of the parent proposal record.
4. In the **Asset Description** field, update the description to show this asset's relationship to the parent proposal.
5. Click **Save**.

You can also update the parent's description to describe the combined entity.

Parent Proposal

FAM Asset Proposal
← →
List Search

Edit
Back
Actions

☐ Inactive

Parent Proposal
Asset Lifetime
36
Asset Description
Merge Asset 101
Accounting Method
Straight Line
Original Cost
24,000.00
Residual Value Percentage
0.0%
Residual Value
0.00

Asset Lifetime Usage
CS in DHR
Branch
FAM Custom Segment Test 1
FAM Custom Segment Test 2

Asset Type
Computer
Proposal Status
Created
Asset
FAM000291 Merge Asset 101
Source Transaction
Bill 1/1/2024
Source Transaction Line
1

Notes
Workflow
General
Accounts
Custom
Subproposals
Tax Methods

FAM Asset Proposal
View
Default View
FAM Asset Proposal
New FAM Asset Proposal
Attach
Customize View

Edit	Asset Type	Proposal Status	Asset	Asset Description	Original Cost	Asset Account	Remove
Edit	Computer	Combined		Merge Asset 102	600.00	Computer	Remove

The child proposal record no longer appears on the Proposed Assets sublist. You can find the child proposal on the Subproposal tab of the parent proposal record.

Child Proposal

FAM Asset Proposal
← →
List Search

Edit
Back
Actions

☐ Inactive

Parent Proposal
11002
Asset Lifetime
36
Asset Description
Merge Asset 102
Accounting Method
Straight Line
Original Cost
600.00
Residual Value Percentage
0.0%
Residual Value
0.00

Asset Lifetime Usage
CS in DHR
Branch
FAM Custom Segment Test 1
FAM Custom Segment Test 2

Asset Type
Computer
Proposal Status
Combined
Asset
Source Transaction
Bill 1/1/2024
Source Transaction Line
2

Notes
Workflow
General
Accounts
Custom
Subproposals
Tax Methods

User Notes
System Notes
View
Default
New Note
Customize View

Edit	Date	Author	Title	Memo	Direction	Type	Remove
No records to show.							

When you generate assets from the parent proposal, the child proposal's value is added to the parent. The system creates a single asset record using the parent record's description and other details.

CSV Templates for Fixed Assets Import Data

Use the following templates as a guide when you create your import file. Replace the sample data with your own, then upload it through the CSV Import Assistant. Click the following links to download the templates to your device:

- [Fully depreciated or disposed asset record](#)
- [Mid-life asset record](#)
- [Asset depreciation history record](#)

 **Note:** If you experience an error when downloading the templates, try again later.

Setting CSV Import Preferences

When you're importing assets, different settings apply to new assets and to mid-life assets. Before you import your CSV file, you must set the appropriate CSV import preferences.

Import Preference for New Assets

If you're importing new assets, set these preferences as follows:

- In Setup > Import/Export > CSV Import Preference, check the **Run Server SuiteScript and Trigger Workflows** box.
- In Fixed Assets > Setup > System Setup, check the **Run Server Script on CSV Import** box.

Import Preference for Mid-life, Fully Depreciated, and Disposed Assets

If you're importing mid-life, fully depreciated, or disposed assets, set these preferences as follows:

- In Setup > Import/Export > CSV Import Preference, check the **Run Server SuiteScript and Trigger Workflows** box.
- In Fixed Assets > Setup > System Setup, clear the **Run Server Script on CSV Import** box.

General Guidelines for Importing Fixed Asset Records

- Import the asset record data first, then import the depreciation history data.
- **Asset Type** is a required field for FAM asset and asset depreciation history imports.
- The **Subsidiary** field is a required field for FAM asset and asset depreciation history imports when you're importing data into a OneWorld account.
 - Map the **NetSuite Subsidiary** field to a field in your CSV file. Otherwise, the import fails.
 - Enter the subsidiary values in this format: Grandparent subsidiary : Parent subsidiary: Child. For example, Consolidated Parent Company : UK Subsidiary : Euro Subsidiary.
- The **Currency Id** field is required for FAM asset imports if **Multiple Currencies** is enabled. The Currency Id is the internal ID of the subsidiary's base currency. To determine the internal ID of a currency, go to Lists > Accounting > Currencies.

- **Location, Department, and Class** are required for FAM asset imports when these fields are mandatory on a journal entry.
- If the Prior Year Net Book Value is not equal to the Asset Original Cost:
 - Set the Asset Original Cost to an amount equal to the Prior Year Net Book Value, then import the asset record.
 - If you're also adding alternate depreciation for mid-life assets, import the alternate depreciation method. This action copies the Asset Original Cost to the asset record, and sets the Prior Year Net Book Value for both the asset and the alternate depreciation method.
 - After you import the asset records, run another import to update the Asset Original Cost to the correct amount. If you added an alternate depreciation, run another import to update the Asset Original Cost on the alternate depreciation method record.
- You don't have to follow the system generated naming format for depreciation history records. Use any value in the **Name** field (in the CSV file) to identify the depreciation period for the depreciation history records you're importing. Avoid using a "|" separator in the name. Otherwise, the record won't appear in depreciation searches.
- To expose all fields for import, set the preferred form for FAM Asset and FAM Asset Depreciation History to the standard form. Go to Customization > Lists, Records, & Fields > Record Types and click a record. Click the Forms tab and check the standard form. To maintain data integrity, reset the preferred form back to the custom form when imports are complete.
- When upgrading to a OneWorld account, the system doesn't automatically populate the values in the asset record's **Subsidiary** field. You can update the asset record using CSV import. You must manually add a value for the subsidiary before importing the CSV file. Alternatively, you can contact NetSuite Professional Services for help with data migration.

Guidelines for Importing Mid-life Asset Records

You can import data using the CSV Import Assistant in NetSuite to create mid-life assets (assets that started depreciating). Each asset record needs a depreciation history record to capture its cumulative depreciation to date. You can import several depreciation history records for each asset, representing each prior period of depreciation.

 **Note:** The Acquisition History Record is automatically created if you define a depreciation start date for the asset.

Use [this template](#) as a guide when you prepare the CSV import file for mid-life assets.

To import mid-life asset records, see [Importing Fixed Asset Records](#). For mid-life assets linked to asset types with default tax methods (alternate depreciation), you must also update the tax methods. For more information, see [Updating Tax Methods](#) and [Importing Tax Method DHRs](#).

Guidelines for Importing Fully Depreciated or Disposed Asset Records

When you're importing records for fully depreciated or disposed assets, you must include additional fields and validations. These extra entries ensure that no other depreciation charge is recorded against these assets.

Before you import fully depreciated and disposed assets, review the CSV import file and make the following changes:

- Set the Asset Status column to **Fully Depreciated** or **Disposed**.

- Set the Depreciation Active column to **FALSE**. This ensures that no depreciation entry is recognized.
- Make sure the Last Depreciation Period matches the Last Depreciation Date. The period number (within the asset's lifetime) must match the asset's most recent depreciation date. For example, if the Depreciation Start Date is July 1, 2021 and the Last Depreciation Date is December 31, 2021, then the Last Depreciation Period should be 6. If the Last Depreciation Period and Last Depreciation Date don't match, an error may occur.
- For fully depreciated assets, if there is a Residual Value Percentage, the Current Net Book Value should be equal to the Residual Value. If there is no Residual Value Percentage, the Current Net Book Value should be zero.
- For disposed assets, the Current Net Book Value must always be zero.

Use [this template](#) as a guide when you prepare the CSV import file for fully depreciated and disposed asset.

To import fully depreciated or disposed fixed asset records, see [Importing Fixed Asset Records](#).

Importing Fixed Asset Records

Before importing asset data, run a test import first to ensure that your CSV import works without errors. Create a test CSV file with a few assets and check the formatting to ensure that the data is imported with correct values.

To import fixed asset records, read the following topics:

- For information about the fields to include in your CSV file, see [CSV Fields for Importing Fixed Asset Records](#)
- For detailed instructions on how to import fixed asset records, see [Uploading Fixed Asset Records through CSV Import](#)

The following video shows you how to import mid-life assets and depreciation history records using the CSV Import Assistant:

 [Creating Mid-life Asset by Importing CSV Records](#)

CSV Fields for Importing Fixed Asset Records

Make sure that the CSV file you're using to import fixed asset records includes the following fields:

Fields	Description
Name	Enter the asset's name.
Asset Description	Enter the asset's description.
Quantity	Enter the asset's quantity.
Subsidiary	Enter the asset's subsidiary. This field is required for FAM asset imports when you're importing data into a OneWorld account.
Asset Type	Enter the asset type. This field is required for FAM asset imports and must be set up in the system beforehand.
Asset Status	Set the asset status to any of the following: ■ New ■ Depreciating

Fields	Description
	■ Fully Depreciated ■ Disposed
Depreciation Active	For new and depreciating assets, set this field to TRUE . For fully depreciated and disposed assets, set this field to FALSE .
Asset Lifetime	Enter the asset's expected lifetime in multiples of the depreciation period. For example, if the depreciation period is Monthly or Annual Depreciation, Monthly Posting, enter the lifetime in months.
Asset Original Cost	Enter the asset's purchase cost.
Asset Current Cost	Enter the purchase cost less any write-down amounts applied to the asset.
Residual Value Percentage	Enter the asset's value at the end of its lifetime.
Residual Value	
Depreciation Start Date	Enter the asset depreciation start date.
Last Depreciation Date	Enter the asset's most recent depreciation date.  Note: The asset may not depreciate or depreciation period may be skipped if this value is wrong.
Last Depreciation Period	Enter the period number (within the asset's lifetime) in which the asset was most recently depreciated.  Note: The asset may not depreciate or depreciation period may be skipped if this value is wrong.
Last Depreciation Amount	Enter the most recent depreciation amount for this asset.
Current Net Book Value	Enter the current net book value. The current NBV is calculated as the original cost less the accumulated depreciation and write-down amounts.

Uploading Fixed Asset Records through CSV Import

To import fixed asset records:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant – Scan & Upload CSV File screen, do the following:
 - a. From the **Import Type** list, select **Custom Records**.
 - b. From the **Record Type** list, select **FAM Asset**.
 - c. Select the asset CSV file.
 - d. Click **Next**.
3. In the Import Assistant – Import Options screen, do the following:
 - a. Set Data Handling to **Add**.
 - b. From the **Custom Form** list, select **Standard FAM Asset Form**.
 - c. Click **Next**.

4. In the Import Assistant – Field Mapping screen, do the following:
 - a. Map the fields in your CSV file to NetSuite fields as follows:

Name	↔	FAM Asset : Name (Req)
Current Net Book Value	↔	FAM Asset : Current Net Book Value
Asset Original Cost	↔	FAM Asset : Asset Original Cost (Req)
Last Depreciation Period	↔	FAM Asset : Last Depreciation Period
Asset Current Cost	↔	FAM Asset : Asset Current Cost
Depreciation Start Date	↔	FAM Asset : Depreciation Start Date
Asset Description	↔	FAM Asset : Asset Description
Last Depreciation Amount	↔	FAM Asset : Last Depreciation Amount
Last Depreciation Date	↔	FAM Asset : Last Depreciation Date
Asset Lifetime	↔	FAM Asset : Asset Lifetime
Residual Value Percentage	↔	FAM Asset : Residual Value Percentage
Residual Value	↔	FAM Asset : Residual Value (Req)
Asset Status	↔	FAM Asset : Asset Status
Subsidiary	↔	FAM Asset : Subsidiary
Asset Type	↔	FAM Asset : Asset Type (Req)

You can also add values for other fields. When you're finished, review the CSV and NetSuite fields to confirm that all fields are mapped.

Note: If you don't see the NetSuite fields, then the standard form isn't set as the preferred form. Be sure to select the standard form to show all fields.

- b. Click **Next**.
To set default values and reference types on fields, see [Setting Default Values and Reference Types](#).
5. In the Import Assistant - Save Mapping and Start Import screen, do the following:
 - a. Enter an **Import Map Name** and **Description**.
 - b. Click **Save & Run**.

Important: When creating asset records through CSV import, default tax methods linked to asset types are also imported. But, some fields for the tax methods are blank. Run another import to update the fields with missing values. For more information, see [Updating Tax Methods](#).

Importing Asset Depreciation History Records (DHRs)

Depreciation History Records (DHRs) capture an asset's depreciation transactions. You must create a DHR for every depreciation entry, which can be monthly, quarterly, or annually depending on your timing preference. For mid-life assets already depreciating, import prior period DHRs to show the correct net book value of the asset.

To import asset depreciation history records, read the following topics:

- For information about the fields to include in your CSV file, see [CSV Fields for Importing Asset DHRs](#).
- For detailed instructions on how to import asset depreciation history records, see [Uploading Asset DHRs through CSV Import](#).

CSV Fields for Importing Asset DHRs

Before importing a depreciation history record, make sure your CSV file includes the following fields:

Field	Description
DHR Name	Enter the depreciation history record name. This field identifies the depreciation period for the DHRs you're importing. You can enter any value for this field. Avoid using a " " separator in the name. Otherwise, the record won't appear in depreciation searches.
Asset Name	Enter the name of the asset linked to the DHR. This field is a combination of the unique ID and the name assigned to the asset record when it's entered in the system. For example, FAM00001 Chairs.
Subsidiary	Enter the asset's subsidiary. This field is required for FAM depreciation history imports when you're importing data into a OneWorld account.
Quantity	Enter the asset's quantity.
Accounting Book	Enter the associated accounting book. This field is required if the system has more than one accounting book.
Asset Type	Enter the asset type. This field is required for FAM depreciation history imports and must already exist in the system.
Transaction Type	Enter Depreciation as the transaction type.
Transaction Date	Enter the depreciation transaction date.
Transaction Amount	Enter the depreciation transaction amount.
Net Book Value (NBV)	Enter the balance as of the transaction.
Depreciation Period	Enter the period number covered by the depreciation transaction.
Prior Year Net Book Value	Enter the asset original cost if the transaction date is within the asset's acquisition year. Otherwise, enter the end of the year net book value.



Note: Use the sample files in [CSV Templates for Fixed Assets Import Data](#). To ensure that your CSV files import successfully, review the following guidelines:

- [General Guidelines for Importing Fixed Asset Records](#)
- [Guidelines for Importing Mid-life Asset Records](#)
- [Guidelines for Importing Fully Depreciated or Disposed Asset Records](#)

Uploading Asset DHRs through CSV Import

To import the CSV file as an asset depreciation history record:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant – Scan & Upload CSV File screen, do the following:
 - a. From the **Import Type** list, select **Custom Records**.
 - b. From the **Record Type** list, select **FAM Depreciation History**.
 - c. Select the CSV file of the asset depreciation history you created.
 - d. Click **Next**.
3. In the Import Assistant – Import Options screen, do the following:
 - a. Set Data Handling to **Add**.
 - b. From the **Custom Form** list, select **Standard FAM Depreciation History**.
4. In the Import Assistant – Field Mapping screen, do the following:
 - a. Map the fields in your CSV file to NetSuite fields as follows:

Accounting Book	↔	FAM Depreciation History : Accounting Book
Transaction Amount	↔	FAM Depreciation History : Transaction Amount
Asset	↔	FAM Depreciation History : Asset
Asset Type	↔	FAM Depreciation History : Asset Type
Net Book Value	↔	FAM Depreciation History : Net Book Value
Depreciation Period	↔	FAM Depreciation History : Depreciation Period
Date	↔	FAM Depreciation History : Date
Quantity	↔	FAM Depreciation History : Quantity
Subsidiary	↔	FAM Depreciation History : Subsidiary
Transaction Type	↔	FAM Depreciation History : Transaction Type
Name	↔	FAM Depreciation History : Name

- b. Click **Next**.
To set default values and reference types on fields, see [Setting Default Values and Reference Types](#).
5. In the Import Assistant - Save Mapping and Start Import screen, do the following:
 - a. Enter an **Import Map Name** and **Description**.
 - b. Click **Save & Run**.

Updating Tax Methods

Update tax methods only if the imported mid-life assets are linked to asset types with default tax methods (alternate depreciation). When asset records are created through CSV import, the default tax methods linked to asset types are also imported. But, some fields for the tax methods are blank. You must run another import to update the fields with missing values.

To update tax methods, perform these tasks in the following order:

- [Create a Saved Search and Export to a CSV file](#)
- [Import CSV File as Alternate Depreciation](#)

Create a Saved Search and Export to a CSV file

To create a saved search and export to a CSV file:

1. Create a saved search as follows:
 - a. Go to Lists > Search > Saved Searches > New.
 - b. Select **FAM Alternate Depreciation**.
 - c. Enter a new search title.
 - d. On the **Criteria** subtab, select date created.
 - e. On the **Results** subtab, add the following fields:
 - Internal ID
 - Asset Status
 - Last Depreciation Date
 - Last Depreciation Period
 - Last Depreciation Amount
 - Book Value (NBV)
 - f. On the **Available Filters** subtab, add your required filters.
 - g. Click **Save & Run**.
2. On the saved search results, click **Export - CSV** to export the Search results as a CSV file.
3. In the exported CSV file, check that the values of the tax methods you're updating are correct. Make corrections to your file before importing it.

Import CSV File as Alternate Depreciation

To import the CSV file as an alternate depreciation:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant – Scan & Upload CSV File screen, do the following:
 1. From the **Import Type** list, select **Custom Records**.
 2. From the **Record Type** list, select **FAM Alternate Depreciation**.
 3. Select your CSV file, and then click **Next**.
3. In the Import Assistant – Import Options screen, set Data Handling to **Add or Update**, and then click **Next**.
4. In the Import Assistant – Field Mapping screen, do the following:
 - a. Map the fields in your CSV file to NetSuite fields as follows:

Last Depreciation Period	↔	FAM Alternate Depreciation : Last Depreciation Period
Last Depreciation Date	↔	FAM Alternate Depreciation : Last Depreciation Date
Last Depreciation Amount (LD)	↔	FAM Alternate Depreciation : Last Depreciation Amount (LD)
Book Value (NBV)	↔	FAM Alternate Depreciation : Book Value (NBV)
Asset Status	↔	FAM Alternate Depreciation : Asset Status
Internal ID	↔	FAM Alternate Depreciation : Internal ID

- b. Click **Next**.

To set default values and reference types on fields, see [Setting Default Values and Reference Types](#).

5. In the Import Assistant - Save Mapping and Start Import screen, do the following:
- Enter an **Import Map Name** and **Description**.
 - Click **Save & Run**.

Importing Tax Method DHRs

After updating the missing fields for the tax methods, you must import the tax method DHRs so the system reflects the correct values.

To import tax method DHRs, read the following topics:

- For information about the fields to include in your CSV file, see [CSV Fields for Importing Tax Method DHRs](#).
- For detailed instructions on how to import fixed asset records, see [Uploading Tax Method DHRs through CSV Import](#).

CSV Fields for Importing Tax Method DHRs

Before importing a tax method DHR, create a CSV file that includes the following fields:

Field	Description
DHR Name	Enter the depreciation history record name. This field identifies the depreciation period for the DHRs you're importing. You can enter any value for this field. Avoid using a " " separator in the name. Otherwise, the record won't appear in depreciation searches.
Asset Name	Enter the name of the asset linked to the DHR. This field is a combination of the unique ID and the name assigned to the asset record when it's entered in the system. For example, FAM00001 Chairs.
Subsidiary	Enter the asset's subsidiary. This field is required for FAM depreciation history imports when you're importing data into a OneWorld account.

Field	Description
Quantity	Enter the asset's quantity.
Accounting Book	Enter the associated accounting book. This field is required if the system has more than one accounting book.
Asset Type	Enter the asset type. This field is required for FAM depreciation history imports and must already exist in the system.
Transaction Type	Enter Depreciation as the transaction type.
Transaction Date	Enter the depreciation transaction date.
Transaction Amount	Enter the depreciation transaction amount.
Net Book Value (NBV)	Enter the balance as of the transaction.
Depreciation Period	Enter the period number covered by the depreciation transaction.
Prior Year Net Book Value	Enter the asset original cost if the transaction date is within the asset's acquisition year. Otherwise, enter the end of the year net book value.
Alternate Method	Enter the name of the associated alternate method.
Actual Depreciation Method	Enter the name of the associated depreciation method.

 **Note:** To ensure that your CSV files import successfully, review the following guidelines:

- [General Guidelines for Importing Fixed Asset Records](#)
- [Guidelines for Importing Mid-life Asset Records](#)

Uploading Tax Method DHRs through CSV Import

To import the CSV file as a tax depreciation history record:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant – Scan & Upload CSV File screen, do the following:
 - a. From the **Import Type** list, select **Custom Records**.
 - b. From the **Record Type** list, select **FAM Depreciation History**.
 - c. Select the CSV file of the tax method depreciation history that you created.
 - d. Click **Next**.
3. In the Import Assistant – Import Options screen, do the following:
 - a. Set Data Handling to **Add**.
 - b. From the **Custom Form** list, select **Standard FAM Depreciation History**.
4. In the Import Assistant – Field Mapping screen, do the following:
 - a. Map the fields in your CSV file to NetSuite fields as follows:

Accounting Book	↔	FAM Depreciation History : Accounting Book
Alternate Method	↔	FAM Depreciation History : Alternate Method
Transaction Amount	↔	FAM Depreciation History : Transaction Amount
Asset	↔	FAM Depreciation History : Asset
Asset Type	↔	FAM Depreciation History : Asset Type
Net Book Value	↔	FAM Depreciation History : Net Book Value
Depreciation Period	↔	FAM Depreciation History : Depreciation Period
Date	↔	FAM Depreciation History : Date
Actual Depreciation Method	↔	FAM Depreciation History : Actual Depreciation Method
Quantity	↔	FAM Depreciation History : Quantity
Subsidiary	↔	FAM Depreciation History : Subsidiary
Transaction Type	↔	FAM Depreciation History : Transaction Type
Name	↔	FAM Depreciation History : Name

- b. Click **Next**.


To set default values and reference types on fields, see [Setting Default Values and Reference Types](#).

5. In the Import Assistant - Save Mapping and Start Import screen, do the following:
 - a. Enter an **Import Map Name** and **Description**.
 - b. Click **Save & Run**.


Setting Default Values and Reference Types

When mapping the NetSuite fields for depreciation, you must set default values for Transaction Type, Reference Type, and Depreciation Method.

The following screenshot shows the default value for the Transaction Type being set to **Depreciation**.



The following screenshot shows the Reference Type for Asset being set to **Internal ID**.



The following screenshot shows the Depreciation Method default value being set to **Accounting Method**.

Creating Asset Records Manually

In the Fixed Assets Management SuiteApp, you can add fixed assets by importing existing data, creating records manually, or generating asset records from transactions. Generating asset records from transactions is typically done for newly acquired assets.

The asset record defines the asset and its depreciation rules, and shows its net book value, depreciation life to date, last depreciation date, original cost, and residual value. After asset types are entered, details of each asset can be entered on individual asset records. When you select an asset type, the system populates some fields with default values, so you don't have to retype them.

Important: Unlike assets generated from transaction records, values for assets you create manually or migrate to NetSuite through CSV import aren't automatically posted to the fixed asset general ledger accounts. You must create the journal entries manually to post the values for these assets.

Important: To ensure that FAM bundle scripts run on assets created through CSV import, you must enable the following settings:

- **Run Server Scripts on CSV Import** (Fixed Assets > Setup > System Setup)
- **Run Server SuiteScript and Trigger Workflows** (Setup > Import/Export > CSV Import Preferences)

To create an asset record:

1. Go to Fixed Assets > Lists > Assets > New.
2. Enter values for the following fields:

Note: The ID is system-generated.

- **Name** – Enter a name for the asset.

- **Asset Description** – Enter a brief description of the asset.
- **Asset Serial Number** – Enter a serial number to track or identify the asset.
- **Alternate Asset Number** – Enter an additional asset reference number.
- **Parent Asset** – If this asset is part of a collection of assets, select the parent asset that this asset belongs to. Child assets depreciate automatically when the parent does and may be affected by other operations on the parent asset.
- **Project** – Select the related project for the asset. You can set **Depreciation Active** to **On Project Completion** so depreciation automatically starts when the project ends. For more information on Depreciation Active, see [Asset Type General Subtab](#).

 **Note:** If the asset record is generated from a proposal, the **Project** field is populated based on the defined project on the transaction or proposal record. The project name also appears on the **Name** field in the depreciation journal entries.

- **Asset Type** – Select the asset type for this asset.
When you select an asset type, the system populates most fields with its default values. The asset type also categorizes assets in reports and other processes.
- **Asset Original Cost** – Enter the original (purchase) cost of the asset.
- **Asset Current Cost** – Enter the current cost of the asset. This includes any write-down already applied to the asset.
- **Residual Value Percentage** – Enter the percentage of the original cost that the asset will be worth at the end of its life. For example, an asset purchased for \$1,000.00 may be worth \$100.00 at the end of its lifetime, so the residual value percentage would be 10% (10% of \$1,000.00 is \$100.00). Entering a residual value always overrides the default value calculated using the percentage. The default value is set by asset type.
For operating lease asset types, this field is set to 0% and won't be editable.
- **Residual Value** – Enter the value that the asset will be worth at the end of its life. For example, an asset purchased for \$1,000.00 may be worth \$100.00 at the end of its lifetime.
For operating leases, the residual value equals the total interest amount, but is shown as a negative value
- **Accounting Method** – Select the depreciation method (formula) to use when depreciating this asset. This accounting method is used to calculate the values entered into the accounting system. The default method is set by asset type.
- **Asset Lifetime** – Enter the expected lifetime of the asset, in multiples of the depreciation period. Currently, only months are supported.

If you enter a value for Asset Lifetime and Depreciation Start Date, the system automatically sets the **Depreciation End Date** field (see [General Subtab](#)). If you leave this field blank, the system automatically computes the asset lifetime if valid values are manually entered in the **Depreciation Start Date** and **Depreciation End Date**. If either the **Depreciation Start Date** or **Depreciation End Date** is changed and the new value entered is valid, the system

automatically computes the new asset lifetime. The system shows a notification whenever the asset lifetime is automatically changed.



Note: The system automatically creates an Acquisition History Record when you set a depreciation start date for the asset. The SuiteApp can't recalculate the Asset Lifetime if you change the Depreciation End Date through CSV import or script.

- **Depreciation Period** – Inline HTML text showing the Depreciation Period of the selected Accounting Method. For information, see [Depreciation Methods](#).
 - **Asset Lifetime Usage** – If you depreciate the asset based on usage (for example, mileage), enter a lifetime usage figure representing its total units. The asset reaches the end of its life when the total usage to date equals the lifetime usage.
 - **Current Net Book Value** – The current book valuation of the asset.
 - **Cumulative Depreciation** – The total depreciation amount applied to date to the asset.
 - **Asset Status** – The status is set to **New** by default. Asset Status automatically changes to **Disposed** when you dispose the asset.
 - **Customer Location** – Select a customer or create a new customer record.
3. Enter values in the fields on each of the subtabs:
 - [General Subtab](#)
 - [Accounts Subtab](#)
 - [Lease Subtab](#)
 - [Insurance Subtab](#)
 - [Maintenance Subtab](#)
 - [Asset Sale/Disposal Tab](#)
 4. Click **Save**. Enter values on the additional subtabs that appear:
 - [Depreciation History Subtab](#)
 - [Asset Usage Subtab](#)
 - [Sub-Assets Subtab](#)
 5. Click **Save**.

Asset Values Record

Each asset record has a corresponding asset values record to store the values that are updated when you depreciate the asset. Whenever you create an asset record, manually or from transactions, the system automatically creates its asset values record.

To speed up the depreciation, the system updates only the asset values record when you depreciate an asset. The asset record's depreciation fields update as well because they source values from the asset values record.

To view the asset values records, go to Customization > Lists, Records, & Fields > Record Types. On the Record Types page, click **List** next to **FAM Asset Values**.

 **Warning:** Manually making changes to the asset values record may cause issues with your Fixed Assets records.

 **Note:** Starting with Fixed Assets Management 19.1, the system removes depreciation fields from asset records with missing asset values. If you need to restore this information, see [Recovering Asset Values](#).

Recovering Asset Values

Starting with Fixed Assets Management 19.1, all assets currently in use should already have asset values. If assets don't have asset values, the system removes the following fields:

- Current Net Book Value
- Last Depreciation Amount
- Last Depreciation Date
- Last Depreciation Period
- Prior Year NBV

If you still need these values, use a script to recover them for the affected assets.

To recover deleted values:

1. Search for assets that don't have asset values and note their internal IDs.
2. Go to Customization > Scripting > Script Deployment.
3. Find the **FAM Retrieve Asset Values MR** script, and click **Edit**.
4. On the Script Deployment page, click the **Parameters** subtab.
5. In the **Asset ID** field, enter the assets' internal IDs, separated by commas.

Compound Assets

Compound assets are parent or primary assets that are comprised of multiple child assets, called components. Simple assets, in comparison, are single assets that don't have components. A component can be a simple asset or another compound asset.

This feature lets you create a compound asset by attaching multiple child assets (components) to the parent asset. You can add components that have the same asset type, subsidiary, and accounting method as the compound asset. Each component's status must be New, Depreciating, or Partially Disposed. You can't add fully depreciated or disposed assets as components.

 **Note:** Limit compound asset to five levels, with a total of 1000 assets and 1000 tax methods to avoid performance issues.

Building Compound Assets

To build a compound asset:

1. Go to Fixed Assets > Lists > Build Compound Asset.

2. Provide values for the following fields:
 - **Asset Name** – Enter a name for the asset.
 - **Asset Type** – Select the asset type for the compound asset.
 - **Accounting Method** – Select the accounting method to use when depreciating the compound asset.
 - **Subsidiary** – Select the subsidiary for the compound asset.
 - **Asset Cost** – This is automatically populated, and shows the combined asset cost of all the components.
 - **Current Cost** – This is automatically populated, and shows the combined current cost of all the components.
3. In the Components section, add a component to the compound asset by selecting from a list of existing assets, or by adding a new asset.
 - To add an existing asset, click the arrow in the **ID/Name** field, and then select an asset from the list.
 - To add a new asset, click the **ID/Name** dropdown, select **New** (or click **+**), and enter asset details. For more information on creating asset records, see [Creating Asset Records Manually](#).
4. Click **Build** to create the compound asset. You'll be redirected to the Process Status page.

General Subtab

On the General subtab, enter values for the following fields:

- **Department** – Enter a department for this asset.
- **Class** – Enter a class for this asset.
- **Location** – Enter a location for this asset.

 **Note:** If location, department, or class are required fields for journal entries, you must set them on the asset record. For example, if you setup requires journal entries to be posted on department change, you must enter a department on the record. For more information, see [Setting Up the Fixed Assets Management System](#).

- **Subsidiary** – If you're using a OneWorld account, select the asset's subsidiary.
For more information about transferring assets between subsidiaries, see [Asset Transfer Accounts](#).
- **Currency** – Shows the subsidiary's base currency.
- **Custodian** – Select the employee responsible for the asset. The Assets subtab on the Employee record shows a list of assets that the employee is a custodian of.
- **Physical Location** – Enter the location of the asset.
- **Include In Reports** – Check this box to include the asset in the Asset Register and Asset Summary Report. By default, all assets are included in the report.
- **Purchase Date** – Enter the date when the asset was purchased.
- **Depreciation Start Date** – Enter the date depreciation starts. For example, an asset can be purchased but not received or placed into service until a few months later.
- **Depreciation End Date** – Enter the date depreciation is expected to end. By default, the value is set to the asset's depreciation start date plus the useful lifetime.

The system shows an error if the end date is before the start date. If you enter valid start and end dates, the system automatically calculates the Asset Lifetime. If you change the end date and it's valid,

the system recalculates the Asset Lifetime. The system shows a message whenever it changes the depreciation end date.

Note: The SuiteApp can't recalculate the Asset Lifetime if you change the **Depreciation End Date** through CSV import or script.

- **Last Depreciation Period** – Set to zero by default.
- **Last Depreciation Amount** – Set to zero by default.
- **Last Depreciation Date** – Set to 1/1/1980 by default.
- **Target Depreciation Date** – Enter the next depreciation date.
- **Depreciation Active** – Select whether the asset is active and included in depreciation processing. For project assets, you can set depreciation to automatically start when the project ends.

Note: The system automatically creates an Acquisition History Record when you set a depreciation start date for the asset. When **Depreciation Active** is set to **False**, no Acquisition History record is created. When **Depreciation Active** is set to **On Project Completion**, the Depreciation Start Date is automatically populated when the project ends.

- **Depreciation Rules** – Select from the following values:
 - **Acquisition** – The asset depreciates in the same period it's first activated.
 - **Disposal** – The asset depreciates in its final period.
 - **Pro-rata** – The asset depreciates in proportionally for partial months in the acquisition and disposal periods, using a standard 30-day month. For example, if depreciation starts on June 18, 2011 and ends on September 17, 2011, then 13 days worth of depreciation is recorded in the first depreciation period, and 17 days worth of depreciation is recorded in the final depreciation period.

The following examples illustrate Pro-rata depreciation calculation when depreciation starts on the last day of the month:

 - If depreciation starts on the last day of a 30-day or 31-day month (for example, April 30 or January 31), depreciation is recorded for 1 day in the acquisition period, and for 29 days in the disposal period.
 - If depreciation starts on the last day of February, depreciation in the acquisition period is calculated for 1 day plus the number of days to complete 30 days. The asset depreciates for the corresponding partial month in the disposal period. For example, if depreciation starts on February 28, three days worth of depreciation (the 28th plus 2 days to make 30) is recorded for the first depreciation period, and 27 days worth of depreciation is recorded in the final depreciation period.
 - **Mid-month** – If Depreciation Start Date is in the first half of the month, then depreciation starts on the same month of the asset acquisition. Otherwise, depreciation starts on the month after the asset acquisition month.
- **Revision Rules** – Controls how revaluations affect the asset. The default value is set by Asset Type.
 - **Current Period** – The system recalculates depreciation to date and posts the difference between the calculated depreciation and the previously posted depreciation in the current period.
 - **Remaining Life** – The revision affects only future depreciation calculations.
- **Manufacturer** – Enter the asset's manufacturer.
- **Date of Manufacture** – If known, enter the asset's manufacture date.
- **Supplier** – Enter the supplier (vendor) the asset was purchased from.
- **Purchase Order** – Select the purchase order for the asset.
- **Parent Transaction** – Select the transaction that generated or represents this asset's acquisition.

Accounts Subtab

The Accounts subtab lists the ledger accounts used to post asset transactions. These accounts are set by default when you select an asset type, but you can edit them on this subtab.

You must enter account values if the tax method is associated to an accounting book. For more information, see [Assets and Accounting Books in Multi-Book Accounting](#).

Lease Subtab

Use the Lease Proposal subtab under the Lease Subtab to view lease agreement details for the asset.

- **Lease Proposal** – This field shows the link to the lease proposal record.
- **Lease Company** – This field shows the company the asset is leased from.
- **Lease Contract Number** – This field shows the contract number of the lease agreement.
- **Lease Start Date** – This field shows the start date for the lease.
- **Lease End Date** – This field shows the end date for the lease.
- **Finance Lease** – This box indicates if the asset is subject to a finance or operating lease.
- **Rental Frequency** – This field shows the frequency of rental payments.
- **Lease Term** – This field shows the expected term of lease.
- **Annual Interest Rate** – This field shows the implicit interest rate to be charged on the financing of this asset.
- **Total Interest** – This field shows the total interest based on the lease payments.
- **Total NPV** – This field shows the total net present value based on the lease payments.
- **Total Lease Payment** – This field shows the total lease payments based on the lease payment amounts.

Insurance Subtab

Use the Insurance subtab to enter insurance details, policy dates, and claims made for this asset.

- **Insurance Company** – Select the asset's insurance company.
- **Insurance Policy Number** – Enter the policy number of the insurance policy covering this asset.
- **Policy Start Date** – Enter the insurance policy start date.
- **Policy End Date** – Enter the insurance policy end date.
- **Insurance Value** – Enter the asset's insured value.
- **Payment Frequency** – Enter the payment frequency in months.
- **Payment Amount** – Enter the periodic payment amount.

Maintenance Subtab

Use the Maintenance subtab to enter maintenance details or warranty schedules for this asset.

- **Maintenance Company** – Select the company that maintains this asset.
- **Maintenance Contract** – Enter the maintenance contract number.
- **Inspection Required** – Check this box if the asset needs inspections.

- **Inspection Interval** – If the asset requires inspection, enter the inspection interval in months.
- **Last Inspection Date** – Enter the date of the last inspection.
- **Next Inspection Date** – Enter the date when the next inspection is due.
- **Warranty** – Check this box if this asset is covered by a warranty agreement.
- **Warranty Period** – If the asset is under warranty, enter the warranty period.
- **Warranty Start Date** – Enter the start date of the warranty period.
- **Warranty End Date** – Enter the expiry date of the warranty period.
- **Repair & Maintenance Category** – Select a category of repair and maintenance.
- **Repair & Maint Subcategory A** – Select a subcategory of repair and maintenance.
- **Repair & Maint Subcategory B** – Select a subcategory of repair and maintenance.
- **Quantity** – Enter the asset quantity.
- **Units of Measurement** – Enter the units of measurement.
- **Quantity Disposed** – Enter the quantity of assets disposed.

Components Subtab

The components subtab lists the child assets that make up the compound asset. In the Components sublist, click **Edit** next to the component to modify its asset record.

The Tax Methods sublist shows each component's alternate methods, grouped by accounting book, method, and currency.

The Depreciation History sublist shows each component's history grouped by accounting book, alternate method, depreciation method, asset type, schedule, and date.

Asset Sale/Disposal Tab

Use the Asset Sale/Disposal subtab to enter details sale or disposal details for the asset.



Note: The subtab only shows values reflecting the latest disposal processed for the asset. Previous disposal values are overwritten.

- **Disposal Date** – The date that the asset was disposed of, by sale or write-off.
- **Disposal Type** – Indicates whether the asset was sold or written off.
- **Disposal Item** – The sales item used on the sales invoice generated when the asset was sold.
- **Customer** – The buyer of the asset.
- **Sales Amount** – The amount the asset was sold for.
- **Sales Invoice** – The invoice for the sale.

Depreciation History Subtab

When you save a new asset record, the system automatically adds the Depreciation History subtab.

The subtab lists history records for both accounting and tax methods linked to the asset. You can click **Depreciation Histories** to open the Depreciation History page in a new tab or window. The Transaction Type column shows the history of asset activity (acquisition, depreciation, revaluation, disposal). If the activity involves financial adjustments, you can view the transaction details through the posting reference.

Note: When the depreciation is zero, the system generates a zero-value depreciation history record with a blank **Posting Reference** field. No journal entry is created.

The **Schedule** filter on the Depreciation History page provides the following options:

- **Yes** – Shows only transactions from Depreciation Schedule Reports (Fixed Assets > Reports > Depreciation Schedule).
- **No** – Shows transactions from Asset Depreciation (Fixed Assets > Transactions > Asset Depreciation).
- **All** – Displays all depreciation history.

You can assign tax depreciation methods to an asset from this subtab. Each method can have a different asset lifetime and residual value. These assignments let you track tax or corporate reporting methods on the asset. The system calculates values automatically when you run a Depreciation Schedule report for the asset type. Tax depreciation methods are used for analysis purposes and don't generate financial transactions.

You can also view and add new alternate method for the asset. For more information, see [Creating FAM Alternate Depreciation](#).

Creating FAM Alternate Depreciation

The Method sublist in the Depreciation History subtab lets you view each alternate method defined on the asset record, and add new ones.

Note: The **Store History** box is checked by default.

To add alternate methods to a new asset record:

1. Go to Fixed Assets > Lists > Assets, and then click the **View** link of the asset.
2. On the FAM Asset page, click the **Depreciation History** subtab, and then click **New FAM Alternate Depreciation**.
3. Select field values. Most of the fields are automatically populated.

Note: If the **Override Flag** is checked in the Alternate Method record, you can edit the **Depreciation Method**, **Convention**, **Asset Life**, **Financial Year Start**, and **Period Convention** fields when you add this tax method to an asset. For information about Alternate Method fields, see [Creating Alternate Methods \(Tax Depreciation Methods\)](#).

- **Alternate Method** – Select a tax method name from the list (or click the + icon) to open a New FAM Alternate Methods record and create a tax method. See [Creating Alternate Methods \(Tax Depreciation Methods\)](#).

Note: The list shows only alternate methods that match the asset's **Subsidiary** on the **General** subtab.

- **Depreciation Method** – By default, this is set to the depreciation method defined in the selected Alternate Method.
- **Original Cost** – Sourced from the Asset record.
- **Current Cost** – Sourced from the Asset record.
- **Residual Value Percentage** – Sourced from the Asset record.
- **Residual Value (RV)** – Sourced from the Asset record.
- **Asset Life (AL)** – Sourced from the Alternate Method record.
- **Book Value (NBV)** – Sourced from the Asset Current Cost.

- **Cumulative Depreciation** – Set to zero by default.
- **Asset Status** – Select the status of this tax method.

4. Under the **General** subtab, enter values for the following fields:

- **Subsidiary** – Sourced from the Asset record.
- **Depreciation Start Date** – Shows the date the tax method starts depreciating.
- **Depreciation End Date** – The expected end date of the asset's depreciation. By default, this is set to the asset's depreciation start date plus its useful life.
- **Last Depreciation Date** – The most recent depreciation date of this tax method.
- **Last Depreciation Amount (LD)** – The asset's most recent depreciation amount. This is set to zero by default.
- **Last Depreciation Period** – The period number (within the tax method's life) when the asset was last depreciated.
- **Depreciation Active** – Select whether the asset is active and included in depreciation processing. For assets related to a job, you can set depreciation to automatically start when the job completes. Default set by asset type.
- **Depreciation Rules** – Select from the following values:
 - **Acquisition** – Asset depreciates in the same period it's activated.
 - **Disposal** – Asset depreciates in its final period.
 - **Pro-rata** – Asset depreciates proportionally for partial months in the acquisition and disposal periods, using a standard 30-day month.
 - **Mid-month** – If the Depreciation Start Date falls within the first half of the month, then depreciation starts on the same month of the asset acquisition. Otherwise, depreciation starts on the month after the asset acquisition month.
- **Revision Rules** – Select how revaluations affect the asset.
 - **Current Period** – The system recalculates depreciation to date and posts the difference between the calculated depreciation and the previously posted depreciation in the current period.
 - **Remaining Life** – The revision affects only future depreciation calculations.
- **Financial Year Start** – Sourced from the Alternate Method record.
- **Annual Method Entry** – Select whether annual depreciation posts on the **Anniversary** (based on the depreciation start date) or the **Fiscal Year** (based on the last day of the fiscal year).
- **Convention** – Sourced from the Alternate Method record.

Averaging conventions set how depreciation is handled in the asset's first year. Conventions are supported for alternate methods only, and default value is **None**. For monthly depreciation, the supported convention is **Mid-Month**. For annual depreciation, the supported conventions are **Half Year** and **Mid-Quarter**. If the convention is set to Mid-Quarter, the asset depreciates for half of the first quarter, no matter when it entered service.



Note: If the Convention is **None**, the asset follows the depreciation rule set in the parent asset record. For details on the depreciation rules, see [General Subtab](#).

- **Period Convention** – Sourced from the Alternate Method record.
- **Depreciation Period** – Sourced from the Depreciation Method record.
- **Prior Year NBV** – Sourced from the Asset Original Cost on the Asset record.

The Prior Year Net Book Value is the asset's net book value for the selected tax method at the end of the previous fiscal year. The **Financial Year Start** field on the Alternate Method record

determines the method's start and end of the year. The Prior Year NBV updates when the depreciated month for an Alternate Method (tax method) matches the **Financial Year Start** month. This captures the NBV as it stood for the financial year that ended.

- **Group Depreciation** – Sourced from the Alternate Method record.
 - **Group Master** – You can check this box only if **Group Depreciation** is checked.
 - **Allow Override** – Sourced from the Alternate Method record. If this box is checked, you can edit the Depreciation Method, Convention, Asset Lifetime, Financial Year Start, and Period Convention.
5. Click **Add** to attach the alternate method to the asset. You can add as many tax methods as you need.
 6. Check **Store History** if you want to keep depreciation history records. Otherwise, clear the box.



Important: Checking the **Store History** box affects the depreciation performance.

7. Click **Save**.

For more information on tax depreciation methods, see [Using Tax Depreciation Methods](#).

For more information on tax depreciation methods, see [Using Tax Depreciation Methods](#).

Asset Usage Subtab

When you save an asset record, the system automatically adds the Asset Usage subtab. This subtab records and displays an asset's unit usage for unit-based depreciation. You can create new usage transactions on this subtab.

To enter asset usage from the Asset Usage subtab:

1. Click **New FAM Asset Usage**.
2. Provide values for the following fields:
 - **Date** – Enter the date of usage.
 - **Period** – Enter the period in which the usage took place. This could be a month, a week, an accounting period name, or any other meaningful period.
 - **Units Used** – Enter the number of units used.
 - **Comments** – Enter any comments or reference text relating to the usage.
3. Click **Save**.

Sub-Assets Subtab

When you save a new asset, the system adds the Sub-Assets subtab. Use this subtab to add child assets to an asset or create a

To add a sub-asset to an Asset record:

1. View or edit the asset record that you want to add sub-assets to. This asset will be the parent asset.
2. Click the **Sub-Assets** subtab.
3. Click **New FAM Asset**.

On the New FAM Asset page, the Parent Asset field shows the parent's name.

4. Enter values for the new asset's fields and subtabs.

For more information, see [Creating Asset Records Manually](#).

5. Click **Save**.

The new asset appears on the parent record's Sub-Asset subtab. The system automatically generates the FAM Asset ID. Click the sub-asset's FAM Asset ID to open and edit the record.

6. Repeat steps 3 to 5 to add more sub-assets.

You can also create a sub-asset from Fixed Assets > Lists > Assets > New. Select a parent asset from the **Parent Asset** list, enter values in the fields and subtabs, and save the record. For more information, see [Creating Asset Records Manually](#).

Income/Expense Subtab

The Income/Expense subtab shows the income earned from the asset and the expenses incurred, such as fuel or maintenance costs. It also shows the journal reference for quick access.

You can manually add transactions in this subtab to record the asset's income and expenses.

To record your income or expense:

1. On the Income/Expense subtab of the asset record, click New FAM Expense/Income.
2. Provide values for the following fields:
 - **Expense/Income Amount** — Enter the amount of income earned or expense incurred for this asset.
 - **Transaction Reference** — Select the transaction record where the expense or income originated.
 - **Memo** — Enter the memo from the transaction reference.
3. Click **Save**.

Notes Subtab

Use the Notes subtab to add notes related to this asset.

Files Subtab

Use the Files subtab to attach files related to this asset.

Updating Fixed Assets Management Records

To update your asset records and depreciation methods in the Fixed Assets Management SuiteApp, read the following topics:

- [Updating Asset Records Using CSV Import](#)
- [Adding Alternate Depreciation Methods Using CSV Import](#)
- [Manually Editing Asset Records](#)
- [Restricting the Editing of Asset Values](#)
- [Triggering the Asset Reset Process](#)

Updating Asset Records Using CSV Import

You can use the CSV Import Assistant in NetSuite to update existing data in the Fixed Assets Management SuiteApp. If the updates affect the original cost, depreciation start date, or cumulative depreciation, then you may also need to update the original asset history records.

On the Fixed Assets Management System Setup page, you can set which roles can edit asset values. For more information, see [Restricting the Editing of Asset Values](#).



Important: Before you import asset data, it's best to perform a test import. Create a test CSV file with a few assets and review the formatting to ensure that data is imported with correct values. Make sure the asset type in the CSV file matches exactly how it's set up in your NetSuite account.



Important: To ensure that FAM bundle scripts run on newly imported assets, enable **Run Server Scripts on CSV Import** (Fixed Assets > Setup > System Setup) and **Run Server SuiteScript and Trigger Workflows** (Setup > Import/Export > CSV Import Preferences).

To update asset records using CSV import:

1. Prepare an import file by creating a custom view from the existing Fixed Asset list in NetSuite.
 1. Go to Fixed Assets > Lists > Assets.
 2. Click **Customize View**.
 3. Set Criteria to filter the list as necessary.
 4. Choose the fields to update and add them to the **Results** subtab of the new custom view.



Important: The NetSuite Internal ID of the Asset is required to link the updated information to the correct asset.

5. Click **Preview**.
 6. Click **Export - CSV** and save the CSV file.
2. On Fixed Assets > Setup > System Setup, make sure that the **Run Server Scripts on CSV Import** box isn't checked. If this box is checked the **Cumulative Depreciation**, **Last Depreciation Date**, and **Last Depreciation Period** will be automatically set to 0 even if your import file includes the correct amounts. For more information, see [General Guidelines for Importing Fixed Asset Records](#).

3. Go to Setup > Import/Export > Import CSV Records. In the Import Assistant Step 1 - Scan & Upload CSV File screen:
 1. From the **Import Type** list, select **Custom Records**.
 2. From the **Record Type** list, select **FAM Asset**.
 3. Select the CSV file to upload.
 4. Click **Next**.
4. In the Import Assistant Step 2 - Import Options screen:
 1. Set Data Handling to **Update**.
 2. From the **Custom Form** list, select **Standard FAM Asset Form**.
 3. Click **Next**.
5. In the Import Assistant Step 4 - Field Mapping screen:
 1. Map the fields in your CSV file to the NetSuite fields.
 - Set the Internal ID mapping type to **Internal ID**.

- Review the CSV fields and NetSuite fields to ensure that all required fields are mapped.
2. Click **Next**.
6. In the Import Assistant Step 5 - Save Mapping and Start Import screen:
 1. Enter an Import Map Name and Description.
 2. Click **Save & Run**.

Adding Alternate Depreciation Methods Using CSV Import

You can use the CSV import Assistant in NetSuite to update alternate depreciation methods assigned to asset records.



Important: Before you import asset data, it's best to perform a test import. Create a test CSV file with a few assets and review the formatting to ensure that data is imported with correct values.

To add alternate depreciation methods to asset records using CSV import:

1. Prepare an Import File by creating a custom view from the existing Fixed Asset list in NetSuite.

1. Go to Fixed Assets > Lists > Assets.
2. Click **Customize View**.
3. Set Criteria to filter the list as necessary.
4. Choose the fields to be updated and add them to the **Results** subtab of the new custom view.

To see the necessary fields to be imported, read [Creating FAM Alternate Depreciation](#).



Important: The Asset's NetSuite Internal ID is required to link the updated information to the correct asset.

5. Click **Preview**.
6. Click **Export - CSV** and save the CSV file.
2. On Fixed Assets > Setup > System Setup, make sure that the **Run Server Scripts on CSV Import** box isn't checked. If this box is checked, the **Cumulative Depreciation**, **Last Depreciation Date**, and **Last Depreciation Period** will be set to 0 even if your import file includes the correct amounts. For more information, see [General Guidelines for Importing Fixed Asset Records](#).
3. Go to Setup > Import/Export > Import CSV Records. In the Import Assistant Step 1 - Scan & Upload CSV File screen:
 1. From the **Import Type** list, select **Custom Records**.
 2. From the **Record Type** list, select **FAM Alternate Depreciation**.
 3. Select the CSV file to upload.
 4. Click **Next**.
4. In the Import Assistant Step 2 - Import Options screen:
 1. Set Data Handling to **Add**.
 2. Click **Next**.
5. In the Import Assistant Step 4 - Field Mapping screen:
 1. Map the fields in your CSV file to the NetSuite fields.
 - Set the Internal ID mapping type to **Internal ID**.

- Review the CSV fields and NetSuite fields to ensure that all required fields are mapped.
2. Click **Next**.

Example: CSV values

Internal ID	Asset Original Cost	Alternate Method
50	1741.32	Depreciation Method 6
50	1741.32	Depreciation Method 8

Example: Mapping

Alternate Method	↔	Alternate Method (Req)	ⓧ
Internal ID	↔	Parent Asset	ⓧ
Asset Original Cost	↔	Book Value (NBV)	ⓧ

6. In the Import Assistant Step 5 - Save Mapping and Start Import screen:
1. Enter an Import Map Name and Description.
 2. Click **Save & Run**.

Triggering the Asset Reset Process

The Fixed Assets Management system tracks changes to asset fields used in the depreciation formula, or that affect the DHR data and summarization. When the reset process is triggered, the system deletes the forecast amounts for all affected records.

To ensure that the process runs smoothly, perform the following steps:

- Add the **FAM Asset Reset Data** permission to your custom role, and set the level to **Create**.
- Enable the **Run Server Scripts on CSV Import** preference in the FAM System Setup page.

The reset process is triggered in any of the following ways:

- **Summarization** — Any change to the summarization (**Summarize by** field in the System Setup page) automatically triggers the reset process and resets all asset records.
- **Scheduled Script** — The **FAM Trigger Reset Process (Scheduled) SS** script runs the reset process daily, if the system detects record changes that need a reset. You can manually run the script or change the time when it runs. For more information, see [Managing Fixed Assets Scripts](#).
- **Fixed Assets Transactions and Field Mapping** — When you run certain FAM transactions or change the field mapping, the Asset Reset process is triggered. The following FAM transactions trigger the reset process:
 - Asset Split
 - Asset Depreciation
 - Asset Disposal (includes bulk disposal)
 - Generate Depreciation Schedule
 - Asset Revaluation
 - Depreciation Schedule Report
 - Asset Transfer (includes bulk transfer)
- **Reset Asset Values in the System Setup Page** — If the system detects record changes that need a reset, the **Reset Asset Values** button appears on the System Setup page. You can go to Fixed Assets > System Setup, and click the button to trigger the reset process.

To see which fields trigger a reset when modified, [Field Changes That Trigger an Asset Reset](#).

If an asset reset is triggered, you'll be redirected to the Process Status page, where you can track the asset reset status. For more information, see [Asset Reset Process Stages](#).

Field Changes That Trigger an Asset Reset

The following table lists fields that can trigger asset reset:

Asset Field	Subtab	Resets Due To
Fields that will always trigger reset		
Asset Lifetime		Update Forecast records
Parent Asset		Summarization of Journals
Repair & Maintenance Category	Maintenance	Summarization of Journals
Repair & Maint Subcategory A	Maintenance	Summarization of Journals
Repair & Maint Subcategory B	Maintenance	Summarization of Journals
Project		Journal Grouping
Depreciation Rules	General	Depreciation Formula
Inactive		Update Forecast records
Depreciation Account	Accounts	Update Forecast records
Depreciation Charge Account	Accounts	Update Forecast records
Depreciation Active	General	Update Forecast records
Custom Segment fields		Journal Grouping
Fields that will trigger reset only if included in the Depreciation Method formula		
Asset Original Cost		Depreciation Formula
Asset Current Cost		Depreciation Formula
Residual Value		Depreciation Formula
Residual Value Percentage		Depreciation Formula
Depreciation Method		Depreciation Formula
Asset Lifetime Usage		Depreciation Formula
Current Net Book Value		Depreciation Formula
Depreciation Start Date	General	Depreciation Formula
Depreciation End Date	General	Depreciation Formula
Last Depreciation Period	General	Depreciation Formula
Last Depreciation Amount	General	Depreciation Formula
Financial Year Start	General	Depreciation Formula
Annual Method Entry	General	Depreciation Formula

Asset Reset Process Stages

If Asset Reset is triggered, the following processes are added to the Process Status page. Click the **Details** link on the process to view the process stage details.

Process	Process Stage	Process Stage Description
Reset Asset	Prepare Data to Reset Records	Gathers changes to the record that affect associated assets or tax methods.
	Reset Asset Values	Removes the tag that identifies the record as having forecast amounts.
	Delete Old Forecast Values	Deletes old forecast records and summary records with no associated records.

 **Note:** Forecast values are created when the system runs the script to generate the depreciation schedule. You can manually run the script or change its schedule. For more information, see [Managing Fixed Assets Scripts](#).

Manually Editing Asset Records

Enabling the **Allow Asset Value Editing** preference on the Fixed Assets Management System Setup page, gives administrators full permission to edit asset record values. Other roles can also edit values if their roles are selected in the **User Roles** field on the same page.

If the **Allow Asset Value Editing** box isn't checked, most fields on the asset record can't be edited. See [Restricting the Editing of Asset Values](#) for a list of fields that cannot be edited.

 **Note:** To enter negative values in asset records, you must check the **Allow Negative Asset Cost** box on the Fixed Assets Management System Setup page.

When an asset record is set to inactive, the depreciation schedule values for the asset's accounting and tax method are deleted to prevent it from depreciating.

 **Note:** Due to a system limitation, forecast amounts aren't deleted if you check the **Inactive** box from the Asset List view (Fixed Assets > Lists > Assets). To make sure that forecast amounts for inactive assets are deleted, check the **Inactive** box from the Edit view of the asset record.

Restricting the Editing of Asset Values

On the Fixed Assets Management System Setup page, you can restrict the editing of asset values. You can edit asset values manually on the Edit FAM Asset page, by inline editing on the Asset list, or by CSV import.

On the System Setup page, checking the **Allow Asset Value Editing** box gives the Administrator role full permission to edit asset record values. You can also let other users edit asset values by granting permission to additional roles.

 **Warning:** When you enable **Allow Asset Value Editing**, you can edit fields that are otherwise locked to prevent errors. Be aware that changing any of these fields without updating the related records can cause errors in the system.

If the **Allow Asset Value Editing** box isn't checked, most fields are set to read-only to prevent asset editing.

- The following fields are set to read-only to prevent manual editing by anyone, regardless of the asset condition and user's role:

- Cumulative Depreciation
- Last Depreciation Period
- Last Depreciation Amount
- Last Depreciation Date
- Asset Status
- When depreciation has started for an asset (the **Cumulative Depreciation** field has a value more than zero), or when the **Asset Status** is **Disposed**, the following fields are set to read-only to prevent manual editing by anyone, regardless of the user's role:
 - Accounting Method
 - Residual Value Percentage
 - Residual Value
 - Asset Lifetime
 - Asset Lifetime Usage
 - Asset Original Cost
 - Asset Current Cost
 - Purchase Date
 - Depreciation Start Date
 - Depreciation End Date
 - Depreciation Rules
 - Currency
 - Quantity
 - Asset Serial Number (not editable only if a value has been saved for this field)
 - Alternate Asset Number (not editable only if a value has been saved for this field)
 - Current Net Book Value (even if the field is disabled, the value can be updated if the asset is new)

Managing Assets



Important: Scripts triggered by script deployment don't have a corresponding FAM process record. The FAM process record is required for FAM scripts, without it, the script will fail. Whenever possible, use the user interface to run or generate FAM transactions and reports. The system automatically creates the FAM process record when scripts run through the user interface.

- [Asset Depreciation](#)
- [Group Tax Depreciation](#)
- [Asset Disposal by Sale or Write-Off](#)
- [Partial Disposal of an Asset](#)
- [Asset Revaluation](#)
- [Asset Split](#)
- [Asset Transfer](#)

Asset Depreciation



Note: In the latest Fixed Assets Management version, custom journals don't work with Multi-book accounting.

Use Asset Depreciation to run first time depreciation or to depreciate assets after you revise their method or period.

You can run depreciation periodically for a single or several asset types. This procedure is run to depreciate assets for the next period. The SuiteApp decides which assets require depreciation by checking the depreciation start date, last depreciation period, and depreciation rules. When it posts the depreciation values, the system creates a batch of GL journal entries.

An asset depreciates for each period (set on the depreciation method) up to the date entered on the Depreciate Assets page.

For example, if an asset depreciates monthly and the last depreciation is in January, a depreciation run in June processes depreciation for February through June.



Note: Depreciation stops when the last depreciation period is reached for both the accounting and alternate/tax methods assigned to the asset.



Important: If you enabled the accounting preferences **Make Departments Mandatory**, **Make Classes Mandatory**, and **Make Locations Mandatory**, but the asset's department, class, or location is not set, the system won't process the depreciation. No depreciation history records or journal entries will be created.

Depreciating Assets for the Period

To depreciate assets for the period:

1. Go to Fixed Assets > Transactions > Asset Depreciation.
2. Enter values for the following fields:
 - **Asset Type(s)** — Select one or more asset types.
 - **Subsidiary(s)** — Select one or more subsidiaries. Check **Include Children** if you want to include the child subsidiaries (and their children) of the selected subsidiary.
 - **Depreciation Period** — Enter a date up to which assets will be depreciated.
 - **Depreciation Reference** — Enter a depreciation reference to be used as the base reference on all generated journals. Leave this field blank to use the default reference.
3. Click **Depreciate Assets**. The SuiteApp calculates depreciation based on the entered method and period.

You'll be redirected to the Process Status page, where you can track the depreciation status. For more information, see [Asset Depreciation Process Stages](#).

If you enabled **Custom Transactions** and **Use Custom Journals**, a specific journal entry is created for asset depreciation. You can view these journal entries in Fixed Assets > Transactions > Journal Types. You have to set the status of the journal entry to **Approved** before it posts. For more information, see [Viewing and Approving Custom Journal Entries](#).

If **Require Approvals on Journal Entries** is enabled, and you don't have permission to approve journal entries, an administrator must approve them before posting.

When an adjustment period is included in the accounting period setup, depreciation journal entries are posted to the end of the base period, if it's open. If the period is closed, the journal entry posts to the next open period.

 **Note:** When depreciation is zero, the system creates a zero-value depreciation history record with no posting reference. No journal entry is created.

The depreciation date should fall within an existing accounting period, otherwise no journal entry is created.

Asset Depreciation Process Stages

You'll be redirected to the Process Status page, where you can track the depreciation status. The Process Status page queues the following processes for depreciation. Click **Details** on any process to view the its stage details. For more information, see [Background Processing of Fixed Assets](#).

Process	Process Stage	Process Stage Description
Asset Depreciation	Generate Depreciation Schedule Values	Creates depreciation history records for assets and tax methods without an existing depreciation schedule. If the asset and tax methods already have a depreciation schedule, the status shows Not Required.
	Create Journal Entries	Creates journal entries posting to the fixed asset depreciation and expense accounts entered on the Accounts tab. A journal entry is created per asset type and per period of depreciation.
	Prepare Data to Update Records	Gets updated values from journal entries, and identifies which records to update. The status shows Not Required if no journal entry was created in the previous step.
	Update Asset Records	Updates values on the asset record. If you enabled Multi-book Accounting, this process also updates tax methods with accounting books.

Process	Process Stage	Process Stage Description
	Update Tax Methods	Updates tax methods. If you enabled Multi-book Accounting, this process also updates tax methods without accounting books.
	Update Compound Assets	Updates compound asset records.
	Update Related Records	Updates other records related to this asset.

Generating Depreciation Schedule Values

The Fixed Assets Management SuiteApp can forecast depreciation values for both accounting and tax methods. This process automatically creates the depreciation schedule for the entire asset life when an asset record is generated from a proposal. This feature is automatically enabled in newly-installed bundles.

For assets that you create manually or through CSV import, a script runs every Sunday to check for assets without depreciation schedules. The script creates the schedule from the asset's depreciation start date and depreciation period. The script also adjusts the depreciation schedule values whenever the asset's depreciation history record changes. You can also manually trigger the precompute process on the FAM System Setup page.

Note: You can change when the script runs, depending on your preference. For more information, see [Managing Fixed Assets Scripts](#).

A depreciation schedule can't be created for assets in the following cases:

- If the depreciation methods use the CU variable in their formula. For example, Asset Usage.
- If the asset is included in a group depreciation.
- If **Use Accounting Period Dates for Depreciation** is enabled, a depreciation schedule is created only up to the accounting period you've set up.

When you check the precompute status, you may see multiple entries for **Generate Depreciation Schedule Values**. These duplicates don't affect any of the FAM records. The number of entries in the FAM Process Stage Details reflects the number of times the script was queued. The scripts can be queued multiple times for any of the following reasons:

- Application server restart – When this happens, the scripts resume processing the record from where it left off.
- Map/Reduce yielding – This is a feature of the scripts that enables it to yield or resume processing if certain limits are reached. For more information, see the help topic [Map/Reduce Yielding](#).
- Batch processing limits – The Generate Depreciation Schedule process handles up to 5,000 records at a time. The script runs again if there are more than 5,000 records to process.

Depreciation of Compound Assets

Although the components depreciate together with the compound asset, they're treated as individual assets. Each component has its own depreciation history record. The compound asset record shows the total component depreciation, including alternate depreciation, but it won't have journal entries. You can find the journal entries in the component asset record under Components > Depreciation History subtab.

The compound asset's depreciation start date follows the date of the component with the earliest depreciation start date. The end date follows the date of the component with the latest depreciation end date.

For more information about depreciating an asset, see [Asset Depreciation](#).

Sample Scenarios for Compound Asset Depreciation

The following describes different scenarios that you may encounter when depreciating a compound asset. A corresponding table shows sample values for the compound asset and the component before and after depreciation. For each scenario described, the straight line accounting method is used to depreciate the assets on a monthly basis.

Scenario 1: Depreciate a new compound asset that contains new components, all of which have the same depreciation start date, for 1 month. Selected depreciation period is 1/31/2015.

	Before Depreciation			After Depreciation		
	Compound	Component 1	Component 2	Compound	Component 1	Component 2
Asset Status	New	New	New	Depreciating	Depreciating	Depreciating
Depreciation Start Date	1/1/2015	1/1/2015	1/1/2015			
Asset Life	6	3	6			
Asset Original Cost	900	300	600			
Asset Current Cost	900	300	600			
Current Net Book Value	900	300	600	700	200	500
Cumulative Depreciation				200	100	100
Last Depreciation Period				1	1	1
Last Depreciation Amount				200	100	100
Last Depreciation Date				1/31/2015	1/31/2015	1/31/2015

Scenario 2: Fully depreciate all components of a compound asset. Each component has a different depreciation end date. Selected depreciation period is 9/14/2015.

	Before Depreciation			After Depreciation		
	Compound	Component 1	Component 2	Compound	Component 1	Component 2
Asset Status	New	New	New	Fully Depreciated	Fully Depreciated	Fully Depreciated
Depreciation Start Date	1/1/2015	6/15/2015	1/1/2015			
Depreciation End Date	9/14/2015	9/14/2015	8/14/2015			
Asset Life	9	3	6			
Asset Original Cost	900	300	600			
Asset Current Cost	900	300	600			
Current Net Book Value	900	300	600	0	0	0
Cumulative Depreciation				900	300	600
Last Depreciation Period				9	3	6
Last Depreciation Amount				100	100	100

	Before Depreciation			After Depreciation		
	Compound	Component 1	Component 2	Compound	Component 1	Component 2
Last Depreciation Date				9/30/2015	9/30/2015	8/31/2015

Scenario 3: Depreciate a compound asset whose component depreciation history record has no transaction amount. Selected depreciation period is 1/31/2015.

	Before Depreciation		After Depreciation	
	Compound	Component 1	Compound	Component 1
Asset Status	New	New	Depreciating	Depreciating
Depreciation Start Date	1/1/2015	1/1/2015		
Depreciation End Date	3/31/2015	3/31/2015		
Asset Life	3	3		
Asset Original Cost	0	0		
Asset Current Cost	0	0		
Current Net Book Value	0	0	0	0
Cumulative Depreciation			0	0
Last Depreciation Period			1	1
Last Depreciation Amount			0	0
Last Depreciation Date			1/31/2015	1/31/2015
Depreciation history record: 1/1/2015 — 1/31/2015; Transaction amount: 0				

Depreciation of Assets with Zero and Negative Costs

The SuiteApp can depreciate assets with zero and negative costs, provided the combination of the affected asset costs is any of the following:

Original Cost	Current Cost	Residual Value
Negative	Negative	Negative
Negative	Negative	Zero
Negative	Zero	Zero

The minimum Residual Value you can enter is zero. By default, the system uses the absolute value of all negative asset costs. Therefore, depreciation for assets with negative values is calculated using the absolute values of the original and current costs up to zero or absolute Residual Value.

You can enter negative values in asset records if **Allow Negative Asset Cost** is enabled. For more information, see [Setting Up the Fixed Assets Management System](#).



Important: For accounting methods, the system won't depreciate assets with negative costs if **Allow Negative Asset Cost** is turned off. No depreciation history records or journal entries are created. Even if **Allow Negative Asset Cost** is turned off, you may still import negative costs depending on your settings for CSV import. For more information, see [General Guidelines for Importing Fixed Asset Records](#).

Asset Disposal by Sale or Write-Off

The Fixed Assets Management SuiteApp lets you write-off or sell a simple or compound asset. When you dispose an asset during or at the end of its useful life, adjust the depreciation provision account so the balance shows the accumulated depreciation to date on assets you still hold.

During asset disposal, the system creates depreciation histories for the asset's accounting and tax methods (Depreciation History and Alternate Depreciation History Sublist). Disposal is applied to both accounting and tax methods and the sale amount is calculated separately for each method. For accounting methods, the amount is sourced from the Asset Current Cost in the FAM Asset record. For alternate or tax methods, the amount is sourced from the Current Cost in the FAM Alternate Depreciation record.

To sell or dispose an asset, read the following topics:

- [Selling an Asset](#)
- [Disposing or Writing-Off an Asset](#)
- [Bulk Asset Disposal through CSV Import](#)
- [Partial Disposal of an Asset](#)

Selling an Asset

When you sell an asset, you enter the proceeds and post the difference between its net book value and the proceeds from the sale to the general ledger. The system creates a sales invoice using the Disposal Item and sets the asset status to **Disposed**.

To sell an asset:

1. Go to Fixed Assets > Transactions > Asset Disposal.
2. In the Primary Information section, enter values for the following fields:
 - **Disposal Type** – Select **Sale**.
 - **Disposal Date** – Enter a posting date for the disposal.
 - **Consolidate Line Items on Invoice** – Check this box to combine the sales amount of all assets for disposal into a single line item on the invoice. Clear this box to itemize each asset for disposal on the invoice.
 - **Customer** – Select the buyer of the asset.
 - **Sales Tax Code** – Select the tax code that applies to this sale.



Note: If SuiteTax is enabled on your account, the SuiteTax engine automatically sets the tax code on the invoice. This field is not available if you're using SuiteTax. For more information, see the help topic [General SuiteTax Topics](#).

- **Sale Item** – Select the sale item that appears on the invoice.

 **Note:** The Sale Item list is unfiltered and may include items not valid for sale. If you select an invalid item, an error prompts you to select a valid sale item.

 **Note:** For OneWorld accounts, the customer, asset, sales tax code, and sale item must have the same subsidiary.

3. On the Disposal Details field group, enter values for the following fields:

- **Asset ID/Name** – Select the asset by name or ID. You can enter a simple, compound, or component asset.

 **Note:** If you select a compound asset, all of its components are added for disposal. The disposal process is the same for simple and component assets.

- **Quantity To Dispose** – Enter the quantity of assets being sold.
- **Sales Amount** – Enter the sales amount.
- **Location** – If **Multi-Location Inventory (MLI)** is enabled, asset disposal by sale requires a location value. If available, the location is sourced from the FAM asset record by default and can't be edited to prevent untracked location transfers. If not available from the asset record, you must select the value in the Location list on the Sale/Disposal page.

4. Click **Add**.

To dispose of multiple assets in one transaction, add more assets in the Disposal Details section. Repeat step 3 as needed.

 **Important:** Make sure the asset you're processing is the one you want to dispose. You can no longer retrieve disposed assets.

5. Click **Dispose**.

If you enabled **Custom Transactions** and **Use Custom Journals**, a specific journal entry is created for asset disposal. You can view these journal entries in Fixed Assets > Transactions > Journal Types. You'll need to manually set the status of the journal entry to **Approved** before it posts. For more information, see [Viewing and Approving Custom Journal Entries](#).

If **Require Approvals on Journal Entries** is enabled, and you don't have permission to approve journals, an administrator must approve them before posting.

Disposing or Writing-Off an Asset

Writing off an asset posts its net book value and cumulative depreciation to the general ledger and set the book value and cumulative depreciation to zero.

To dispose (write off) an asset:

1. Go to Fixed Assets > Transactions > Asset Disposal.
2. In the Primary Information section, provide values for the following fields:
 - **Disposal Type** – Select **Write-off**.
 - **Disposal Date** – Enter a posting date for the disposal.
3. On the Disposal Details section, enter values for the following fields:
 - **Asset ID/Name** – Select the asset by name or ID. You can enter a simple, compound, or component asset.

Note: If you select a compound asset, all of its components are added for disposal. The disposal process is the same for simple and component assets.

- **Quantity To Dispose** – Enter the number of assets to dispose of.
- **Location** – If available, the location is sourced from the FAM asset record by default and can't be edited to prevent untracked location transfers. If not available from the asset record, you must select the value in the Location list on the Sale/Disposal page.

4. Click **Add**.

To dispose of multiple assets in one transaction, add more assets in the Disposal Details section. Repeat step 3 as needed.

Important: Make sure the asset you're processing is the one you want to dispose. You can no longer retrieve disposed assets.

5. Click **Dispose**. Writing off an asset sets its book value to zero.

The system creates a disposal depreciation history record. If **Multi-Book Accounting** is enabled, the system also generates a journal entry to write off tax methods linked to accounting books.

If **Custom Transactions** and **Use Custom Journals** are enabled, the system creates a specific journal entry for asset disposal. You can view these journal entries in Fixed Assets > Transactions > Journal Types. You'll need to set the journal entry status to **Approved** before it posts. For more information, see [Viewing and Approving Custom Journal Entries](#).

If **Require Approvals on Journal Entries** is enabled, and you don't have permission to approve journal entries, an administrator must approve the journal entry before posting.

You'll be redirected to the Process Status page, where you can track the disposal's status. For more information, see [Asset Disposal Process Stages](#).

Asset Disposal Process Stages

The Process Status page queues the following processes for asset disposal. Click **Details** on any process to view the process stage details.

Process	Process Stage	Process Stage Description
Asset Disposal	Dispose Asset	Processes the asset for disposal.
	Update Related Records	Links the invoice to the asset record if the disposal is successful. If it fails, the system reverts changes made in the previous stage.
	Delete Old Forecast Values	The system deletes existing depreciation schedule since it's no longer accurate after disposal.
	Update Compound Assets	Updates compound asset records.
	Update Related Records	Updates other records related to this asset.
Generate Depreciation Schedule	Generate Depreciation Schedule Values	Creates new depreciation history records for generated assets and tax methods.

Bulk Asset Disposal through CSV Import

To process multiple asset disposals using CSV import

1. Go to Fixed Assets > Transactions > Asset Disposal.

 **Note:** You can't add columns or custom fields to this import.

2. On the Asset Sale/Disposal page, click **Import CSV**.
3. On the Bulk Asset Disposal page, click **Choose File**, then select the CSV file that contains the records you want to process.

Click the link below the Choose file button to view a sample file.

4. Check the **Consolidate Line Items on Invoice** box to combine the sales amount of all assets for disposal into a single line item on the invoice.
5. Click **Submit**.

The following table shows sample disposal values for a CSV import:

Disposal Type	Disposal Date	Customer	Tax Code	Sale Item	Asset	Quantity to Dispose	Sale Amount	Location
Sale	1/31/2015	Customer ABC	-Not Taxable-	Item for Disposal	79	3	7,000.00	California

 **Important:** To ensure you are correctly entering values in your CSV file, see [CSV File Mapping for Asset Disposal](#).

If **Multi-Book Accounting** is enabled, the system also creates a journal entry to write off tax methods linked to accounting books. For information about multi-book asset disposal, see [Disposing an Asset in Multiple Books](#).

CSV File Mapping for Asset Disposal

When you're disposing multiple assets through CSV import, use the following mapping to enter values in your CSV file:

Header	Value
Disposal Type	Must match the disposal type.
Disposal Date	Must match the disposal date and can't be earlier than the last depreciation date.  Important: To avoid errors during disposal, make sure the CSV file's date format matches the one set in the General Preference page. To check the date format, contact your account administrator.
Customer	Must match the customer name and must be under the same subsidiary as the asset. Leave blank if the disposal type is Write Off .
Tax Code	Must match the applicable tax code for the customer's subsidiary.  Important: Remove this field or leave it blank if you're using SuiteTax, or if the disposal type is Write Off .
Sale Item	Must match the name of the non inventory item used for disposal and must be under the same subsidiary as the asset. Leave blank if the disposal type is Write Off .
Asset	Must match the asset internal ID.

Header	Value
Quantity to Dispose	Must match the number of assets to dispose of.
Sale Amount	Enter the sale value. It can't be zero (0) or a negative value. Leave blank if the disposal type is Write Off .
Location	Must be under the same subsidiary as the asset's current location.

Partial Disposal of an Asset

The Fixed Assets Management SuiteApp lets you dispose a partial quantity of an asset. When you sell or dispose a portion of an asset, you can enter the quantity you want to dispose. The system reduces the asset's remaining value (similar to a write-down) so that future depreciation calculates correctly. The asset record tracks the disposed quantity and the asset retains its current status.

On the Asset Disposal page, enter the quantity of assets to sell or write off in the **Quantity Disposed** field. For more information, see [Asset Disposal by Sale or Write-Off](#).

Asset Revaluation

The Asset Revaluation feature lets you write down or revalue an asset. A write-down is a form of depreciation that involves a partial write-off. Writing down the asset lets you enter a new net book value and post the difference to the general ledger. Revaluation adjusts the true value of the fixed assets. Asset Revaluation is supported for accounting methods only. It does not apply to alternate/tax methods that are not linked to an accounting book.

Starting with Fixed Assets Management version 18.1, asset and tax records are linked to an accounting book. In non multi-book accounts, the system tags all records to the primary accounting book. With this change, you'll see the tax methods on the Asset Revaluation page when you select an asset. Records are arranged by accounting book, GL posting tax methods, and then non GL posting tax methods.

For information about asset revaluation in multi-book accounting, see [Revaluing an Asset in Multiple Books](#).

Single Asset Revaluation

To revalue a single asset:

1. Go to Fixed Assets > Transactions > Asset Revaluation.
2. On the Asset Revaluation page, enter values for the following fields:
 - **Asset ID/Name** — Select the asset by name or ID.
When you select an asset, the page shows the revaluation amounts by accounting book and method.
 - **Accounting Books** — Select the accounting book that you want to revalue.

 **Note:** This field is available only if you enabled the **Multi-book Accounting** feature.

- **Write-down %** — Enter the write-down percentage for revaluation. This applies to tax methods linked to an accounting book.

For compound assets, the write-down percentage applies to all components. To set a different percentage for each component, go to Step 4.

- **Transaction Date** – Enter a journal date for this transaction. If the field is blank, the system uses the date when the revaluation is processed.

The revaluation date must be on or after the Last Depreciation Date.

- **Transaction Reference** – Enter a reference to identify the journal entry for this transaction.
- **Write-down Amount** – The system calculates this amount from the Current Cost and the Write-down %. You can enter a write-down amount to override the calculated value. This amount is subtracted from the current net book value.

For compound assets, this amount shows the total write-down for all the components.

- **Adjusted Residual Value** – Enter the new residual value of the asset.
- **Adjusted Lifetime** – Enter the new lifetime of the asset.

If the new lifetime equals the last depreciation period, the asset's status becomes **Fully Depreciated**. If the asset's revision rule is set to Current Period, the current net book value equals the residual value, and the cumulative depreciation equals the asset current cost.

- **Adjusted Depreciation Method** – Select the new depreciation method that for this asset.

3. Click **Calculate** to compute the write-down amount based on the write-down percentage.

If **Multi-Book Accounting** is enabled, clicking **Calculate** also enables the revaluation fields for the selected accounting books. If this feature isn't enabled, you don't have to click Calculate to enable the revaluation fields. They're automatically enabled when you select an asset.



Note: If you're revaluing a simple asset, any change to the accounting book selection and write-down percentage requires you to recalculate the write-down amount. Removing a book, for example, requires you to click **Calculate** to remove the book's accounting method from the revaluation. If you're revaluing a compound asset, you can click **Process Revaluation** regardless of any changes after calculating the write-down amount.

4. To revalue only a specific component, or set different write-down percentages for each component, go to the Component section. Enter the write-down percentage for the component you want to revalue.

5. Click **Process Revaluation**.

The system creates journal entries to post the difference in value.

The system writes a revaluation depreciation history record to each component. The compound asset record shows the total component revaluation, but has no journal entries of its own. You can find the journal entries in the component asset record under Components > Depreciation History subtab.

If you enabled **Custom Transactions** and **Use Custom Journals**, the system creates a specific journal entry for asset revaluation. You can view these journal entries in Fixed Assets > Transactions > Journal Types. You'll need to set the journal entry's status to **Approved** before it posts. For more information, see [Viewing and Approving Custom Journal Entries](#).

If **Require Approvals on Journal Entries** is enabled, and you don't have permission to approve journal entries, an administrator must approve them before posting.

You'll be redirected to the Process Status page, where you can track the revaluation's status.

Asset Revaluation Process Stages

The Process Status page queues the following processes for asset revaluation. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Asset Revaluation	Revalue Asset	Adjusts the value of the asset.
	Update Related Records	If the revaluation is successful, the system skips this process and sets the status to Not Required . If it fails, the system reverts changes made in the previous stage.
	Delete Old Forecast Values	The system deletes existing depreciation schedule since it's no longer accurate after the revaluation.
	Update Compound Assets	Updates compound asset records.
	Update Related Records	Updates other records related to this asset.
Generate Depreciation Schedule	Generate Depreciation Schedule Values	Creates new depreciation history records for generated assets and tax methods.

Multiple Asset Revaluation

You can revalue multiple assets at one time through CSV import. The process applies the same validation and posting logic used in single asset revaluation. But, it queues affected records, generates all related journal entries in one run.

To revalue multiple assets, read the following topics:

- [Guidelines and Limitations when Revaluing Multiple Assets](#)
- [Revaluing Multiple Assets through CSV Import](#)

Guidelines and Limitations when Revaluing Multiple Assets

When creating a CSV file for bulk asset revaluation, review the following guidelines and limitations:

- The Asset ID and Transaction Date fields in the CSV file are required. If one of these fields is blank, the CSV file won't be processed.
- The value in the Asset column must match the Asset Internal ID.
- To revalue a tax method, enter its internal ID in the Tax Method ID column. Leave the column blank to revalue only the asset.
- At least one optional column, other than the Tax Method ID and Transaction Reference, must have a value.
- Only component assets can be revalued. Compound assets aren't supported.
- The CSV file size can't exceed 10 MB and is subject to the File Cabinet's storage availability.
- Numbers and currency amounts in the CSV file should follow the formats defined in the General Preferences page.
- If the CSV file has validation errors, it won't be processed even if some rows are valid.

Revaluing Multiple Assets through CSV Import

To revalue multiple assets:

1. Go to Fixed Assets > Transactions > Asset Revaluation.
2. On the Asset Revaluation page, click **Import CSV**.

3. On the Bulk Asset Revaluation page, click **Choose File** and locate the CSV file containing details of the assets you want to revalue.

You can download a sample file from the link below the **Select File** field.

4. Click **Submit**.

You'll be redirected to the Process Status page, where you can track the revaluation's status. The Process Status page queues the following processes for revaluation. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Bulk Asset Revaluation	Map CSV Data to Revaluation Details	Maps and converts the CSV data to prepare for revaluation.
	Revalue Asset	Adjusts the asset value.
	Update Related Records	If the revaluation is successful, the system skips this process and sets the status to Not Required . If it fails, the system reverts changes made in the previous stage.
	Delete Old Forecast Values	The system deletes existing depreciation schedules since it's no longer accurate after the revaluation.
	Update Compound Assets	Updates compound asset records.
	Update Related Records	Updates other records related to this asset.

Asset Split

The Fixed Assets Management SuiteApp lets you split assets that aren't disposed or marked inactive on the asset record.

The **Quantity** field on the asset record's Maintenance subtab tracks the number of individual elements that form the asset. Splitting an asset lets you separate a specified quantity from the original asset and create new asset records.

Depreciation continues to work on each asset as a whole. If some units need different depreciation rules, you can split them to create a separate asset. Likewise, if some units are transferring to a different class, department, location, or subsidiary, they must first be split into a separate asset and then moved. You can't combine assets (for example, reverse the process of splitting an asset).

For information about asset split in multi-book accounting, see [Splitting an Asset in Multiple Books](#).

To split assets one at a time or in bulk, read the following topics:

- [Splitting an Asset](#)
- [Splitting Assets in Bulk](#)

Splitting an Asset

Divide a single asset into new records by selecting the source asset on the Asset Split page. You can enter split quantities and adjust values to create new assets.

To split an asset:

1. Go to Fixed Assets > Transactions > Asset Split.

2. In the **Asset ID/Name** field, select an asset to split.

The Split Details subtab becomes available when you select an asset. The Alternate Depreciation subtab shows the tax methods linked to the selected asset. Assets generated after the split inherit the original asset's alternate depreciation. New asset values are calculated based on the ratio of the split quantity.

3. In the Split Details subtab, under the Assets Generated from Split sublist, enter the **Split Quantity** and click **Add**. Repeat this step for each asset record that you want to create from the split.

The Split Details subtab lists details of both the original and new assets after the split. New asset values are calculated based on the split quantity. These values can be edited. The following conditions are applied when you modify the split details:

- The split quantity can't be zero.
- The net book value can't exceed the current cost for both the old and new assets.
- The sum of the net book value and depreciation to date must equal the current cost.
- The last depreciation amount can't exceed the depreciation to date.
- The residual value can't exceed the current cost and net book value for both the original and generated assets.
- New asset values can't exceed the original asset's values.

4. Click **Split** to create a new split asset and update the original asset.

You'll be redirected to the Process Status page, where you can track the asset split's status. For more information, see [Asset Split Process Stages](#).

Asset Split Process Stages

The Process Status page queues the following processes for asset split. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Asset Split	Split Assets	Splits assets according to the specified quantity.
	Split Alternate Depreciation Methods	Creates alternate depreciation methods for the new assets.
	Delete Old Forecast Values	The System deletes the existing depreciation schedule since it's no longer accurate after the asset split.
Generate Depreciation Schedule	Generate Depreciation Schedule Values	Creates a new depreciation forecast for the asset and its tax methods

Splitting Assets in Bulk

When many assets must be divided at once, bulk splitting applies the same validation rules used for a single split. The system processes each asset in sequence, and refreshes all related depreciation forecasts.

To split assets in bulk, read the following topics:

- [Guidelines and Limitations for Splitting Assets in Bulk using CSV Import](#)
- [Splitting Multiple Assets through CSV Import](#)

Guidelines and Limitations for Splitting Assets in Bulk using CSV Import

When creating a CSV file for bulk asset split, review the following guidelines and limitations:

- The CSV file must include values for the new assets generated by the split.
- The Asset and Quantity columns are required. If left blank, the CSV file won't be processed.
- The Original Cost, Current Cost, Current Book Value, Residual Value, and Last Depreciation Amount columns are optional. If left blank, values for these columns are automatically calculated based on the quantity ratio.
- If you enter values for the optional columns, make sure that the Original Cost, Current Cost, and Current Book Value must all have values. Otherwise, the CSV file won't be processed.
- The value in the Asset column must match the Asset internal ID.
- The total values entered can't exceed the original asset's values. The original asset must also have at least one quantity remaining after the split.
- The CSV file size can't exceed 10 MB and is subject to the File Cabinet's storage availability.
- Numbers and currency amounts in the CSV file should follow the formats defined in the General Preferences page.
- If the CSV file has validation errors, it won't be processed even if some rows are valid.

Splitting Multiple Assets through CSV Import

To split multiple assets using CSV Import:

1. Go to Fixed Assets > Transactions > Asset Split.
2. On the Asset Split page, click **Import CSV**.
3. On the Bulk Asset Split page, click **Browse** and select the CSV file you want to process.

You can download a sample file from the link below the **Select File** field.

4. Click **Submit**.

The following table shows sample values for the assets that will be generated from the split transaction:

Asset	Quantity	Original cost	Current cost	Current book value	Residual value	Last depreciation amount
330	1	16,667.67	16,667.67	16,667.67	833.33	0

Creating a Saved Search for Asset Split User Notes

The system creates a user note in the asset records generated by the split. You can create a saved search for these user notes to check the source asset ID and the FAM process record ID.

To create a saved search for user notes in asset records generated from a split:

1. Go to Lists > Search > Saved Searches > New.
2. On the New Saved Search page, click **User Note**.
3. (Optional) On the **Search Title** field, enter a name for your search.

4. On the Criteria subtab, select the **Date** filter, and on the Saved User Note Search popup, set the following values:
 1. **Date** – Select **within**.
 2. **From** – Set to the earliest date of the split transactions you want to search.
 3. **To** – Set to the latest date of the split transactions you want to search.
 4. Click **Set**.
5. On the Results subtab, in the Field sublist, add **Date**, **Title**, and **Memo**.
6. Click **Save**.

Asset Transfer

The Fixed Assets Management SuiteApp lets you transfer simple and compound assets across asset types, subsidiaries, classes, departments, or locations. For asset transfers across subsidiaries, you need valid asset transfer account records. For more information, see [Asset Transfer Accounts](#).

Starting with Fixed Assets Management version 4.0, asset transfers are processed in the Asset Transfer page. You can't transfer the asset type at the same time as the subsidiary, department, class, or location. The Subsidiary, Department, Class, Location, and Asset Type fields on the asset record are grayed out even if **Allow Asset Value Editing** is enabled.

Read the following topics to learn more about transferring assets:

- [Transferring an Asset](#)
- [Transferring Multiple Assets through CSV Import](#)
- [Transferring Assets Across Subsidiaries](#)
- [Transferring Assets Across Classes, Departments, or Locations](#)
- [Transferring Assets Across Asset Types](#)

 **Note:** The SuiteApp doesn't support asset transfers using inline editing. Inline editing lets you change values on the asset record, but it can't transfer the asset's current cost and cumulative depreciation amount, nor does it create journal entries. Asset transfer through mass updates isn't available in the SuiteApp.

Transferring an Asset

To process an asset transfer:

1. Go to Fixed Assets > Transactions > Asset Transfer.
2. On the Asset Transfer page, select an **Asset ID** or **Name** from the list. You can enter a simple, compound, or component asset.
3. In the **Transfer Date** field, enter the effective transfer date. You can enter a future date if you enabled **Allow Future-dated Depreciation**. For more information, see [Setting Up the Fixed Assets Management System](#).

 **Note:** For future-dated transfers requiring currency conversions, the system uses the current exchange rate at the time you set the transfer date value.

4. Select the new **Department**, **Class**, **Location**, **Subsidiary**, or **Asset Type**.

When you transfer a compound asset, all its components are transferred. If a component is also a compound asset, its own components are transferred as well. You can transfer individual components, but only to another class, department, or location.

 **Note:** When you transfer a compound asset to another subsidiary, the components' class, department, and location remain the same. The transfer won't be processed if the asset's current class, department, and location isn't a part of the target subsidiary.

5. When you are finished, click **Process Transfer**.

When you transfer an asset, the system calculates catch-up depreciation to ensure that depreciation is up-to-date.

You'll be redirected to the Process Status page, where you can track the asset transfer's status. For more information, see [Asset Transfer Process Stages](#).

If you enabled **Custom Transactions** and **Use Custom Journals**, the system creates a specific journal entry for asset transfer. You can view these journal entries in Fixed Assets > Transactions > Journal Types. You'll need to manually set the journal entry's status to **Approved** before it posts. For more information, see [Viewing and Approving Custom Journal Entries](#).

If **Require Approvals on Journal Entries** is enabled, and you don't have permission to approve journal entries, an administrator must approve them before posting.



Important: You must update depreciation history records for asset transfers where the transaction type is **Sale** or **Disposal** and the disposal type is blank. Set the transaction type to **Transfer**.

Asset Transfer Process Stages

The Process Status queues the following processes for asset transfer. Click **Details** on any process to view its stage details.

Process	Process Stage	Process Stage Description
Asset Transfer	Validate Asset Transfer Values	Checks if the details of the asset being transferred, and its child records, are valid.
	Catch-up Precomputation	Creates depreciation history records from the asset's last depreciation date and depreciation start date, up to the period before the transfer. This process includes the asset's child records.
	Catch-up Journal Creation	Creates catch-up journal entries for posting records (assets or tax) from the asset's last depreciation date and depreciation start date, up to the period before the transfer. This process includes the asset's child records.
		 Note: If a journal fails, the related assets aren't transferred.
	Prepare Data to Update Records	Gets updated values from journal entries and identifies records to update. The status shows Not Required if no journal was created in the previous step.
	Update Asset Records	Updates posting asset or tax methods based on its depreciation values.
	Update Tax Methods	Updates non-posting tax methods based on its depreciation values.
	Transfer Assets	Processes the transfer of the asset to the specified asset type, subsidiary, class, department, or location.

Process	Process Stage	Process Stage Description
		 Note: When the asset transfer fails, the catch-up depreciation won't be rolled back.
	Update Compound Assets	Updates affected compound assets.
	Update Related Records	If the asset is transferred successfully, the system skips this stage and sets the status to Not Required . If it fails, the system reverts changes made in the previous stage.
	Delete Old Forecast Values	The system deletes the existing depreciation schedule since it's no longer accurate after the transfer.

Transferring Multiple Assets through CSV Import

To process multiple asset transfers using CSV import:

1. On the Asset Transfer page, click **Import CSV**.

 **Note:** You can't add columns or custom fields to this import.

2. Click **Choose File**, then select your CSV file.

Click the link below the **Choose File** button to view a sample file.

 **Note:** When you use the sample template, you must either enter values for each header or remove the headers that you don't need. If a header is blank, its existing value is cleared when the transfer is complete.

3. Click **Submit**.

The following table shows sample transfer values for a CSV import:

Asset	Asset Type	Subsidiary	Class	Department	Location
79	Computer	Parent Company	Servers	Accounting	California

 **Important:** To ensure you are correctly entering values in your CSV file, see [CSV File Mapping for Asset Transfer](#).

CSV File Mapping for Asset Transfer

When you're transferring multiple assets through CSV import, use the following mapping to enter values in your CSV file:

Header	Value
Asset	Must match the asset record's internal ID
Asset Type	Must match the asset type
Subsidiary	Must match the asset's subsidiary

Header	Value
Class	Must match the asset's class
Department	Must match the asset's department
Location	Must match the asset's location

Transferring Assets Across Subsidiaries



Important: Transferring assets across subsidiaries requires valid asset transfer records. For more information, see [Asset Transfer Accounts](#).

When you transfer an asset to another subsidiary, the system journals its current cost and accumulated depreciation from the origin subsidiary accounts to the destination subsidiary accounts.

Book Specific Journal

345

Edit

Back

Actions

Primary Information

Entry No.
345

Accounting Book
Primary Accounting Book

Currency
Yen

Exchange Rate
1

Date
1/31/2023

Classification

Subsidiary
Subsidiary 1

Lines

Communication

Related Records

System Information

Custom

GL Impact

1,400,000 -

Account	Debit	Credit	Memo
Equipment	1,400,000		Asset Transfer In (FAM)
Acc. Dep-Equipment		946,667	Asset Transfer In (FAM)
Equipment		453,333	Asset Transfer In (FAM)

Book Specific Journal

344

Edit

Back

Actions

Primary Information

Entry No.
344

Accounting Book
Primary Accounting Book

Currency
USA

Exchange Rate
1.00

Date
1/31/2023

Classification

Subsidiary
ABC Company

Lines

Communication

Related Records

System Information

Custom

GL Impact

14,000.00 -

Account	Debit	Credit	Memo
Equipment		14,000.00	Asset Transfer Out (FAM)
Acc. Dep-Equipment	9,466.67		Asset Transfer Out (FAM)
Equipment	4,533.33		Asset Transfer Out (FAM)

During a transfer, the system automatically converts the asset value to the destination subsidiary's base currency. Depreciation journal entries and reports generated after the transfer reflect the new base currency. The system also converts the following values to the new base currency:

- Asset Original Cost
- Asset Current Cost
- Residual Value
- Current Net Book Value
- Prior Net Book Value
- Cumulative Depreciation
- Last Depreciation Amount

The system tracks historical records of asset activities for both accounting and alternate/tax methods.

Depreciation History

Asset

FAM000035

Method

Accounting Method

Accounting Book

Primary Accounting Book

GL Posting

Yes

Schedule

Depreciation History -

Edit	Transaction Type	Date	Transaction Amount	Net Book Value	Quantity	Posting Reference	
Edit	Write-down	12/16/2024	10,000.00	10,125.00	25	Journal #314	
Edit	Acquisition	1/31/2023	1,400,000.00	1,400,000.00	25	Journal #345	
Edit	Depreciation	1/31/2023	-9,466.67	0.00	25	Journal #344	
Edit	Transfer	1/31/2023	14,000.00	0.00	25	Journal #344	
Edit	Depreciation	1/31/2023	946,667.00	453,333.00	25	Journal #345	
Edit	Depreciation	12/31/2022	191.67	4,533.33	25	Journal #341	
Edit	Depreciation	11/30/2022	191.67	4,725.00	25	Journal #340	

Transferring Assets Across Classes, Departments, or Locations

When you transfer an asset to a new class, department, or location, the system carries its current cost and cumulative depreciation from the origin subsidiary to the destination subsidiary. Journal postings are generated only if the following settings are enabled:

- Post on Location Change
- Post on Class Change
- Post on Department Change

For more information, see [Setting Up the Fixed Assets Management System](#)

The system tracks historical records of asset activities for the accounting method only. No historical records for alternate tax methods are created when transferring assets across classes, departments, or locations.

To post journal entry on location change, make sure that **Post on Location Change** is enabled in the System Setup page.

Note: No journal entry is created for transfers to a class, department, or location, if the original transfer value is null.

Transferring Assets Across Asset Types

Changing the asset type also updates the general ledger asset, depreciation account assignments, and asset life. The last posted amounts for the current cost and cumulative depreciation are carried over from the old to the new accounts through sale and reversal transactions. The asset inherits the asset life of the new asset type.

The system tracks historical records of asset activities for both the accounting and alternate/tax methods.

Tax methods with accounting book values on the original asset type must exist on the default alternate depreciation list of the destination asset type. Otherwise, the transfer won't be processed. See the following example:

Original Asset Type	Accounting Book	Alternate Depreciation
	Secondary Book	Depreciation Method 8
	Secondary Book	Depreciation Method 9
	Empty	Depreciation Method 9

Destination Asset Type	Accounting Book	Alternate Depreciation
	Secondary Book	Depreciation Method 8
	Secondary Book	Depreciation Method 9

Note: In the previous example, the original asset type's third alternate method (with no accounting book) also transfers to the destination asset type.

Deleting Assets

This feature lets you remove invalid assets and their related records. You can use it to delete assets without journal entries or proposal records. If the asset has a journal entry, you must manually remove it before deleting the asset.

Note: You can't delete compound assets with this feature. You can, however, delete non-compound component assets.

To delete invalid assets:

1. Go to Fixed Assets > Setup > Delete Assets.
2. On the Delete Invalid Assets page, add the assets to delete through the Asset Details sublist or through CSV import.
 - To add assets through the Asset Details list:
 1. From the Asset Details list, select the asset ID or name that you want to delete, and then click **Add**.
 2. Click **Delete**.
Click **OK** in the confirmation dialog to delete the assets and their related records.
 - To add assets through CSV import:
 1. Click **Import CSV**.
The system redirects you to the Bulk Asset Deletion page.
 2. On the Bulk Asset Deletion page, click **Choose File** to locate the CSV file on your device.
Click the link below the Choose File field to view a sample file.
 3. Click **Submit** to upload your CSV file. You'll be redirected to the FAM Process Status page.

Group Tax Depreciation

To use group tax depreciation methods for a group of assets, complete these tasks in the following order:

1. Create an Alternate Depreciation Method for Group Tax Depreciation.
2. Define Assets for Group Tax Depreciation.
3. Create a Group Master Record for Group Tax Depreciation.
4. Run [Asset Depreciation](#) for the group of assets.
5. Generate Asset Reports

Create an Alternate Depreciation Method for Group Tax Depreciation

Create an alternate depreciation method to use for group tax depreciation

1. Go to Fixed Assets > Setup > Alternate Methods.
2. Enter values for the fields and check the **Pool Flag** box. For more information, see [Creating Alternate Methods \(Tax Depreciation Methods\)](#).
3. Click **Save**.

Define Assets for Group Tax Depreciation

Define assets for group tax depreciation

1. Go to Fixed Assets > Lists > Assets.
2. Select the asset record to include in the group depreciation.
3. On the Asset Record page, click the **Depreciation History** subtab.
4. Click **New FAM Alternate Depreciation Method**.
5. In the **Alternate Method** field, select the group tax depreciation method that you created. You'll notice that **Group Depreciation** is already checked.
6. Enter the **Book Value (NBV)**.
7. Enter or edit values in the other fields.
8. Click **Save**.
9. Repeat steps 1 to 8 for each asset in the subsidiary until the group is complete.

Create a Group Master Record for Group Tax Depreciation

Create a group master record for group tax depreciation

1. Go to Fixed Assets > Lists > Assets > New.
2. Type a name for this group master record.
3. On the **General** subtab, select a **Subsidiary**. The subsidiary of this group master record must match the subsidiary of the assets defined for the group depreciation.
4. Set **Original Cost** and **Residual Value** to zero.
5. Enter values for the following required fields: **Asset Type**, **Accounting Method**, and **Asset Lifetime**.
Asset Type can be of any value.

6. Enter values for the other fields.
7. Click **Save**.
8. Click the **Depreciation History** subtab.
9. Click **New FAM Alternate Depreciation**.
10. In the **Alternate Method** field, select the group tax depreciation method.
11. Check the **Group Master** box.
The **Group Master** box is available only if the selected alternate method is a group depreciation method (Group Depreciation box is checked).
12. Click **Save**.

To run Asset Depreciation for the group, see [Asset Depreciation](#).

To generate a Depreciation Schedule report for the group, see [Generating Asset Reports](#).

After assets are depreciated, you can open the group master asset record and view its depreciation history. The [Creating FAM Alternate Depreciation](#) can be found in the Depreciation History subtab of the asset record. Click the **Depreciation Histories** link to view the transactions. The **Schedule** filter in the Depreciation History page provides the following options:

- **Yes** – Shows only transactions from the Depreciation Schedule Reports (Fixed Assets > Reports > Depreciation Schedule).
- **No** – Shows transactions from the Asset Depreciation (Fixed Assets > Transactions > Asset Depreciation).
- **All** – Shows all depreciation history.

Viewing and Approving Custom Journal Entries



Important: You must enable **Use Custom Journals** (from the FAM System Setup page) and **Custom Transactions** (from Setup > Company > Enable Features > SuiteCloud > SuiteGL). In the latest version of Fixed Assets Management, you can't use this feature with Multi-book accounting.

1. Go to Fixed Assets > Journal Types, and then select the journal type that you want to view.
The page lists the custom journal entries for a specific fixed asset transaction.
2. To approve a custom journal, click **Edit** next to the entry.
3. In the **Status** list, select **Approved**.
4. Click **Save**.

Asset Reports

The Fixed Assets Management SuiteApp provides several reports that offer comprehensive reporting across assets, valuation and depreciation. With these reports, you can report on assets across locations, subsidiaries, asset types, and more.

Report values are organized by subsidiary and accounting book. Within a subsidiary and accounting book combination, the values are further organized per asset type.

Read the following topics to learn more about asset reports:

- [Asset Register Report](#)
- [Asset Summary Report](#)
- [Depreciation Schedule Report \(Net Book Value and Period Depreciation\)](#)
- [Depreciation Monthly Report](#)
- [Asset Listing Report \(Anlagenspiegel\)](#)
- [Schedule 16 Reports](#)

 **Important:** Scripts triggered through script deployment does not have a corresponding FAM process record. The FAM process record is a required parameter for FAM scripts, and without it, the script will fail. You're recommended to use the appropriate user interface for running or generating FAM transactions and reports. The FAM process record is automatically created when scripts are triggered through the appropriate user interface.

Asset Register Report

This report lists cost, accumulated depreciation, and net book value for each asset between the periods selected. The system assumes that depreciation history records with blank Accounting Book fields are for the Primary Book. In the asset register report, these DHRs are displayed under the Primary Book.

The asset register report includes the following information:

- **Asset Type** — This shows the class or type where the asset belongs to.
- **ID** — This shows the asset ID.
- **Name** — This shows the name of the asset record.
- **Depreciation Start Date** — This shows the date when the asset depreciation started.
- **Asset Life** — This shows the life of the asset.
- **Beginning Balance** — This shows the balance of all assets before the report date. This column contains the following information:
 - **Beginning Cost** — This shows the asset's acquisition amount before the report start date
 - **Beginning Depreciation** — This shows the asset's accumulated depreciation before the report start date.
 - **Beginning Net Book Value** — This shows the asset's net book value before the report start date.
- **Acquisitions** — This shows the cost of all assets acquired within the report period.

 **Note:** If the asset is transferred to another class, department, or location, the Acquisition column shows the asset cost and the transferred amount.

- **Transfer** — This shows the current cost of the transferred asset.

- **Sale** — This shows the amount of assets sold during the report period.
- **Disposals** — This shows the amount of assets written off during the report period.
- **Depreciation** — This shows the accumulated depreciation within the report period.
- **Revaluation** — This shows the adjustment made to the asset due to revaluation.
- **Write Down** — This shows the asset's write down amount.
- **Lease** — This shows the lease adjustment amount. The previous period lease adjustment is considered in the computation of the cost beginning balance.
- **Net Book Value** — This shows the asset's net book value at the end of the report period.

Asset Summary Report

This report shows the total cost, depreciation, and net book value for the selected asset types over the specified period. The system assumes that depreciation history records with blank Accounting Book fields are for the Primary Book. In the asset summary report, these DHRs are displayed under the Primary Book.

The report has the following sections:

- The **Cost** section includes the following information:
 - **Beginning Balance** — This shows the balance of the asset types at the start of the report period.
 - **Additions** — This shows the cost of new assets acquired during the report period.
 - **Sale** — This shows the amount of assets sold during the report period.
 - **Disposal** — This shows the amount of assets written off during the report period.
 - **Revaluation** — This shows the write-off amount.
 - **Ending Balance** — This shows the balance of the asset types at the end of the report period.
- The **Depreciation** section includes the following information:
 - **Beginning Balance** — This shows the depreciation balance of the asset types at the start of the report period.
 - **Additions** — This shows the depreciation for the report period.
 - **Sale** — This shows the amount of assets sold during the report period.
 - **Disposal** — This shows the amount of assets written off during the report period.
 - **Revaluation** — This shows the depreciation adjustment.
 - **Ending Balance** — This shows the total depreciation of the asset types at the end of the report period.
- The **Net Book Value** section includes the following information:
 - **Beginning Balance** — This shows the net book value of the asset at the start of the report period.
 - **Ending Balance** — This shows the net book value of the asset at the end of the report period. You can calculate this as Asset Cost (ending balance) – Depreciation Ending Balance = NBV Ending Balance.
- The **Total NBV** section includes the following information:
 - **Additions** — This shows the additional asset acquisition and depreciation within the report period.
 - **Sale** — This shows the total sales adjustments within the report period.
 - **Disposals** — This shows the total write-off adjustment within the report period.
 - **Revaluation** — This shows the total revaluation adjustment within the report period. This is the sum of the write-down amount and depreciation adjustments.

- **Lease** — This shows the lease adjustment amount.

Depreciation Schedule Report (Net Book Value and Period Depreciation)

The depreciation schedule net book value report shows the asset's current value for the specified period. The depreciation schedule period depreciation report shows the total depreciation of each asset for the specified period. The system assumes that depreciation history records with blank Accounting Book fields are for the Primary Book. In the depreciation schedule report, these DHRs are displayed under the Primary Book.

The depreciation schedule report can also group and display the depreciation and net book values by 4-4-5 week periods. The report uses accounting periods as column headers instead of calendar months. You'll see this change in the report if the following conditions are met:

- The account uses the 4-4-5 Weeks accounting period.
- The **Use Accounting Period Dates For Depreciation** preference is enabled to record depreciation histories correctly. For more information, see [Fixed Assets General Preferences](#).

The depreciation schedule report includes the following information in the PDF/XML and CSV versions:

- **Asset Type** — This shows the asset's class or asset type.
- **ID** — This shows the asset ID.
- **Name** — This shows the asset's name.
- **Asset Life** — This shows the asset's lifespan.
- **Depreciation Method** — This shows the asset's depreciation method.
- **Periods** — This shows the asset's depreciation period. The maximum period is 12 months. For report periods over 12 months, the succeeding months are shown on the following pages.

 **Note:** The report supports the Calendar Months and 4-4-5 Weeks accounting period format. The 4 Weeks accounting period format, which has 13 periods, is not supported.

The period names match their column position in the report. For example, Period 1, Period 2, and so on. These are different from the names of the accounting periods. Period names are sourced from the Manage Accounting Periods page. For more information, see the help topic [Manage Accounting Periods Page](#).

The CSV version of the depreciation schedule report includes the following additional information:

- **Subsidiary** – Shows the asset's subsidiary.
- **Posting** – Shows whether the asset's depreciation method uses GL Posting.
- **Accounting Book** – Shows the accounting book associated with the depreciation histories.
- **Calendar Year** – Shows the year for the 12 periods that begin on January 1 and ends on December 31.
- **Financial Year** – Shows the label of the parent financial year record for the 12 periods. The financial year matches the calendar year if **Use Accounting Period Dates for Depreciation** is not enabled.

- **Financial Year ID** – Shows the internal ID of the parent financial year record. This column is blank if **Use Accounting Period Dates for Depreciation** is not enabled.

Data in the report will appear blank under the following conditions:

- The dates are outside of the selected start and end dates on the Generate Reports page.
- The accounting period is incomplete.
- The accounting period starts and ends on a month other than January and December.



Note: To view forecast amounts for depreciation, you can generate an asset depreciation schedule report for future periods.

When the **Use Accounting Period Dates for Depreciation** preference is enabled, you won't see forecast depreciation amounts for undefined accounting periods.



Important: If the Subsidiary has no amount for the report period, it's listed in the Subsidiary with zero value section.

Depreciation Monthly Report

The depreciation monthly report shows the depreciation expense for the period by asset, the asset records, and journal entries. The system assumes that depreciation history records with blank Accounting Book fields are for the Primary Book. In the depreciation monthly report, these DHRs are displayed under the Primary Book.

The depreciation monthly report includes the following information:

- **Date** — Shows the asset's last depreciation date.
- **Asset ID** — Shows the asset ID.
- **Asset Name** — Shows the asset's name.
- **Posting Reference** — Shows the journal entry information.
- **Transaction Amount** — Shows the depreciation amount.

Asset Listing Report (Anlagenspiegel)

The Asset Listing report shows the total acquisition or production costs, additions, disposals, transfers, and write-ups for the fiscal year. By default, it's an annual report set to the current year. Customers can also run the report monthly or quarterly.

The Asset Listing report follows the format for Germany's consolidated financial statements, as per the German Commercial Code. This report is designed for German accounts and subsidiaries, and available to users with Austria and Switzerland accounts.

The Asset Listing report includes the following information:

- **Asset Record** (Anlageposten) – Shows the asset name
- **Asset ID** (Anlagen-ID) – Shows the asset ID

- **Asset Type** (Anlagentyp) – Shows the asset's class or type.
- **Opening Balance – Cost** (Gesamtmte AK/HK) – Shows the beginning balance at the start of the report period
- **Acquisition** (Zugaenge) – Shows new acquisitions for the selected period
- **Disposals** (Abgaenge) – Shows disposals for the current year
- **Transfer** (Umbuchungen) – Shows the adjustments, including WiP to activated assets and interdepartmental transactions
- **Revaluation** (Zuschreibungen) – Shows the revaluation
- **Accumulated Depreciation** (Abschreibungen Kumuliert) – Shows the accumulated depreciation or YTD depreciation
- **Net Book Value** (Buchwert Abschlussjahre) – Shows the NBV for the current financial year
- **NBV Previous Years** (Buchwert Vorjahre) – Shows the NBV for the previous financial year
- **Depreciation** (Abschreibung Abschlussjahre) – Shows the current financial year depreciation

Schedule 16 Reports

Schedule 16 reports are supplemental documents used to calculate corporate tax and are available for Japanese accounts and accounts with a Japanese subsidiary. Schedule 16 reports only include posting DHRs. Assets with a lifespan of 1 or over 50 are excluded from these reports. The following Schedule 16 reports are available:

- **Schedule 16 (1)** - This report includes assets, leased assets, disposed, and fully depreciated assets using the Japan Straight-Line depreciation method. This report excludes leased assets that use the straight line depreciation method, and assets with Depreciation Active set to false.
- **Schedule 16 (2)** - This report includes assets, leased assets, disposed, and fully depreciated assets using the Japan 200% Declining Balance and Japan 250% Declining Balance depreciation methods. This report excludes leased assets that use the old declining balance method, and assets with Depreciation Active set to false.
- **Schedule 16 (4)** — This report includes all leased assets, disposed, and fully depreciated assets using the standard Straight Line depreciation method. This report excludes leased assets that use the Japan Straight Line and Japan Declining Balance depreciation methods, and assets with Depreciation Active set to false.

Asset Report Generation

The fixed asset reporting tool uses Advanced PDF format. This enables you to print, view, or download the report in CSV (for Depreciation Schedule Report), PDF, or XML format. To generate the fixed asset reports, you must enable the **Advanced PDF/HTML Templates** feature in Setup > Company > Enable Features > SuiteCloud.

Read the following topics to learn how to generate asset reports or export generated reports to an Excel file:

- [Generating Fixed Asset Reports](#)
- [Exporting Asset Reports to an Excel File](#)

Note: Fixed Assets Management doesn't currently support Depreciation Schedule Reports for assets with negative costs. For more information, see [Fixed Assets Report Preferences](#).

Important: Update depreciation history records for asset transfers with a 'Sale or Disposal' transaction type and no asset disposal type. Set the transaction type to 'Acquisition' and the transaction amount to a negative value. Asset transfers are shown as an Acquisition with a negative value on fixed asset reports.

Generating Fixed Asset Reports

To generate fixed asset reports:

1. Go to Fixed Assets > Reports > Generate Reports.
2. Provide values for the following fields:
 - **Report Type** — Select the report type to generate.
 - **Asset Register** — This report lists cost, accumulated depreciation, and net book value for each asset with the selected periods.

Note: In Fixed Assets Management version 4.01.2 and later, disposals generate two types of depreciation history records (DHR) — a 'Sale' DHR for assets sold and a 'Disposal' DHR for assets written off. The Asset Register saved search includes added columns for SALE and DISP.
 - **Asset Summary** — This report lists cost or valuation, depreciation, and net book value totals for selected asset types and periods.
 - **Depreciation Schedule Net Book Value** — This report shows each asset's current value for the period.
 - **Depreciation Schedule Period Depreciation** — This report shows each asset's total depreciation for the period.

Note: Generate an asset depreciation schedule report for future periods to view forecast depreciation amounts.
 - **Depreciation Monthly Report** — Shows the depreciation expense for the period by asset, including asset records and journal entries.
 - **Asset Listing Report** — Shows the total acquisition or production costs, additions, disposals, transfers, and write-ups for the fiscal year. This report is designed for German accounts and subsidiaries, and is also available to users with Austria and Switzerland accounts.
 - **Schedule 16 (1)** - This report shows assets, leased assets, disposed and fully depreciated assets that use the Japan straight line depreciation method.
 - **Schedule 16 (2)** - This report shows assets, leased assets, disposed and fully depreciated assets that use the Japan 200% declining balance and Japan 250% declining balance depreciation method.
 - **Schedule 16 (4)** — This report includes all leased assets, disposed and fully depreciated assets that use the standard Straight Line depreciation method.
 - **Show Components in Reports** — Check this box to view only the components on the report. Otherwise, clear this box to view only the parent compound asset on the report.

 **Note:** This option is only available for the Asset Register and Asset Listing Reports.

- **Save Report as CSV** — Check this box to save the generated report as a CSV file. Enabling this setting disables the XML or PDF output.

 **Note:** This option is only available for the Depreciation Schedule and Depreciation Monthly Reports.

- **Start Date** — Enter the start date for the report period.
- **End Date** — Enter the end date for the report period.
- **Assets to Include** — Select the assets to include in the report: All Assets, All Assets Except Leased, or Leased Only.

 **Note:** For Depreciation Monthly reports, this field is set to **All Assets**.

- **Alternate Depreciation** — Select the depreciation method.

 **Note:** Selecting **Accounting Method** sets the Accounting Book filter to **Primary Accounting Book**, and the Books to Include filter to **GL Posting**. This applies to all reports except the Depreciation Monthly report.

- **Asset Types** — Select one or more asset types to categorize assets. Default values are assigned to most of the asset configuration based on the asset type.

 **Note:** If no asset type is selected, the report also includes inactive asset types.

- **Subsidiary** — Select the subsidiaries for which you want to generate a report.
This field is available only for OneWorld accounts.
- **Include Children** — Check this box to include assets of the child subsidiaries in the report.
- **Accounting Books** — Select the accounting books for which you want to generate a report.

 **Note:** This field is available only if the **Multi-Book Accounting** feature is enabled in your account.

Selecting **None** generates a report with the following information:

- All depreciation history records for accounting methods and tax methods created before the Multi-Book feature was enabled.
- Tax methods not associated to an accounting book.
- **Books to Include** — Select to include **GL Posting**, **Non GL Posting**, or **Both** books in the report.

 **Note:** If you select Depreciation Monthly Report, this option is set to **GL Posting**.

- **Departments** — Select a department to include only its associated assets.
This field is available only if the **Departments** feature is enabled in your account.
- **Class** — Select a class to include only its associated assets associated.
This field is available only if the **Classes** feature is enabled in your account.
- **Location** — Select a location to only include its associated assets.

This field is available only if the **Locations** feature is enabled in your account.

3. Click **Generate**.

You'll be redirected to the Process Status page to track the report's progress. On the My Reports page (Fixed Assets > Reports > My Reports), you can view the generated report as PDF or XML. When viewing XML reports, use an application that can properly display XML files.

The My Reports page doesn't show failed reports.



Important: The report excludes manually created assets without depreciation history records and assets disposed before or after the report period.

To view a list of reports generated in the last 30 days, see [Viewing Fixed Asset Reports](#).

Exporting Asset Reports to an Excel File

To export asset reports:

1. Go to Fixed Assets > Reports > My Reports.
2. Right click the XML link for the report that you want to export to Excel, and save it to your computer.
3. Find the downloaded XML report on your computer, and then open it with Excel.



Note: You can set your web browser to use Excel as the default program to open XML files.

Fixed Assets Report Template

The Fixed Assets Management SuiteApp lets you customize the default report template to meet your company's requirements. You can customize report templates through XML manipulation or the user interface. Please read the following topics to learn more:

- [Customizing the Fixed Assets Report Template through the User Interface \(UI\)](#)
- [Customizing the Fixed Assets Report XML Template](#)
- [Mapping Asset Values to FAM Reports](#)

Customizing the Fixed Assets Report Template through the User Interface (UI)

Starting with Fixed Assets Management v19.1, you can customize the FAM report template through the user interface. You can add fields from the asset and alternate depreciation record to the following report templates:

- Asset Register Report
- Depreciation Monthly Report
- Depreciation Schedule NBV Report
- Depreciation Schedule PD Report

- Asset Listing Report

Custom columns added to the report template are also included in these CSV reports:

- Depreciation Monthly Report
- Depreciation Schedule NBV Report
- Depreciation Schedule PD Report

 **Note:** Custom columns won't appear on reports generated before the FAM 2024.1 upgrade. After upgrading to FAM 2024.1, resave your custom report templates. The update applies to your custom report template, even without modifications.

Customizing FAM Report Template through the UI

To customize FAM report template:

1. Go to Fixed Assets > Reports > Customize Report Template.
2. Set values for the following fields:
 - **Report Type** - Select the report template to customize.
 - **Set as Preferred Template** - Check this box to use the custom template for report generation.
 - **Paper Size** - Set the default paper size for this report template.
 - **Paper Orientation** - Set the orientation for the report template.
3. In the Customize Report sublist, click **Add Column** to add columns to the report template. Enter the following details in the dialog:
 - a. **Column Label** - Enter the column name as it should appear in the report.
 - b. **Show** - Check this box to display the field in the report.
 - c. **Source Record** - Select the source record for the field that you want to add.
 - d. **Source Field** - Select the field that you want to add.

You can only select custom fields with the **Store Value** option enabled on the custom field record. A message appears when saving a custom report with fields that don't use the **Store Value** option. To check if a custom field can store value, go to Customization > Record Type > Fields subtab.

 **Note:** Fields that the SuiteApp manually sources when generating the report data can still be used even if **Store Value** is not checked. For example, the **Currency** field in the FAM Asset and Alternate Depreciation record is excluded from the validation.

- e. Click **Save**.
You can add the same source field to the report template multiple times. The new field appears in the Customize Report sublist.
4. Click **View Column Information** to see all the columns included in the report template.
 5. Click **Preview** to see a sample report using your custom template.
The sample report is saved to your computer as a PDF file. The report includes sample data for each field and column.
 6. Click **Save** to create your template.

Reverting to the Standard FAM Report Template

To stop using the custom template for FAM reports, switch to the standard FAM report template. Reverting to the standard template removes all customizations that you applied.

To revert to the standard report template:

1. Go to Fixed Assets > Reports > Customize Report Template.
2. On the Customize FAM Report Template page, select the report type to revert to the standard template.
3. In the Customize Report Columns sublist, click **Revert to Standard Template**.
The system shows a preview of the standard report template. At this point, the changes are not yet applied.
4. Click **Save** to apply the changes.

Customizing the Fixed Assets Report XML Template



Important: Basic knowledge in Freemarker and XML is required to customize the report template.

Download the default report template and customize it to add or remove fields from the asset register and depreciation schedule reports.

Set the report template for generating fixed assets reports on the System Setup page.

Read the following help topics for more information on customizing the asset report template:

- [Supported Asset Fields](#)
- [Downloading the Default Asset Report Templates](#)
- [Adding a Placeholder for New Fields in the Asset Report](#)
- [Adding or Removing a Field from the Default Asset Report Template](#)
- [Setting a Custom Template for Asset Reports](#)

Supported Asset Fields

You can add or remove the following asset fields from the default report template:

Primary Information

- Asset Description
- Asset Serial Number
- Alternate Asset Number
- Parent Asset
- Project (Job)
- Accounting Method
- Depreciation Period

- Asset Lifetime Usage
- Asset Status
- Customer Location

General Tab

- Department
- Class
- Location
- Custodian
- Physical Location
- Purchase Date
- Depreciation End Date
- Last Depreciation Period
- Last Depreciation Date
- Target Depreciation Date
- Depreciation Active
- Depreciation Rules
- Revision Rules
- Manufacturer
- Date of Manufacture
- Supplier
- Purchase Order
- Parent Transaction
- Prior Year NBV
- Fiscal Year Start
- Annual Method Entry

Downloading the Default Asset Report Templates

To download the default asset report templates:

1. Go to Documents > Files > File Cabinet.
2. On the left navigation pane, click SuiteBundles > Bundle 508242 > src > resource.
3. From the resource folder, click the **Download** link for the report template that you want to customize:
 - **Asset Listing Report** – FAM_ListingReport_Template.xml
 - **Asset Register Report** – FAM_RegisterReport_Template.xml
 - **Asset Summary Report** – FAM_SummaryReport_Template.xml
 - **Depreciation Schedule Report** – FAM_ScheduleReport_Template.xml
 - **Depreciation Monthly Report** – FAM_DeprMonthlyReport_Template.xml

To begin customizing the default asset report templates, follow these steps in the order shown:

1. [Adding a Placeholder for New Fields in the Asset Report](#)
2. [Adding or Removing a Field from the Default Asset Report Template](#)
3. [Setting a Custom Template for Asset Reports](#)

Adding a Placeholder for New Fields in the Asset Report

The report line custom record connects the asset record to the report. Each entry in the custom record represents a line item in the asset report. Adding a field to this custom record creates a placeholder for the asset value in the report.

To add a field to the report line custom record:

1. Go to Customization > List, Records, & Fields > Record Types.
2. Click the report line record for the report template you want to customize.
 - **FAM Asset Register Rep Line** – for Asset Register and Asset Listing report
 - **FAM Depreciation Schedule Report Line** – for Asset Depreciation Schedule report
 - **FAM Depreciation Monthly Report Line** – for Depreciation Monthly report
3. On the Custom Report Type page, click **New Field** in the Fields subtab.
4. On the FAM Asset Register Rep Line Field or the FAM Depreciation Schedule Report Line Field page, provide values for the following fields:
 - **Label** – Enter the label of the new field that will appear on the report
 - **ID** – Enter a unique ID for the field. The ID will be used to add the field to the report template.
 - **Type** – Select a field type similar to the asset field you're adding. See the following table for sample values:

Asset Field	Type	List/Record
Asset Description	Free-Form Text	
Accounting Method	List/Record	FAM Depreciation Method
Lifetime Usage	Integer Number	
Depreciation End Date	Date	

- **List/Record** – If the Type is List/Record, select the corresponding list or record for the asset field that you're adding.
 - **Store Value** – Check this box.
 - **Show in List** – Check this box.
5. On the Sourcing & Filtering subtab, provide values for the following fields:
 - **Source List** – Select **Source Asset**.



Important: To ensure that the field you're adding gets its value from the asset record, the Source List must always be set to **Source Asset**.

- **Source From** – Select the asset field to use as a value source for the new field.
- For example, select **Asset Status** if you want the new field to display the status of the asset on the report.
6. Click **Save**.
 7. Repeat steps 3 to 6 to add more fields to the report line custom record.

Adding or Removing a Field from the Default Asset Report Template

Note: Use the following procedure to customize the asset report templates.

To add or remove a field from the default report template:

1. Open the default asset report template that you want to modify.
2. Find the asset loop in the default template.

In the asset register template, this starts with `<#list report.recmachcustrecord_assetregister_reparent as line>` and ends with `</#list>`.

```
<body size="A4-landscape">
  <#assign lineIndex = 0>
  <#assign listSize = report.recmachcustrecord_assetregister_reparent?size>
  <#list report.recmachcustrecord_assetregister_reparent as line>
    <#assign lineIndex = lineIndex + 1>
    <#assign lineType = line.custrecord_assetregister_linetype>
    <#if lineType == "sub_header">
      <p style="font-size: 18px; color: #003399">ARR_title_ARR</p>
```

In the depreciation schedule template, this starts with `<#list report.recmachcustrecord_fam_schedrepline_parent as line>` and ends with `</#list>`.

```
<#list report.recmachcustrecord_fam_schedrepline_parent as line>
  <#assign lineIndex = lineIndex + 1>

  <#if (subsidiary != "" && subsidiary != line.custrecord_fam_schedrepline_subsidiary) ||
    (book != "" && book != line.custrecord_fam_schedrepline_book) ||
    (year != "" && year != line.custrecord_fam_schedrepline_year) ||
    (type != "" && type != line.custrecord_fam_schedrepline_type)>

    <tr>
      <td colspan="6"></td>
      <td colspan="12" style="border-top-style: solid; border-top-width: 1px;"
        margin-bottom="1px"></td>
    </tr>
```

3. In Freemarkter notation, add a new variable inside the asset loop of the default template. Add a 'line' prefix to the new field's ID.

For example, if the ID is **custrecord_ds_cust_asset_status**, this appears in the template as: `#{line.custrecord_ds_cust_asset_status}`.

```
<tr>
  <td><p align="left">#{line.custrecord_fam_schedrepline_assetid}</p></td>
  <td><p align="left">#{line.custrecord_fam_schedrepline_assetname}</p></td>
  <td><p align="left">#{line.custrecord_fam_schedrepline_assetlife}</p></td>
  <td><p align="left">#{line.custrecord_fam_schedrepline_method}</p></td>
  <td><p align="left">#{line.custrecord_ds_cust_asset_status}</p></td>
  <td><p align="right">
    #{line.custrecord_fam_schedrepline_p1?string["#",##0.00;(#,##0.00)"]}
  </p></td>
```

4. Add more variables for each field that you want to add to your template.
5. To remove a field from the report template, delete the variable that contains the field's ID.
6. Save your custom template.

To ensure that the system recognizes your custom template, add the following report name prefixes to the custom template filename:

- **FAM_AR** – for asset register report template (for example, FAM_AR_CustomTemplate.xml)

- **FAM_AS** – for asset summary report template (for example, FAM_AS_CustomTemplate.xml)
 - **FAM_DS** – for depreciation schedule report template (for example, FAM_DS_CustomTemplate.xml)
 - **FAM_DM** — for Depreciation Monthly report template (for example, FAM_DM_CustomTemplate.xml)
 - **FAM_AL** — for Asset Listing report template (for example, FAM_AL_CustomTemplate.xml)
7. Upload your custom template to the file cabinet.

Mapping Asset Values to FAM Reports

When customizing the asset report templates, make sure that the Asset Values record is updated accordingly. If you added the following fields in your asset report template, edit the report line to update the source values:

- Current Net Book Value
- Last Depreciation Amount
- Last Depreciation Date
- Last Depreciation Period
- Prior Year NBV

To change the values on the rep line of the depreciation monthly report:

1. Go to Customization > Lists, Records & Fields > Record Types.
2. On the Custom Record Type page, click **FAM Depreciation Monthly Report Line**.
3. On the Fields subtab, click the custom field added for any of the following:
 - Current Net Book Value
 - Last Depreciation Amount
 - Last Depreciation Date
 - Last Depreciation Period
 - Prior Year NBV
4. On the Sourcing & Filtering subtab, set the values for the following fields:
 - **Source List** — Select **Source Asset Values**.
 - **Source From** — Select the field to use as a value source.
5. Repeat Step 4 for each field mentioned above, if you have added them in FAM reports.

Setting a Custom Template for Asset Reports

To set a custom template for asset reports:

1. Go to Fixed Assets > Setup > System Setup.
2. On the Reports subtab, select a custom template for asset reports in these fields:
 - Preferred Asset Register Template
 - Preferred Asset Summary Template
 - Preferred Depreciation Schedule NBV Template

- Preferred Depreciation Schedule PD Template
- Preferred Depreciation Monthly Template
- Preferred Asset Listing Template

 **Note:** You can select custom templates in the corresponding fields if you added a report name prefix to the custom template file name.

3. Leave the field blank to use the default report template.
4. Click **Save**.

The system uses your preferred templates to generate asset reports. For more information about generating asset reports, see [Generating Asset Reports](#).

Viewing Fixed Asset Reports

You can view a list of reports generated for the past 30 days from the My Reports page.

To view fixed asset reports:

1. Go to Fixed Assets > Reports > My Reports.
Reports are displayed in reverse chronological order.
2. Click the **Date Generated** link to view or download the report.
3. If you have sufficient permission, you can click **Delete Report** to delete a report.
To delete multiple reports, check the boxes beside the reports or click **Mark All**, and click **Delete**.
4. If you are an account administrator, click **Show All Reports** to view all the reports generated on your account.

 **Note:** This option is available when you enable the **Allow Administrator to View All Reports** preference from Fixed Assets > Setup > System Setup.

Fixed Assets Saved Searches

The Fixed Assets Management SuiteApp provides the following saved searches that you can customize and export:

- [Standard Fixed Asset Saved Searches](#)
- [Additional Fixed Asset Saved Searches](#)



Note: To customize a saved search, open it from Fixed Assets > Searches, and then click **Edit this Search**.

When you customize FAM saved searches or create your own, make sure the following fields are sourced from the Asset Values record:

- Current Net Book Value
- Last Depreciation Period
- Last Depreciation Date

Check the Results tab on your custom saved search to ensure that the fields are sourced from the correct record. Otherwise, your saved search may return the wrong values.

For more information about Saved Searches, see the help topic [Saved Searches](#).

Standard Fixed Asset Saved Searches

These are available at Fixed Assets > Searches.

- **Additions** – Shows new asset purchases.
- **Disposals** – Shows assets that are disposed, sold, and written off.
- **Asset List** – Shows each asset's Net Book Value for a specific date.
- **Asset Register** – Shows the Net Book Value for a specific date, but with different columns.
- **Proposal History** – Shows the asset proposal activity.
- **Inspections Due** – Shows assets with maintenance schedules and their inspection due dates.
- **Insurance Renewals Due** – Shows assets with insurance renewal due dates.
- **Expiring Leased Assets** – Shows the expiry dates of leased assets.

Additional Fixed Asset Saved Searches

The following saved searches are also available at Lists > Search > Saved Searches:

- FAM Default Alternate Depreciation Sublist View
- FAM Non-Posting Alternate Depreciation with Book
- FAM Non-Posting Proposal Alternate Depreciation with Book
- FAM Non-Posting Default Alternate Depreciation with Book
- FAM Default Alternate Depreciation w/o Books
- FAM Proposal Alternate Depreciation w/o Books

- FAM Proposal Alternate Depreciation Sublist View
- FAM Alternate Depreciation w/o Books
- FAM Lease Payments for Schedule Generation
- FAM Lease Schedule Preview
- FAM Administrator Email

Lease Accounting Reports

The following saved searches are available for Lease Accounting:

- [Lease Liability Detail Report](#)
- [Right-of-Use Asset Listing Report](#)
- [Short Term Lease Liability Report](#)
- [Long Term Lease Liability Report](#)

Lease Liability Detail Report

This report shows details about your lease liability. You can filter the reporting period by lease start date, accounting book, or subsidiary. The report shows the current period by default, but you can set the date range.

The following information is available in the lease liability detail report:

- Lease Start Date
- Number (Document Number)
- Transaction
- Lease Liability Account
- Lease Company
- Total Lease Liability
- Total Interest

Right-of-Use Asset Listing Report

- This report lists all leased assets. You can filter the report to show assets under an operating or finance lease.

The following information is available in the right-of-use asset listing report:

- ID
- Asset Name
- Lease Start Date
- Lease End Date
- Lease Term
- Total Net Present Value
- Total Lease Payments
- Finance Lease

Short Term Lease Liability Report

This report shows details for short term lease liability, which is the total principal amount for the current fiscal year.

The report shows active leases with the following information for the current fiscal year:

- Lease Liability Account
- Lease Company (Vendor)
- Asset
- Sum of Liability (Principal)

Long Term Lease Liability Report

This report shows the details for long term lease liability, which is the total principal amount on or after the start of the next fiscal year.

The report shows active leases with the following information for the next fiscal year:

- Lease Liability Account
- Lease Company
- Asset
- Principal

Managing Fixed Assets Scripts

Fixed Assets Management transactions trigger background scripts that require a SuiteCloud processor to run. If no processor is available, the script is queued until one becomes available.

Scripts are processed according to their order in the queue (first in, first out) and their priority level (highest to lowest priority).

Fixed Assets Management Script Priority

Fixed Assets Management transactions and report generation processes are managed by scheduled scripts and process records. A process management tool controls the order and execution of these scripts to ensure everything runs in the correct sequence. However, unrelated scripts may interrupt the sequence and interfere with the SuiteApp's process execution. To ensure that FAM transaction processes run smoothly, you can set a higher priority level for FAM script deployments.

To learn more about prioritizing FAM scripts, read the following topics:

- [Prerequisites for Prioritizing FAM Scripts](#)
- [Setting a Priority for FAM Scripts](#)



Note: FAM scripts have a Standard Priority level by default.

Prerequisites for Prioritizing FAM Scripts

- The Priority on the following script deployments must be set to High:
 - **FAM Trigger Process SS** (customdeploy_fam_triggerprocess_ss)
 - **FAM Process Manager SS** (customdeploy_fam_processmanager_ss)
- The scheduled script that manages the process must be prioritized as well. For more information, see [Background Processing of Fixed Assets](#).



Important: The bundle update preference for most FAM scripts are set to **Update Deployments**. When the SuiteApp is updated, the script priority that you set will be updated to the value in the source account. This issue is currently being addressed. Until the issue is resolved, you must prioritize the FAM scripts again after the SuiteApp is updated.

Setting a Priority for FAM Scripts

To set a priority for FAM scripts:

1. Go to Customization > Scripting > Script Deployment, and then click **Edit** next to the record that you want to modify.
2. On the Script Deployment record, set the **Priority** field to **High**.
3. Click **Save**.

Repeat steps 1–3 for all scripts that you want to prioritize. To view a list of scripts, go to Customization > Scripting > Scripts. Expand the filter on the Scripts page, and in the **From Bundle** list, select the ID of the latest FAM SuiteApp version.

Changing the Scheduled Script Runtime

Fixed Assets Management system runs scripts on a regular schedule. You can change the schedule of some scripts if you'd like to run them more often.

To change the scheduled script runtime:

1. Go to Customization > Scripting > Script Deployment.
2. On the Script Deployments page, click the **Edit** link for the script you want to update:
 - **FAM Trigger Pre-Compute SS** (ID: customdeploy_fam_triggerprecompute_ss) — This script runs every Sunday, by default. Select this script to update the runtime for generating a depreciation schedule.
 - **FAM Trigger Reset Process (Scheduled) SS** (ID: customdeploy_fam_triggerresetsched_ss)— This script runs daily, by default. Select this script to update the runtime for the Asset Reset process.
 - **FAM Trigger Reports Cleanup SS** (ID: customdeploy_fam_trigrptcleanup_recur_ss)— This script runs daily, by default. Select this script to update the runtime for the Clean Up Report process.
3. On the Schedule subtab, check the day of the week when you want the script to run, and select a start time.
4. Click **Save** or **Save and Execute** to save the changes and run the script.

 **Note:** The scripts only process asset records that need a reset or a depreciation schedule.

Updating Script Deployment Settings for Suitelets Available Without Login

Setting Suitelets to be available without login gives users access to the Suitelet and run scripts without logging in. For sample use cases and more information, see the help topic [Setting Available Without Login](#).

Starting 2025.1, script deployment audience settings now distinguish between external and internal roles. For more information, see [Changes to Audience Settings in Script Deployment Records and Single Page Applications](#).

Due to this update, you may notice changes in your account—such as updates to system information—that could affect custom approval workflows. To avoid issues while using the SuiteApp, set **Online Forms User** as an external role in the script deployment record.

 **Note:** Before completing the following steps, make sure you enabled the **Online Forms** feature. For more information, see the Prerequisites section in [Installing the Fixed Assets Management SuiteApp](#).

To add Online Forms User as an external role in the script deployment record:

1. Go to Customization > Scripting > Script Deployments.
2. On the Script Deployments page, locate the **FAM Trigger Process SU** script deployment record (ID: customdeploy_fam_triggerprocess_su), and click the **Edit** link next to it.
3. Under the Audience subtab of the Script Deployment record, select **Online Forms User** in the **External Roles** field.
4. Click **Save**.

Running the Migration Script to Update the Fixed Assets Management SuiteApp

To reduce errors during an update, make sure you run a successful depreciation before migrating to the new system.

If you still encounter errors, you'll receive an e-mail explaining the issue. You'll need to fix the error manually, then run the migration script again.

To manually run the migration script:

1. Go to Customization > Scripting > Scripts.
2. Find the script, **FAM Write Summary Record SS (Migrate)**, and then click **Deployments**.
3. Click **Edit** to open the Edit Script Deployment Page.
4. From the Save options, select **Save & Execute**.

Fixed Asset Error Recovery Script

You may sometimes encounter system errors during a depreciation run. The cause of the error and the specific process where the error occurred are available in the Process Status page. You can modify these scripts to fix the error. For more information, read the following topics:

- [Modifying the Script Deployment to Create Summary Records](#)
- [Modifying the Script Deployment to Update Asset Values](#)

Modifying the Script Deployment to Create Summary Records

If an error was caused by missing summary records, you can modify a script to create the summary records.

To modify the script deployment:

1. Go to Customization > Scripting > Scripts.
2. In the Filters pane, set the Type to **Scheduled**.

3. Click the **View** link next to **FAM Trigger Error Handling SS**.
4. On the Script page, click the **Deployments** subtab, and then click **FAM Trigger Error Handling SS** to view the deployment record.
5. On the Script Deployment page, click **Edit**.
6. Click the Parameters subtab, and then set **Type** to **Check Summaries**.
7. Click **Save and Execute**.

Modifying the Script Deployment to Update Asset Values

If an error occurred on the fourth stage of Asset Depreciation (Update Asset Records), you can modify and run the recovery script to update the asset values.

To modify the script deployment:

1. Go to Customization > Scripting > Scripts.
2. In the Filters pane, set the Type to **Scheduled**.
3. Click the **View** link next to **FAM Trigger Error Handling SS**.
4. On the Script page, click the **Deployments** subtab, and then click **FAM Trigger Error Handling SS** to view the deployment record.
5. On the Script Deployment page, click **Edit**.
6. Click the Parameters subtab, and then set **Type** to **Asset Update**.
7. Click **Save and Execute**.

Background Processing of Fixed Assets

To optimize application and database servers, mechanisms have been implemented to manage SuiteScript usage. SuiteScript thresholds are based on the volume of activity that a company's users can manually generate, as well as a provision for automated functions.

That's why FAM transactions and report generation processes run in the background, managed by scheduled server scripts and process records.

Read the following topics for more information:

- [Process Status Page](#)
- [Process Stage Details](#)
- [Process List](#)
- [Fixed Assets Custom Plug-In](#)
- [Scheduled Server Scripts for Controlling Asset Transactions](#)

Process Status Page

To view the status of a process, go to the Process Status page (Fixed Assets > Background Processing > Status).

FAM Process Status List							
Refresh							
#	Internal ID	Process Name	Date Created	Status	Process Stage	Details	Errors
1	170725	Clean Up FAM Reports	1/12/2025 3:01 pm	Completed		Details	
2	170625	Generate Depreciation Schedule	1/12/2025 12:01 am	Completed		Details	
3	170528	Reset Asset Values	1/6/2025 3:06 pm	Completed		Details	
4	170527	Check FAM Diagnostics Scan Preferences	1/6/2025 3:06 pm	Completed		Details	
5	170526	Check FAM Post-Upgrade Processes	1/6/2025 3:06 pm	Completed		Details	
6	170525	Data Migration	1/6/2025 3:06 pm	Completed		Details	
7	170425	Generate Depreciation Schedule	1/5/2025 12:02 am	Completed		Details	
8	170327	Check FAM Diagnostics Scan Preferences	1/3/2025 8:23 pm	Completed		Details	
9	170326	Check FAM Post-Upgrade Processes	1/3/2025 8:22 pm	Completed		Details	
10	170325	Data Migration	1/3/2025 8:22 pm	Completed		Details	
11	170228	Reset Asset Values	1/3/2025 10:50 am	Completed		Details	

Note: The process status page displays the 20 most recent processes.

The following table describes each column on the Process Status page:

Column	Description
Internal ID	Click the internal ID to open the FAM process record, and view more details about the selected process.
Process Name	Identifies the process that was triggered.
Date Created	Shows the date when the process was triggered.
Status	Shows the current status of the process: ■ Queued – The process is waiting for another process (that's currently running) to finish. ■ In Progress – The process is currently running. Only 1 process may be in progress at any time. ■ Deferred – The Generate Depreciation Schedule process, triggered by the precompute scheduled script, may be delayed if another transaction is queued. The deferred process will be resumed when the queue is clear. ■ Completed – The process was successfully completed with no errors ■ Completed with Errors – The process was completed, but some errors occurred. Click the Error link to view details. ■ Failed – The process was not completed. Click the Error link to view details.
Process Stage	Shows the process stage that's currently running. The process stage is visible only when the process is currently running.
Details	Click the Details link to view details about the specific stages in the process. For more information, see Process Stage Details .
Errors	Processes with a status of Failed or Completed with Errors are highlighted in red. You can click the Error link to view details.

Process Stage Details

FAM Process Stage Details for ID: 63250, Name: Asset Depreciation							
Refresh							
#	Process Stage	Date Created	Status	Start	End	Message	Errors
7/7	Update Related Records	12/9/2024 2:21:01 pm	Not Required				
6/7	Update Compound Assets	12/9/2024 2:21:01 pm	Not Required				
5/7	Update Tax Methods	12/9/2024 2:20:47 pm	Completed	12/9/2024 2:20:49 pm	12/9/2024 2:20:59 pm	Tax methods updated: 11	
4/7	Update Asset Records	12/9/2024 2:20:31 pm	Completed	12/9/2024 2:20:32 pm	12/9/2024 2:20:45 pm	Assets/Tax methods updated: 20	
3/7	Prepare Data to Update Records	12/9/2024 2:20:21 pm	Completed	12/9/2024 2:20:22 pm	12/9/2024 2:20:30 pm		
2/7	Create Journal Entries	12/9/2024 2:20:00 pm	Completed	12/9/2024 2:20:02 pm	12/9/2024 2:20:20 pm	Transactions created: 4	
1/7	Generate Depreciation Schedule Values	12/9/2024 2:20:00 pm	Not Required				

Column	Description
#	Shows the total number of stages in the process and their order in the queue.
Process Stage	Show the specific stages of the process.
Date Created	Shows the date when the process stage was triggered.
Status	Shows the current status of the process stage: ■ Not Required – The process stage was skipped. ■ Queued – The process stage is waiting for another process (that's currently running) to finish. ■ In Progress – The process stage is currently running. Only 1 process may be in progress at any time. ■ Deferred – The Generate Depreciation Schedule process, triggered by the precompute scheduled script, may be delayed if another process is queued. The deferred process will be resumed when the queue is clear. ■ Completed – The process stage was successfully completed with no errors ■ Completed with Errors – The process stage was completed, but some errors occurred. Click the Error link to view details. ■ Failed – The process stage was not completed. Click the Error link to view details.
Start / End	The Start and End columns show how long the process stage took to complete.
Message	Shows the number of files or records the process stage created or updated.
Errors	The process stages with a status of Failed or Completed with Errors , are highlighted in red. You can click the Error link to view details of the problem that occurred.

When you are processing large volumes of data or records, you may see duplicate entries of the same process.

Process List

You can check a process' status by viewing its corresponding FAM Process record in the FAM Process List.

To view the process record:

1. Go to Fixed Assets > Background Processing > FAM Process List.
The **Status** column shows the current state of the background process.

2. Click the **View** link next to the required record to see more details.

Fixed Assets Custom Plug-In

Starting with Fixed Assets Management 2017.2, the custom plug-in **nsFamObject** applied to FAM asset transactions (Proposal, Creation, Revaluation, and Disposal) is no longer supported. The plug-in uses BG Process architecture, which was replaced by FAM Process Manager in version 2017.2.

Scheduled Server Scripts for Controlling Asset Transactions

To view the status of the scheduled scripts controlling asset transactions, go to Setup > Customization > Script Deployments > Status.

Viewing Script Error Notification Settings for Fixed Assets Management

The following table lists the default notification setting for each type of FAM script:

FAM Script Type	Notification Setting
Client	Notify Current User
Suitelet	Notify Current User
User Event (UE)	Notify Current User
Scheduled	Notify All Admins
Bundle Installation	Notify All Admins

 **Note:** All FAM scripts are locked. The notification settings cannot be changed.

To view the notification setting for a FAM script:

1. Go to Customization > Scripting > Scripts.
2. On the Scripts page, click **View** next to the script whose settings you want to view.

 **Note:** You can use the filters at the top of the page to refine the list on the Scripts page.

3. On the Script page, click the **Unhandled Errors** subtab. The selected option shows which notification is used for script errors:
 - **Notify Current User** – NetSuite sends an email to the currently logged-in user.
 - **Notify All Admins** – NetSuite sends an email to all users with the Administrator role.

 **Note:** The **Notify Script Owner**, **Notify Group**, and **Notify Emails** settings are currently not in use.

Multi-Book Accounting for Fixed Assets Management

The Multi-Book Accounting add-on for Fixed Assets Management lets you assign assets to multiple books. The asset values are automatically converted to the base currency of the book where the asset is recorded.

Multi-Book Accounting for Fixed Assets Management provides the following features:

■ **Parallel Currencies**

With Parallel Currencies, each book in a subsidiary has its own base currency. This feature allows subsidiaries in different countries to manage foreign business transactions in multiple currencies.

Fixed assets are recorded using the historical foreign currency rate. The initial conversion from the transaction currency to the base currency uses different base currencies and exchange rates. When you acquire an asset, its value in the subsidiary is recorded using the daily spot rate on the acquisition date. Then, throughout the asset's life, all depreciation calculations are based on the base currency amount.

For example, your base currency is USD, you acquire an asset for GBP 100 with a daily rate of 1.5USD per GBP. With Parallel Currencies, the asset value is recorded as USD 150. If the subsidiary has a secondary book with a different base currency, the original asset value is also converted to the secondary book's base currency.

■ **Record Assets in Multiple Books**

Multi-Book Accounting lets you assign an asset to multiple depreciation books that generate journal entries for different general ledger books, or to the same set of books. Each book can have unlimited depreciation methods per asset record.

Read the following topics for more information about Multi-Book Accounting for Fixed Assets Management:

- [Setting Up Multi-Book Accounting for Fixed Assets Management](#)
- [Managing Assets in Multiple Books](#)

Setting Up Multi-Book Accounting for Fixed Assets Management

To set up multi-book accounting for Fixed Assets Management, read the following topics:

- [Prerequisites for Fixed Assets Multi-Book Accounting](#)
- [Roles and Permissions for Fixed Assets Multi-Book Accounting](#)
- [Updating Depreciation History Records](#)

Prerequisites for Fixed Assets Multi-Book Accounting

You must perform the following tasks before proceeding:

- Enable the **Multi-book Accounting** feature. Contact your account representative or NetSuite Professional Services to find out how to get Multi-Book Accounting.
- Set up an accounting book. For more information, see the help topic [Multi-Book Accounting Overview](#).

Roles and Permissions for Fixed Assets Multi-Book Accounting

If you're using a custom role with Multi-Book Accounting for Fixed Assets Management, set the **Accounting Book** permission to **View**. This enables custom roles to set up accounting books. For more information, see the help topic [Roles and Data Access for Multi-Book Accounting](#).

Updating Depreciation History Records

The asset register report groups the depreciation history records by accounting book. To include entries without an accounting book, you must update your depreciation history record through mass update or CSV import.



Note: When you enable Multi-Book Accounting for the first time in your account, all historical depreciation journals are automatically updated to Primary Accounting Book.

Updating Depreciation History Records through Mass Update

To update depreciation history records through mass update:

1. Go to Lists > Mass Update > Mass Updates.
2. Expand General Updates, then under Custom Records, click the **FAM Depreciation History** link.
3. In the Criteria subtab, add the following filters:
 - **Accounting Book** - Select **None** to update only the depreciation history records with blank accounting books.
 - **Alternate Method** - Select **None** to update only the depreciation history records for the asset's accounting method.
4. In the Mass Update Fields subtab, check the **Accounting Book** field, and then set the value to **Primary Accounting Book**.
5. Click **Preview**.
6. Click **Perform Update**.

Updating Depreciation History Records through CSV Import

To update depreciation history records through CSV import:

1. Prepare an import file by creating a saved search for depreciation history records.
 - a. Go to Lists > Search > Saved Searches > New.

- b. On the New Saved Search page, click the FAM Depreciation History link.
 - c. In the Criteria subtab, add the following filters:
 - **Accounting Book** - Select **None** to update only the depreciation history records with blank accounting books.
 - **Alternate Method** - Select **None** to update only the depreciation history records for the asset's accounting method.
 - d. Click **Preview**, and then export the search results to CSV. For more information, see the help topic [Exporting Search Results](#).
 - e. Edit the CSV file to add a column for **Accounting Book**, and then set the value to **Primary Accounting Book**.
 - f. Save the CSV file.
2. Import CSV file for depreciation history record.
- a. Go to Setup > Import/Export > Import CSV Records.
 - b. In the Import Assistant Step 1 – Scan & Upload CSV File screen:
 - From the **Import Type** list, select **Custom Records**.
 - From the **Record Type** list, select **FAM Depreciation History**.
 - Select the CSV file to upload.
 - Click **Next**.
 - c. In the Import Assistant Step 2 – Import Options screen:
 - Set Data Handling to **Update**.
 - Click **Next**.
 - d. In Import Assistant Step 4 – Field Mapping screen:

Map the fields in your CSV file to the NetSuite fields. Review the both sets of fields to ensure that all required fields are mapped correctly. Make sure that the Internal ID mapping type is set to **Internal ID**.

- e. In the Import Assistant Step 5 – Save Mapping and Start Import screen:
 - Enter an **Import Map Name** and **Description**.
 - Click **Save & Run**.

Managing Assets in Multiple Books

Read the following topics to learn more about managing assets in multiple books:

- [Defining Asset Accounts and Values for Multiple Books](#)
- [Assets and Accounting Books in Multi-Book Accounting](#)
- [Asset Proposal](#)
- [Running Depreciation on an Accounting Book](#)
- [Transferring Fixed Assets Within Multi-Book Accounting](#)
- [Revaluing an Asset in Multiple Books](#)
- [Disposing an Asset in Multiple Books](#)
- [Splitting an Asset in Multiple Books](#)

Defining Asset Accounts and Values for Multiple Books

General ledger accounts on the Accounts tab of the Asset Type record store the primary book values. For more information about defining asset accounts, refer to [Asset Type Accounts Subtab](#).

The screenshot shows the 'FAM Asset Type' record for 'Furniture & Fixtures'. The top navigation bar includes links for Activities, Transactions, Lists, Reports, Analytics, Documents, Setup, and Customization. The record header shows 'FAM Asset Type' and 'Furniture & Fixtures' with navigation arrows. Below the header are buttons for 'Edit', 'Back', and 'Actions'. The record details include: Name (Furniture & Fixtures), Inactive checkbox, Description, Accounting Method (Straight Line), Residual Percentage (12,0%), Asset Lifetime (48), and Operating Lease checkbox. The 'Accounts' subtab is selected, showing a table of asset and depreciation accounts.

Notes	General	Accounts	Maintenance	Other Methods	Lifetimes
Asset Account		Furniture & Fixtures			Write Off Account
Depreciation Account		Acc. Dep-Furniture & Fixtures			Miscellaneous Expense
Depreciation Charge Account		Depreciation Expense			Write Down Account
					Miscellaneous Income
					Disposal Cost Account
					Gain (loss) on Sale of Assets

The Accounts subtab in the FAM Default Alternate Depreciation tab stores the secondary book general ledger accounts. You can link existing FAM default alternate depreciation to an accounting book by assigning a Book ID and populating other secondary book fields.

Changes to saved default alternate depreciation are prospective. Existing assets using the old default alternate depreciation won't be affected. You can override the alternate depreciation for default asset types in the Depreciation History subtab of the asset record. For more information, see [Depreciation History Subtab](#).

The **Other Methods** subtab in the Asset Type record appears only after you save the record.

Note: You can set different depreciation methods per accounting book.

Assets and Accounting Books in Multi-Book Accounting

You can link new and depreciating assets to an accounting book. The Asset Original Cost, Current Cost, Current Net Book Value, Prior Year NBV, and Cumulative Depreciation values are converted to the base currency of the book they're linked to. The depreciation amount is calculated based on the converted amount. For more information, see [Linking Accounting Books to an Asset](#).

Fully depreciated and disposed assets can't be linked to an accounting book. For most FAM records, you can only select secondary books in the Accounting Book field.

The Depreciation History subtab stores secondary book values. The secondary book might use a different base currency from the primary book. If both books share the same base currency, they'll have the same default values. You can override these default values by editing the asset record.

The acquisition history record is automatically created when you set a depreciation start date. The acquisition value is based on the asset amount in the primary book, multiplied by the secondary book's base currency exchange rate at the depreciation start date.

If the asset is partially depreciated for the accounting method only, and you add a new tax method to an accounting book, the system creates monthly depreciation history records with journal entries. If you run depreciation on closed periods, the system posts the journal entries to the next open period.

If the asset is partially depreciated for both accounting and tax methods, a new depreciation history is created based on the last depreciation date. The system doesn't create catch-up depreciation histories. You must manually create a book-specific journal entry for the cumulative depreciation.

Note: When you depreciate a tax method, the system uses the accounting book's base currency, not the currency of the asset's subsidiary.

OneWorld accounts can set the book base currency in the **Currencies** tab of the Subsidiary record. For more information, see the help topics [Creating Subsidiary Records](#) and [Foreign Currency Management](#).

Linking Accounting Books to an Asset

To link an accounting book to an asset:

1. Go to Fixed Assets > Lists > Assets, and then click the **Depreciation History** subtab.
2. In the **Depreciation History** subtab, do one of the following:
 - To create a new alternate depreciation, click **New FAM Alternate Depreciation**.
 - To edit an existing alternate depreciation, click the **Edit** link next to the alternate depreciation.
3. In the FAM Alternate Depreciation page, select the **Accounting Book** that you want to link to this alternate depreciation.

You can only link active books to alternate methods. If an alternate depreciation is already linked to an accounting book, you can no longer change the Accounting Book value.

Note: If you select a value for the **Accounting Book** field, the Currency field is sourced from the subsidiary's book base currency. If the **Accounting Book** field is blank, the Currency field is sourced from the subsidiary's primary book.

4. In the **Alternate Method** list, select the depreciation method to use. The system automatically populates other values on the form. These values are sourced from the Asset Type record.
 Asset values on the form, such as Asset Cost and Net Book Value, is sourced from the Asset Record. This value is converted to the base currency of the secondary book. Values under the **General** tab are sourced from the Asset Record and values on the **Accounts** subtab are sourced from the Asset Type.
 If the asset is already depreciating, you can't edit the fields unless **Allow Asset Value Editing** is enabled. For more information, see [Restricting the Editing of Asset Values](#).
5. Click **Save**.

No journal entries are created for depreciation history records that already exist or aren't linked to an accounting book.

The **Accounting Book** field is populated for new depreciation history records. For existing depreciation history records, the **Accounting Book** field might show as blank or null.

Asset Proposal

The Asset Proposal record contains values for the primary book. Values on the **FAM Proposal Alt Depreciation** subtab are sourced from the Asset Type's secondary book.

FAM Proposal Alt Depreciation									
New FAM Proposal Alt Depreciation									
Alternate Method	Accounting Book	Posting	Depreciation Method	Convention (C)	Asset Life (AL)	Financial Year Start	Period Convention	Depreciation Period	Depreciation Rule
Depreciation Method 8	Secondary Book 1	No	Straight Line	None	36	January	12 months of 30 days each	Monthly	
Depreciation Method 8	Primary Accounting Book	No	Straight Line	None	12	January	12 months of 30 days each	Monthly	
Depreciation Method 9	Secondary Book 2	No	Straight Line Remaining	None	24	January	12 months of 30 days each	Monthly	

You can edit the Asset Proposal record to change the default general ledger accounts or proposal values per book. For more information, see [Asset Proposal and Generation](#).

For more information about asset proposal, see [Asset Proposal and Generation](#).

Running Depreciation on an Accounting Book

Depreciation computation and journal entry creation in Multi-Book Accounting for Fixed Assets Management happens for each book. You can select the book that you want to depreciate, and the journal entries created will use the Book Specific Journal Entry form.

Note: The system doesn't create a depreciation journal entry for depreciation history records that aren't linked to an accounting book. These records are depreciated when you run depreciation for any book.

The Alternate Depreciation History subtab under the Tax Methods tab is combined with the Accounting Method Depreciation History in the Depreciation History tab. The combined subtab is named **Depreciation History**.

Insurance Maintenance Components Asset Sale/Disposal Asset Usage Sub-Assets Income/Expense Lease Depreciation History						
Method						
New FAM Alternate Depreciation						
Method	Accounting Book	GL Posting	Depreciation Start Date	Depreciation End Date	Asset Status	View ^
Accounting Method	Primary Accounting Book	Yes	10/26/2014	10/25/2015	Disposed	Depreciation Histories
Depreciation Method 8	Secondary Book 1	Yes	10/26/2014	4/25/2016	Disposed	Depreciation Histories
Depreciation Method 8	Primary Accounting Book	No	10/26/2014	10/25/2015	Disposed	Depreciation Histories

For more information about depreciating assets, see [Asset Depreciation](#).

Transferring Fixed Assets Within Multi-Book Accounting

When you transfer assets in Multi-Book Accounting for Fixed Assets Management, the transferred asset is recorded in the currency of the destination subsidiary. The currency is automatically converted to reflect

the book's base currency. Asset Cost, Asset Current Cost, Cumulative Depreciation, Net Book Value are converted to the destination subsidiary's book-specific base currency.

Any depreciation journal entry created after the transfer uses the book-specific base currency of the destination subsidiary. The corresponding journal entry is also book specific.



Important: If the destination subsidiary isn't linked to any book, the system won't process the transfer. For Tax Methods not linked to a book, the transfer is recorded in the Primary Book.

An asset transfer account is required for a successful transfer. For more information, see [Asset Transfer Accounts](#).

There's no separate asset transfer process for secondary books. Secondary book asset transfers are recorded when assets are transferred in the primary book.

For more information about asset transfer, see [Asset Transfer](#).

Revaluing an Asset in Multiple Books

For multi-book enabled accounts, the **Accounting Book** field appears on the asset revaluation page. This lets you select which accounting books (linked to the asset) you want to revalue. Click the **Calculate** button to compute the write-down amount and enable the revaluation fields for the selected accounting books.

Asset Revaluation

Process Revaluation Refresh Calculate Import CSV

Primary Information

Asset ID/Name: FAM005414 Revaluation Asset

Asset Description:

Asset Serial Number:

Alternate Asset Number:

Asset Type: Machinery & Equipment

Current Book Value: 10,800.00

Revision Method:

Current Period:

Asset Status: New

Accounting Book:

Primary Accounting Book

Secondary Book 1

Secondary Book 2

Write-Down %:

Transaction Date:

Transaction Reference:

Primary Accounting Book (GL Posting: Straight Line)

Current Cost	Write-down Amount	Residual Value	Adj Residual Value	Asset Lifetime	Adj Lifetime	Depreciation Method	Adj Depreciation Method
10,800.00		0.00		18		Straight Line	

Primary Accounting Book (Non GL Posting: Depreciation Method 8: Straight Line)

Current Cost	Write-down Amount	Residual Value	Adj Residual Value	Asset Lifetime	Adj Lifetime	Depreciation Method	Adj Depreciation Method
10,800.00		0.00		12		Straight Line	

Secondary Book 1 (GL Posting: Depreciation Method 8: Straight Line)

Current Cost	Write-down Amount	Residual Value	Adj Residual Value	Asset Lifetime	Adj Lifetime	Depreciation Method	Adj Depreciation Method
10,800.00		600.00		12		Straight Line	

To revalue an asset, follow the procedure in [Asset Revaluation](#).

Disposing an Asset in Multiple Books

Upon disposal, the asset is disposed in all associated accounting books. The accounting and tax methods linked to the accounting books create depreciation histories.

When you write off an asset, a journal entry is created to write off the tax methods linked to the accounting books. Selling an asset creates a book-generic invoice that uses the primary book's residual value.

FAM Asset
FAM003018

Edit Back

Actions

ID
FAM003018
Name
Disposal (Sale)
☐ Inactive
Asset Description

Asset Serial Number

Alternate Asset Number

Parent Asset

Project

Asset Type
Furniture & Fixtures
Asset Original Cost
24,000.00
Asset Current Cost
24,000.00

Residual Value Percentage
0.0%
Residual Value
0.00
Depreciation Method
Straight Line
Asset Lifetime
18
Depreciation Period
Monthly
Asset Lifetime Usage

Current Net Book Value
0.00
Cumulative Depreciation
24,000.00
Asset Status
Disposed
Customer Location

Component Of

☐ Asset Is Leased
Asset Tag

CF - Asset - Istrec

FAM Test Field

Business Unit

FAM CSEG 01

CS Test Data - Multi Select

FAM CSEG 101

Notes Files General Accounts Insurance Maintenance Components Asset Sale/Disposal Asset Usage Sub-Assets Income/Expense Lease **Depreciation History**

Method

New FAM Alternate Depreciation

Method	Accounting Book	GL Posting	Depreciation Start Date	Depreciation End Date	Asset Status	View ^
Accounting Method	Primary Accounting Book	Yes	2/3/2014	8/2/2015	Disposed	Depreciation Histories
Depreciation Method 8	Secondary Book 1	Yes	2/3/2014	2/2/2015	Fully Depreciated	Depreciation Histories

To dispose an asset, follow the procedure in [Asset Disposal by Sale or Write-Off](#).

Splitting an Asset in Multiple Books

You can perform one split transaction per asset to create the general ledger results that is posted to different books. New assets created from the split transaction have the same set of alternate and tax depreciation as the original asset. An acquisition history record is created to reduce the original acquisition cost. A depreciation history record is also created to reduce the depreciation amount, and a journal entry is generated if the asset is linked to an accounting book or tax method. Tax methods not linked to an accounting book still record depreciation histories, but don't generate journal entries.

To split an asset, follow the procedure in [Asset Split](#).

Fixed Assets Lease Accounting

The Lease Accounting feature in the Fixed Assets Management SuiteApp helps you comply with the IFRS 16 and ASC 842 lease standards. These standard require lessees to recognize nearly all leases and transfer all operating leases to the balance sheet starting January 1, 2019.

The Lease Accounting feature lets you do the following tasks from the SuiteApp:

- [Creating a Lease Record](#)
- [Adding Lease Payments](#)
- [Generating the Lease Amortization Schedule](#)
- [Lease Journal Entries](#)
- [Recording Lease Interest](#)
- [Lease Asset Proposal and Generation](#)
- [Migrating Existing Lease Details](#)
- [Lease Record Modification](#)

Watch the following help video for a brief overview and demo of the Lease Accounting feature in Fixed Assets Management:

 [Fixed Assets Management Lease Accounting](#)

FAM Lease Accounting Prerequisites

The following prerequisites lets you use the Lease Accounting feature in the Fixed Assets Management SuiteApp:

- To ensure that you have access to the Lease record, enable the **Custom Transactions** feature. Go to Setup > Company > Enable Features > SuiteCloud and check **Custom Transactions**.
- Set up an asset type for your lease asset and specify whether it is an operating lease type or a finance lease type:
 - **Finance Lease** - If you're setting up an asset type for a finance lease, clear the **Operating Lease** box on the Asset Type record.
 - **Operating Lease** - If the asset type is for assets generated from an operating lease, check the **Operating Lease** box.

For more information about setting up an asset type, see [FAM Asset Types](#).

- Set additional permissions required for Lease Accounting. For more information, see [Setting up Permissions for Lease Accounting](#).
- Create new general ledger accounts and set them to the Lease record. For more information, see [Setting Up General Ledger Accounts for Lease Accounting](#).

Setting up Permissions for Lease Accounting

To set up additional permissions for Lease Accounting:

1. Go to Setup > Users/Roles > Manage Roles.
2. Click the **Edit** link next to the custom role.

3. Under the Permissions subtab, click **Custom Record**.
4. Add the following permissions:

Subtab	Permission	Level
Transaction	Lease	Edit
Lists	Vendors	View
Custom Record	Lease Payments	Full

Setting Up General Ledger Accounts for Lease Accounting

Lease Accounting for Fixed Assets Management lets you recognize the right-of-use asset and lease liability, and accrue interest. To use these features, you must create new GL accounts and link them to the Lease record.

Go to Lists > Accounting > Accounts > New, and add the following accounts:

Account	Type
Right-Of-Use Asset	Fixed Asset, Other Current Asset
Acc. Dep. — Right-Of-Use Asset	Fixed Asset
Lease Liability	Accounts Payable, Other Current Liability, Long Term Liability
Interest Expense	Expense, Other Expense
Gain on Modification	Other Income

Creating a Lease Record

You can enter all relevant lease information in the Lease record, allowing you to effectively manage your lease asset. From the Lease record page, you can do the following tasks:

- Propose a lease asset
- Create a mid-life lease
- Define the terms of the lease
- Add lease payments
- Create the lease amortization schedule

When a lease journal is generated, a link to the journal entry becomes available in the record page.

You can upload records through CSV import to create a Lease record.

To learn more about creating a lease record, read the following topics:

- [Creating a Lease Record Manually](#)
- [Importing Lease Records](#)
- [Posting Reference Subtab \(Lease Accounting\)](#)
- [Accounting Books Subtab \(Lease Accounting\)](#)
- [Lease Amortization Schedule Subtab](#)

Note: You currently can't create a mid-life lease through CSV import.

Creating a Lease Record Manually

To create a lease record manually:

1. Go to Fixed Assets > Leases > Lease > New.
2. Enter values for the following fields:

Primary Information

- **Mid-life Lease** – Check this box if you're creating a mid-life lease.
- **Lease Company** – Enter the company where the asset is being leased from.

Note: If the source transaction for a mid-life lease is a Vendor Bill, the Vendor is set as the Lease Company. If the source transaction is a Journal, you must manually enter the Lease Company.

- **Lease Contract Number** – Enter the contract number of the lease agreement.
- **Asset Description** – Enter the name of the lease asset.
- **Lease Start Date** – Enter the start date for the lease.
- **Lease End Date** – Enter the end date for the lease.
- **Finance Lease** – Check this box if the asset is under a finance lease. Leave the box unchecked if the asset is under an operating lease.
- **Transaction** – If you are creating a mid-life lease, select the source journal entry or bill transaction for the lease asset. If the transaction includes a proposal, make sure the asset type matches the lease type you're creating (operating or finance).

Note: The source transaction's debit account must be a Fixed Asset account type. The source transaction's credit account must be one of the following account types: Accounts Payable, Other Current Liability, or Long-term Liability.

- **Prior Interest Periods Recognized** – For mid-life leases, enter the number of interest periods have already been recognized before importing the lease into NetSuite. The value must be greater than or equal to 0, and less than or equal to the lease term.
- **Rental Frequency** – Select the frequency of the rental payments:
 - **Annual** – Select this option if the lease is paid every year.
 - **Monthly** – Select this option if the lease is paid every month.
 - **Quarterly** – Select this option if the lease is paid every quarter.
 - **Semiannually** – Select this option if the lease is paid every six months.
- **Lease Term** – Enter the expected term of lease. The lease term and rental frequency determines the duration of your lease. See the following examples:

Rental Frequency	Lease Term	Lease Duration
Annual	2	2 years
Monthly	2	2 months

Rental Frequency	Lease Term	Lease Duration
Quarterly	2	6 months
Semiannually	2	1 year

- **Annual Interest Rate** – Enter the implicit interest rate to be charged on the financing of this asset.

Classification

- **Subsidiary** – If you're using a OneWorld account, select the subsidiary of the lease company.
- **Class** – Select the class of the lease asset.
- **Department** – Select the department of the lease asset.
- **Location** – Select the location of the lease asset.
- **Currency** — This field shows the base currency of the subsidiary.

 **Note:** Multi-currency is currently not supported.

 **Note:** For mid-life leases, the **Subsidiary**, **Class**, **Department**, and **Location** fields are sourced from the transaction attached to the lease record

3. Click **Save**.

The status of the Lease appears at the top of the record page. For more information, see [Lease Record Status](#).

The Lease record contains the following subtabs:

- [Posting Reference Subtab \(Lease Accounting\)](#)
- [Accounting Books Subtab \(Lease Accounting\)](#)
- [Lease Amortization Schedule Subtab](#)

Lease Record Status

The following table lists the possible status for the Lease record:

Status	Description
Pending Lease Payments	There are no lease payments or the lease payments are incomplete. To enter lease payments, see Adding Lease Payments .
Pending Lease Schedules	Lease payments have been entered, but the lease schedules have not been created. To generate a lease schedule, see Generating the Lease Amortization Schedule .
Pending Lease Journal Creation	Lease schedules have been created, but the lease journals have not been generated. The Create Lease Journal button appears next to the Edit button at the top of the page. To generate a lease journal, see Lease Journal Entries .
Lease Transaction Attached	A transaction to recognize the right-of-use asset and lease liability has been created. A link to the generated journal becomes available in the Lease record.
Asset Proposed	An asset proposal record has been created for the lease journal entry. The generated Asset Proposal is linked back to the Lease record. For more information, see Asset Proposal and Generation .
Asset Created	An asset record has been generated for the lease asset. The created Asset is linked back to the Lease record.

Importing Lease Records

To import lease records:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant Step 1 – Scan & Upload CSV File screen:
 - a. From the **Import Type** list, select **Transactions**.
 - b. From the **Record Type** list, select **Leases**.
 - c. Select the proposal CSV file.
 - d. Click **Next**.
3. In the Import Assistant Step 2 – Import Options screen:
 - a. Set Data Handling to **Add**.
 - b. Click **Next**.
4. In the Import Assistant Step 4 – Field Mapping screen:
 - a. Map the fields in your CSV to the NetSuite fields.
 - b. Review the CSV fields and NetSuite fields to ensure that all required fields are mapped.

 **Note:** If you remove the **Date** field from the import file, the system uses the current date.

- c. Click **Next**.

Sample mapping:

Annual Interest Rate	↔	Lease Proposal : Annual Interest Rate (Req)
Asset Description	↔	Lease Proposal : Asset Description
Lease Company	↔	Lease Proposal : Lease Company (Req)
Lease Contract Number	↔	Lease Proposal : Lease Contract Number
Lease End Date	↔	Lease Proposal : Lease End Date (Req)
Finance Lease	↔	Lease Proposal : Finance Lease
Interest Expense	↔	Lease Proposal : Interest Expense (Req)
Lease Liability	↔	Lease Proposal : Lease Liability (Req)
Rental Frequency	↔	Lease Proposal : Rental Frequency (Req)
Right-Of-use Asset	↔	Lease Proposal : Right-of-Use Asset (Req)
Lease Start Date	↔	Lease Proposal : Lease Start Date (Req)
Lease Term	↔	Lease Proposal : Lease Term (Req)
External ID	↔	Lease Proposal : Externalid
Subsidiary	↔	Lease Proposal : Subsidiary (Req)
6/7/2019	↔	Lease Proposal : Date (Req)

5. In the Import Assistant Step 5 - Save Mapping and Start Import screen:
 - a. Enter an Import Map Name and Description.
 - b. Click **Save & Run**.

The Lease record contains the following subtabs:

- [Posting Reference Subtab \(Lease Accounting\)](#)
- [Accounting Books Subtab \(Lease Accounting\)](#)
- [Lease Amortization Schedule Subtab](#)

Posting Reference Subtab (Lease Accounting)

From the Posting Reference subtab, you can set the accounts used to track the right-of-use asset, lease liability, and interest expense. The subtab displays the following fields:

- **Right-of-Use Asset** – Select the account used to track the right-of-use asset.
For mid-life leases, this field is automatically populated based on the transaction's debit account.
- **Lease Liability** – Select the account used to track the lease liability.
For mid-life leases, this field is automatically populated based on the transaction's credit account.
- **Interest Expense** – Select the account used to track the interest expense.

Accounting Books Subtab (Lease Accounting)

For Multibook-enabled accounts, this subtab shows information about the base currency of the associated secondary books. These values are carried over to generated lease journal entries.

Lease Amortization Schedule Subtab

The Lease Amortization Schedule subtab shows information about lease payments, interest, and related journals for this lease. The subtab displays the following columns:

- **Date** – Shows the lease payment date.
- **Lease Payments** – Shows the lease payment amount.
- **Net Present Value** – This value is calculated based on the rental frequency:
 - For annual rentals: $NPV = \text{lease payment} / (1 + \text{annual interest rate})^{\text{period}}$
 - For monthly rentals: $NPV = \text{lease payment} / (1 + (\text{annual interest rate} / 12))^{\text{period}}$
- **Balance** – This value is calculated by subtracting the principal from the previous balance. The starting balance is equal to the total net present value.
- **Interest** – This value is calculated by multiplying the interest rate by the previous balance. The computation varies depending on the rental frequency:
 - For annual rentals: $\text{Interest} = \text{interest rate} * \text{previous balance}$
 - For monthly rentals: $\text{Interest} = (\text{interest rate} * \text{previous balance}) / 12$
 - If the first lease payment is between the 1st and the 15th of the month, it falls under Period 0. No interest is calculated, and the principal amount equals the lease payment amount.
 - If the first lease payment is between the 16th and the end of the month, it falls under Period 1. The existing calculation for the interest and principal is followed.
- **Principal** – This value is calculated by subtracting the interest from the lease payments.
- **Journal** – This column shows the link to the journal for each Interest lease payment.

At the end of the schedule, the rounding off difference is applied to the principal. The calculation is as follows:

- Principal Amount = Previous Balance
- Interest Amount = Payment Amount – Principal Amount
- Balance = Previous Balance – Principal Amount

Adding Lease Payments

You can add your lease payments through the Lease Amortization Schedule subtab or through CSV import. From the Lease Amortization subtab, you can enter lease payments one at a time on the Payment sublist. You can also click the **Generate Payments** to enter up to 120 payments at one time.

To learn more, read the following topics:

- [Adding Lease Payments through the Lease Amortization Schedule Subtab](#)
- [Adding or Updating Lease Payments through CSV Import](#)

Adding Lease Payments through the Lease Amortization Schedule Subtab

To add lease payments:

1. Go to Fixed Assets > Leases > Lease > New.
2. On the Lease page, click **Edit** next to Lease record for which you want to add a lease payment.

 **Note:** You can enter lease payments when you create a lease record. If you have an existing lease record without lease payments or incomplete lease payments, you can enter the payments one at a time.

3. Click the **Lease Amortization Schedule** subtab on the Lease record:
 - To enter multiple payments at one time:
 1. In the **Start Date** field, enter the start date for the payments you want to generate.
 2. In the **Amount** field, enter the fixed amount for the payments you want to generate.
 3. Click **Generate Payments**.

This button is available when you create a new lease or when you enter lease payments on modified lease records.

 **Note:** The system generates only up to 120 payments at a time. To add payments beyond this limit, you can enter them through CSV import. For more information, see [Adding or Updating Lease Payments through CSV Import](#).

- To enter lease payments one at a time:
 1. In the **Date** column, enter the lease payment date.
 2. In the **Amount** column, enter the lease payment amount.
 3. Click **Add**.

 **Note:** If the first lease payment date falls on or before the 15th of the month, no interest is calculated, and the principal amount is equal to the lease payment amount.

4. Click **Save**.

The net present value, balance, interest, and principal is computed when the lease payment is saved.

Adding or Updating Lease Payments through CSV Import

You can add or update lease payments to add the interest journals through CSV import. To do so, you must perform the following steps:

- [Creating a Saved Search for the Lease Payments](#)
- [Adding Interest Journals to the CSV File](#)
- [Importing Lease Payments](#)



Important: If you created a lease record through lease migration, you must update lease payments first before you can finalize the migration.

Lease Payment Import Guidelines

Before importing your lease payments, review the following import guidelines:

- A Lease record must be created first, before adding lease payments through CSV import.
- The CSV file must include the following columns: Lease Payments, Date, Lease.
- When adding data to the CSV file, make sure you use the Internal ID of the lease record in the Lease column.
- The Lease Payment Date should be unique and should fall within the lease start and end dates.
- Lease Payments should not be a negative value.
- Amortization schedules won't be created automatically when lease payments are imported.

Creating a Saved Search for the Lease Payments

To create a saved search for lease payments:

1. Go to Transactions > Management > Saved Searches > New.
2. On the New Saved Searches page, click **Lease Payments**.
3. On the Saved Lease Payments Search page, enter a title for your saved search.
4. On the **Criteria** subtab, select **Leases** as a filter.
5. On the popup window that appears, click the lease record that you migrated and click **Set**.
6. On the **Results** subtab, under the **Columns** subtab, remove the **Script ID** field, and then add the following:
 - Internal ID
 - Leases
 - Date
7. Click **Save & Run**.
8. Click the Export – CSV icon to export your search to a CSV file.

Adding Interest Journals to the CSV File

To add the interest journals to the CSV file:

1. On your computer, open the CSV file of the lease payments saved search.
2. Add a **Journal** column next to the **Date** column.
3. In the **Journal** column, enter the **Journal ID** that corresponds to the date of the lease payments on the CSV file.

 **Note:** You must add journal IDs only up to the date where you have an interest journal generated.

4. Save the file as CSV.

Importing Lease Payments

 **Important:** To ensure that FAM bundle scripts are running on records created using CSV import, you must enable **Run Server SuiteScript and Trigger Workflows** (Setup > Import/Export > CSV Import Preferences).

To import lease payments:

1. Go to Setup > Import/Export > Import CSV Records.
2. In the Import Assistant Step 1 – Scan & Upload CSV File screen:
 - a. From the **Import Type** list, select **Custom Records**.
 - b. From the **Record Type** list, select **Lease Payments**.
 - c. Select the lease payments CSV file.
 - d. Click **Next**.
3. In the Import Assistant Step 2 – Import Options screen:
 - a. Set **Data Handling** to any of the following:
 - **Add** — If you are adding lease payments for a new lease asset.
 - **Update** — If you are updating lease payments for an existing lease asset.
 - b. Click **Next**.
4. On the Import Assistant Step 3 – Field Mapping screen:
 - a. Map the fields in your CSV file to the following NetSuite fields:

 Date	↔	Lease Payments : Date	
 Journal	↔	Lease Payments : Journal	
 Lease Proposal	↔	Lease Payments : Lease Proposal	
 Internal ID	↔	Lease Payments : Internal ID	

- b. Click the pencil icon next to Journal to show the Default Value or Reference Type popup.
- c. In the **Choose Reference Type** list, select **Internal ID**, and then click **Done**.
- d. Review the CSV and NetSuite fields to ensure that all required fields are mapped, and then click **Next**.

5. On the Import Assistant Step 5 – Save Mapping and Start Import screen:
 - a. Enter an **Import Map Name** and **Description**.
 - b. Click **Save & Run**.

Generating the Lease Amortization Schedule

The Lease Amortization Schedule is the schedule of the net present value and interest for the lease. You can generate a lease amortization schedule if you have previously entered lease payments for the Lease record. The status of the Lease record should show Pending Lease Schedules if there are no schedules created yet.

To generate the lease amortization schedule:

1. Go to Fixed Assets > Leases > Generate Lease Schedules.
2. Select the lease record for which you want to generate a Lease Amortization Schedule.
3. Click the **Generate** button at the top of the page.

The system computes the net present value, interest, and principal.

Lease Journal Entries

When the interest schedules for the lease record are generated, the **Create Lease Journal** button becomes visible on the Lease record. This button is only available if no journal entry has been created for the lease record.

This process debits to the Right-of-use asset and credit to the Lease Liability. The generated lease journal is used to propose and create a leased asset. The leased asset goes through the whole asset life cycle.

To learn more about lease journal entries, read the following topics:

- [Creating a Lease Journal Entry](#)
- [Reversing a Lease Journal](#)

Creating a Lease Journal Entry

To create a lease journal entry:

1. Go to Fixed Assets > Leases > Lease.
2. Select the lease record for which you want to generate a journal entry.
3. On the Lease page, click **Create Lease Journal**.

The system creates a journal entry and adds a link to it in the **Journal** field on the Lease record.

Reversing a Lease Journal

Reversing a lease journal lets you modify lease records with a linked journal record. This process reverses the original lease journal and removes it from the lease record. You can then update the lease record and create a new lease journal.

To reverse a lease journal:

1. Go to Fixed Assets > Leases > Lease.
2. On the Leases page, select the lease record that you want to modify.
3. On the Lease record page, click **Reverse Journal**.

 **Note:** The **Reverse Journal** button is only available if the lease record has a linked journal record.

After reversing the original lease journal, the lease status reverts to **Pending Lease Journal Creation**.

Recording Lease Interest

The Record Lease Interest page lets you recognize the interest amount per period. The interest amount comes from the lease amortization schedule on the lease record. The interest journal includes a link to the related lease record.

To use this feature, you must create additional GL accounts. For more information, see [Setting Up General Ledger Accounts for Lease Accounting](#)

To record the interest incurred on your leased assets:

1. Go to Fixed Assets > Leases > Record Lease Interest.
2. Provide values for the following fields:
 - **Date** – Enter a date for the lease payments.
 - **Subsidiaries** – Select the subsidiaries of the leased assets.
3. Click **Record Interest**.

 **Note:** You can record interest only for Lease records with an **Asset Created** status.

The system creates an interest journal for lease payments without a lease interest, dated on or before the date entered. A link to the interest journal entry is available in the Lease Amortization Schedule subtab in the Lease record.

The interest journal lines are as follows:

- For finance lease:
 - Debit to Interest Expense
 - Credit to Lease Liability
- For operating lease:
 - Debit to Accumulated Depreciation – Right-Of-Use Asset
 - Credit to Lease Liability

The GL accounts used in the interest journal is sourced from the accounts you set in the Posting Reference subtab of the Lease record. The generated journal is automatically approved if any of the following conditions are met:

- The journal is created by a user with permission to approve journals.

- The **Require Approvals on Journal Entries** preference is turned off.

Otherwise, the journal is set to **Pending Approval**.

Lease Asset Proposal and Generation

After creating the lease journal to recognize the right-of-use asset and lease liability, you can create the asset from the Asset Proposal or Manage Asset Proposal page. The Lease record status will be set to **Asset Proposed** or **Asset Created**.

If an asset is created from a lease record, the **Asset is Leased** box on the asset record is automatically checked. The Lease subtab on the Asset Record shows information about the lease and a link to the lease record. For more information about generating an asset from a proposal, see [Asset Proposal and Generation](#).

The information from the lease record carries over to the Lease tab of the asset record. The Lease tab shows the following information:

- Lease record link
- Lease Company
- Lease Contract Number
- Lease start and end dates
- Finance Lease checkbox
- Rental Frequency
- Lease Term
- Annual Interest Rate



Note: Existing Lease fields will not be used and will be set to deprecated.

Initial Measurement of the Right-of-Use Asset

The right-of-use asset equals the net present value of the lease.

For a finance lease, the asset's residual value (RV) equals the residual value percentage (RV%) in the asset type multiplied by the current cost. If the right-of-use asset is proposed and generated from a lease, the RV% is the same as the RV% in the asset type.

For an operating lease, the RV of an asset that's proposed and generated from a lease equals the total interest amount of the lease, shown as a negative value. The RV% is calculated as the residual value divided by the asset current cost.

Re-measurement of the Right-of-Use Asset

The re-measurement amount for the lease liability matches the adjustment made to the right-of-use asset. The calculation for the lease modification adjustment is the same for finance and operating leases. The write-down adjustment is calculated as the difference between the following:

- The lease liability balance at the effective date of modification
- The new net present value using the modified lease terms

If you modify an operating lease asset, the RV is calculated as the total interest of the modified lease, shown as a negative amount.

Note: You should use **Straight Line Remaining Depreciation Method** because the depreciation after modification is computed based on the current net book value or remaining life. If you use other depreciation methods, depreciation after modification is calculated as Current Cost divided by the Asset Life.

Migrating Existing Lease Details

With the introduction of the Lease Accounting feature, the old lease details in the asset record (**Lease** subtab > **Deprecated** subtab) will no longer be used. Lease details for all new lease assets are now in the **Lease** subtab. You can migrate lease details to create a Lease record for existing lease assets.

To migrate existing lease details:

1. Go to Fixed Assets > Lists > Assets.
2. Click **Edit** next to the asset that you want to migrate.
3. Click the **Deprecated** subtab under the **Lease** subtab, and then click the **Migrate Lease Details**.

Note: The **Migrate Lease Details** link is available only if the asset is subject to a finance lease.

The following values are sourced from the asset record:

- Original Cost = Net Present Value
 - Asset Lifetime = Lease Term
 - Depreciation Start Date = Lease Start Date
 - Interest Rate (Deprecated) = Annual Interest Rate
4. Click **Save**.
 5. After saving the migrated lease record, you must add existing interest journals through CSV import. See [Adding or Updating Lease Payments through CSV Import](#).
 6. After updating the interest journals for the lease asset, click **Finalize Migration** on the Lease page. When the lease migration has been finalized, the status of the proposal record changes to **Asset Created**.

After finalizing the migration, interest journals for pending payments are generated when you Recognize Lease Interest.

Lease Record Modification

Important: To modify lease records, make sure that the **Allow Lease Modifications** preference is enabled in the FAM System Setup page. For more information, see [Setting Up the Fixed Assets Management System](#).

Modifying lease records lets you update the original lease terms and conditions. The **Modify Lease Record** button appears on Lease records with associated assets, unless the depreciation period is set to **Annual Depreciation, Monthly Posting**.

For assets with a quarterly or semiannual rental frequency, the lease term is converted to months or years to match the depreciation period, which only supports monthly and annual options. After the conversion, the lease term should match the asset lifetime.

For example, when a lease contract with a quarterly rental frequency and a lease term of 4 is proposed for an asset with a monthly depreciation period, the asset lifetime is converted to 12 months. Conversions for annual depreciation are rounded up.

A Lease Contract record is generated every time you create or modify a lease. This record includes lease details and links to the Lease record and Journal.

You can also modify leases from the Lease Modification page.

Watch the following help video for a brief overview and demo of the Lease Modification feature in Fixed Assets Management:

 [Fixed Assets Lease Modification](#)

Modifying Lease Records

To modify lease records:

1. Go to Fixed Assets > Leases > Lease Modifications.
2. On the Lease Modifications page, enter values for the following fields:

Primary Information:

- **Lease** – Select the lease record that you want to modify.

 **Note:** You can modify lease records with associated assets, if the asset life is equal to the Lease Term and its depreciation period is equal to the Rental Frequency. If you want to modify a lease record after a journal has already been created, you must first reverse the lease journal. For more information, see [Reversing a Lease Journal](#).

- **Effective Date** – Set the date when both the lessee and lessor approve the lease modification.

Lease Modification Details:

- **Modified Lease Term** – Enter the new lease term.
- **Modified Annual Interest Rate** – Enter the new implicit rate of the lease.
- **Modified Lease End Date** – The modified lease end date is automatically calculated based on the modified lease term and start date.

3. Click **Process** to update your lease records.

 **Note:** You can't process lease modifications simultaneously using multiple browser tabs.

Asset adjustments apply only to the accounting method. You can manually adjust the tax methods through asset revaluation. For more information, see [Asset Revaluation](#).

The Lease record status changes to **Pending Process** and a link to the Process Status page is displayed. The Process Status page shows the Deactivate Payment process. This process sets the payment records for the modified lease where the payment date is greater than or the same as the effective date, or inactive. For more information, see [Processes Triggered by Lease Modifications](#).

Processes Triggered by Lease Modifications

When you apply modifications to your lease, the following processes are triggered:

- A lease modification journal entry is created to record adjustments to the Lease Liability and Right-of-Use Asset accounts.
- A reversal interest journal entry is recorded to reverse the interest expense on lease payments after the effective date of modification
- The lease modification journal entry is linked to the new **Lease Modification DHR**. The Asset Current Cost and Net Book Value are then updated.

Note: You should use **Straight Line Remaining Depreciation Method** since the depreciation after modification is computed based on the current net book value or remaining life. If you use other depreciation methods, like Straight Line, depreciation after modification is computed as Current Cost divided by the Asset Life.

Calculating the Lease Modification Adjustment

To show how the lease modification adjustment is calculated, the following sample lease information is used:

- Original lease term: 3 years
- Annual payment: 150,000
- NPV: 408,487.20
- Interest rate: 5%

At the end of the second year, a modification is made to extend the lease for another year. The annual lease payments remain unchanged but a new incremental interest of 8% is applied to the lease.

Calculating the Adjustment Value

To calculate the adjustment, first identify the balance at the time of modification. In the sample scenario, this corresponds to the balance at the end of the second year.

Period	Date	Lease Payments	NPV of Lease Payments	Balance	Interest	Principal
1	12/31/2020	\$150,000.00	\$142,857.14	\$278,911.56	\$20,424.36	\$129,575.64
2	12/31/2021	\$150,000.00	\$136,054.42	\$142,857.14	\$13,945.58	\$136,054.42
3	12/31/2022	\$150,000.00	\$129,575.64	\$0.00	\$7,142.86	\$142,857.14
		NPV	\$408,487.20			

The new NPV is then calculated using the modified lease terms. The following table shows the payment details and new NPV for the modified lease:

Period	Date	Lease Payments	NPV of Lease Payments	Balance	Interest	Principal
1	12/31/2022	\$150,000.00	\$138,888.89	\$138,888.89	\$21,399.18	\$128,600.82
2	12/31/2023	\$150,000.00	\$128,600.82	\$0.00	\$11,111.11	\$138,888.89
		NPV	\$267,489.71			

Note: If the first lease payment falls between the 1st and the 15th of the month, it falls under Period 0. No interest should be computed and the principal amount should equal the lease payment amount. For more information, see [Lease Amortization Schedule Subtab](#).

The lease modification adjustment is the difference of the new NPV and the balance at period of modification.

New NPV: \$267,489.71

Balance: \$142,857.14

Lease modification adjustment: \$124,632.57

If the new NPV is higher than the balance, the difference is a positive adjustment value. This value is added to the lease liability. If the new NPV is lower than the balance, the difference is a negative adjustment value. This value is subtracted from the lease liability.

The write-down adjustment calculation from a modification is the same for both operating and finance lease. The write-down adjustment is the difference between the lease liability balance at the effective date of modification and the new NPV using the updated lease terms.

Viewing Lease Modification Details

If you modified your lease, the Lease Modification subtab becomes available on the Lease record. You can view the modified lease terms from this subtab.

To view the lease modification details:

1. Go to Fixed Assets > Leases > Lease.
2. Select the lease record that you want to view.
3. On the Lease page, click the **Lease Modification** subtab. The following information is available in this subtab:
 - **Contract ID** — This column shows a link to the Contract record.

Note: You can't edit the Contract record. The Lease Payments subtab on the Contract record shows the amortization schedule, total lease payments, total NPV, total lease liability, total interest, and total principal.

- **Effective Date** — This column shows the effective date of the lease modification. For the original contract, the effective date is the same as the lease start date.
- **Journal ID** — This column shows a link to the journal record.
- **Annual Interest Rate** — This column shows the modified implicit rate of the lease.
- **Term** — This column shows the modified lease term.
- **End Date** — This column shows the modified lease end date.