SRS Suite PRO — Roles and Role Templates Guide

2026-10-17

Contents

1. About this guide

2. Key ideas

3. Who can do what

4. The Roles screen

5. Creating a role

6. Editing a role

7. Access level

8. Choosing the permissions of a role

9. Services of a role

10. Users of a role

11. How a user gets a role

12. Activity of a role

13. Setting a role inactive, activating it and deleting it

14. Role Templates

15. Assigning a template to an existing role

16. Questions

1. About this guide

This guide explains how to manage roles in SRS Suite PRO: what a role is, how to create and edit roles, how to choose their permissions and services, how role templates work, and how to link an existing role to a template.

You will find the two screens under **Roles Admin** in the left menu:

- **Roles** — every role of your company.
- **Role Templates** — reusable templates that keep the permissions of many roles in sync.

What you can see and do depends on your own permissions (see chapter 3).

2. Key ideas

Role. A role is a set of permissions. Every user gets one or more roles, and the role decides what the user can see and do.

Permission. One thing a user is allowed to do, for example "Invoices > Module Access" or "Users > Create User". Permissions are grouped by the word before ">" (Invoices, Users, Work Orders…).

Internal and External roles.

- An **Internal** role is for your own company's staff. It can apply to the whole company ("ALL") or to one dealer and department.
- An **External** role is for users who work at a dealer. It always belongs to one dealer.

The type is chosen when the role is created and cannot be changed later. The permissions you can pick depend on the type.

Role template. A template is a model role. You set its permissions once, and every role linked to the template gets the same permissions. When you change the template's permissions, all its roles are updated at the same time.

Template-based role. A role linked to a template. In the Roles list, its "Based on" column shows the template's name (roles without a template show "—"). Its permissions come from the template and follow every change to the template's permissions. Its access level is copied from the template when the role is created or linked. Only its name can be changed on the Roles screen.

Access level. A number you can give a role (1 or higher). The access level of the role you are using in your current session limits the Roles list when it is greater than 1: only roles with a numbered access level below it are shown. Level 1 and an empty access level do not currently restrict this list.

Active, inactive and deleted. An inactive role is hidden from the default list and can be activated again. A deleted role disappears from every list and cannot be assigned, but its history is kept.

3. Who can do what

To…	You need the permission
Open Roles and see roles and their permissions	"Roles > List"
Add, edit, activate, set inactive or delete roles; change permissions, services and access level	"Roles > Modify"
See the users of a role ("View Users")	"Users > Module Access"
Remove a role from a user	"Users > Create User"
Open Role Templates	"Roles Admin > Role Templates"
Create roles from the Role Templates screen	"Roles Admin > Role Templates"
Create a role from a template using "Add Role", or assign a template to an existing role	"Roles Admin > Role Templates" and "Roles > Modify"

Company administrators can do everything.

If you can see roles but not change them, the list shows "Read only — you can view permissions but not change them".

4. The Roles screen

Open **Roles Admin › Roles**.

Filters

- **"Type"** — "All", "Internal" or "External".
- **"Based on"** — pick a template to see only the roles linked to it. Leave "Any template" to see all.
- **"Show inactive"** — when on, the list shows **only** the inactive roles. Turn it off to go back to the active ones.
- **Dealers in the top bar** — if you select dealers at the top of the screen, the list shows only the roles of those dealers. A switch "Include roles without dealer" then appears: turn it on to also see the internal roles that apply to the whole company.

The list

Columns: "Name", "Based on" (the role's template, or "—"), "Department", "Dealer", "Company", "Type", "Access level" and "Permissions" (how many permissions the role has). "ALL" in Department or Dealer means the role is not limited to one.

- Use **"Search…"** to find roles by name.
- Click "Name", "Type" or "Access level" to sort.
- Click a row to open its permissions.
- **"Export"** downloads an Excel file with the rows of the page you are looking at.

5. Creating a role

Click **"Add Role"**.

A normal role

1. Choose the **"Type"**: "Internal" or "External".
2. Choose the **"Dealer"**. It is required for external roles. For an internal role, leave it empty to make the role apply to the whole company.
3. Choose the **"Department"**, or leave "ALL".
4. Type the **"Name"**.
5. Optionally, type the **"Access level"** (1 or higher).
6. Click **"Save"**.

A new role includes "Inventory > Create Car" by default. Open its permissions to review it and choose the permissions the role needs (chapter 8).

A role from a template

If you can use templates, the dialog shows the switch **"Based on template"**.

1. Turn on "Based on template".
2. Pick the template.
3. For an external template, choose the **"Dealer"**.
4. Click **"Save"**.

The role gets the template's name (for an external template, "*Template* - *Dealer*"), its access level and its permissions, and stays linked to the template. An internal template creates only one role this way; an external template creates one role per dealer.

6. Editing a role

Open the **"…"** menu of the role and choose **"Edit"**.

- **A normal role:** you can change the department, the name and the access level. The type, company and dealer cannot be changed.
- **A template-based role:** you can change only the name. The dialog says "Based on template "*name*": only the name can be changed here."

7. Access level

Click the number in the **"Access level"** column, type the new value (1 or higher) and click **"Save"**. A template-based role keeps the access level it got from the template when it was created or linked; the number cannot be clicked, and changing the template's access level does not change it.

8. Choosing the permissions of a role

Click the shield button or the row of the role. The **Permissions** panel opens.

- Permissions are grouped. Click a group to open or close it, or use **"Expand all"** / **"Collapse all"**.
- Next to each group you see **assigned / total**, for example "3 / 9": the role has 3 of the 9 permissions of that group.
- **"Show assigned only"** opens all the groups and shows only the permissions the role has. Click **"Show all"** to see every permission again. While "Show assigned only" is on, a permission you untick stays on screen, so you can tick it again.
- **"Search permissions"** finds permissions by name or description. It works together with "Show assigned only".
- Tick or untick a permission to change it. **Each change is saved immediately**; there is no Save button.
- The "i" icon shows what a permission does.
- Some permissions cannot be combined. If you tick one of them, you see "Before adding this permission, remove its conflicting permission."

For a template-based role the panel is read-only and says "This role is based on template "*name*". Edit permissions from Role Templates." It shows only the permissions the role has, with every group open; "Expand all" and "Show assigned only" are not shown. If the role has none, you see "This role has no permissions assigned."

9. Services of a role

In the **"…"** menu choose **"Services"**. The panel lists the dealer, department and service of each row, with two checkboxes: **"Create WO"** (the user can create work orders for that service) and **"Approve WO"** (the user can approve them). Each change is saved immediately.

Services belong to the departments of each dealer. That is why "Services" appears for external roles and for internal roles linked to a dealer or department that has services. Internal roles of your own company with no such services do not show this option.

"Apply update to the users"

- **On** (the default every time you open the panel): the change is also applied to every user who already has this role.
- **Off**: users who already have the role are not changed. For an external role, only users who get the role from now on receive the new services.

The checkboxes at the top of each column mark or unmark all services currently shown. If you have entered a search, only matching services are changed. You are asked to confirm when more than 10 services are affected.

Assign all services to several external roles

1. In the list, tick the external roles.
2. Click **"Assign all services (n)"**.
3. Choose **"Create Work Orders"** and/or **"Approve Work Orders"**.
4. Click **"Apply"**.

Every service of each selected role gets exactly the options you ticked, and the change is applied to the users of those roles. To change these options later, use "Services" with "Apply update to the users" on, or run "Assign all services" again. Use an individual user's profile for changes that apply to that user only.

10. Users of a role

In the **"…"** menu choose **"View Users"**. You see the active users with this role, one row per dealer where they have it.

To remove the role from a user at one dealer, click the trash icon and confirm with **"Remove"**. The selected role assignment is removed. This can also clear the user's service settings for that dealer or service provider: for example, when you remove an external role, the user's services at that dealer are cleared.

A user marked **"PRO role"** uses this role to enter SRS Suite PRO, so it cannot be removed here. A company administrator has to change the user's PRO role first (chapter 11).

11. How a user gets a role

Roles are given to users in SRS Suite, not in PRO: open **Users**, edit the user and use the **Roles** tab. A company administrator selects or changes the user's PRO role in the **"SRS PRO"** column. If you cannot see that column, ask your company administrator to make the change. Other users need a role selected there to enter PRO; company administrators can enter without this selection.

12. Activity of a role

In the **"…"** menu choose **"Activity"**. Each entry shows what changed, when and who did it: creation, name or access level changes, permissions added and removed, services, activation, deletion and template assignment.

When a template's permissions change, the change is recorded in the template's activity, not in each role.

13. Setting a role inactive, activating it and deleting it

In the **"…"** menu:

- **"Set inactive"** hides the role from the default list. Use "Show inactive" to find it, and **"Activate"** to bring it back.
- **"Delete"** removes the role from every list; it can no longer be assigned, but its history is kept. If active users still have the role, you see "Cannot delete this role: it is still assigned to *n* user(s)." Remove the role from those users first (chapter 10).

14. Role Templates

Open **Roles Admin** › **Role Templates**. You need the permission "Roles Admin > Role Templates".

Creating or editing a template

1. Click **"Add Template"**.
2. Choose the **"Type"** ("Internal" or "External"). It cannot be changed later.
3. Type the **"Name"**.
4. Optionally, type the **"Access level"**.
5. Click **"Save"**.

When editing, the **"Active"** switch sets the template active or inactive. An inactive template does not appear in the template pickers ("Based on", "Add Role" and "Assign template"); the roles already linked to it keep working.

Changing a template's name or access level does **not** change the roles that already use it.

The template's permissions

Click the shield button or the template's row. Use the search, permission groups, the "3 / 9" counters and "Show assigned only" as described in chapter 8. Each change is saved immediately and **also updates every role linked to the template**, active or inactive. Deleted roles are not updated.

Creating roles from a template

In the **"…"** menu choose **"Create Roles"**. The panel lists the roles linked to the template.

- **Internal template:** click **"Create Roles"** and confirm. One role is created with the template's name for the whole company. If the template already has an internal role, the button is disabled.
- **External template:** click **"Create Roles"**, tick one or more dealers and confirm. One role is created for each dealer, named "*Template* - *Dealer*". Dealers that already have a role from this template are not listed.

The new roles get the template's permissions and access level.

From this panel you can also set each role inactive, activate it, or delete it (trash icon). A role with active users cannot be deleted.

Activity, setting inactive and deleting

- **"Activity"** shows who created or changed the template, its permissions (with the roles that were updated) and its roles.
- **"Set inactive"** / **"Activate"** works like for roles.
- **"Delete"** removes the template for good. It is only possible when no role is linked to it.

15. Assigning a template to an existing role

Use this when a role already exists — with its users — and you want it to follow a template from now on. You need "Roles Admin > Role Templates" and "Roles > Modify".

1. In **Roles**, open the **"…"** menu of the role and choose **"Assign template"**. The option appears only on roles that are not linked to a template yet.
2. In **"Select a template"**, pick the template. Only active templates of the same type as the role are listed.
3. Read what will change:
    - the warning;
    - **"Name"**: current name → new name;
    - **"Access level"**: current → new (only if it changes);
    - **"Permissions added"** and **"Permissions removed"**, or "Permissions stay the same".
4. Click **"Assign template"**.

What changes

- The role loses its own permissions and takes the template's.
- It is renamed to the template's name (for an external role, "*Template* - *Dealer*"). You can rename it afterwards with "Edit".
- It takes the template's access level. This is a one-time copy: it cannot be changed afterwards in PRO, and changing the template's access level does not update the role.
- From now on its permissions are edited in Role Templates, and every change to the template's permissions also updates this role.

What stays the same: its users, its services, its dealer, its department and whether it is active.

This cannot be undone. A role cannot be unlinked from its template.

Several roles, one template. You can assign the same internal template to several internal roles — for example, one "Car Wash" role per dealer. Each keeps its own dealer and department, and all of them get the template's permissions. (Creating roles from an internal template, chapter 14, still creates only one.)

When it cannot be assigned — the dialog explains why and the button stays disabled:

- "This template already has a role for this dealer."
- "This external role has no dealer, so it cannot take a template."
- "This role's dealer is no longer linked to your company, so it cannot take a template."

The assignment is recorded in the Activity of the role (with the permissions added and removed) and of the template.

16. Questions

Why can't I change the permissions of a role? Either you do not have "Roles > Modify", or the role is linked to a template (its "Based on" column shows the template). Change the template's permissions instead.

I changed a template's permissions. Do I have to update its roles? No. Every linked role is updated at the same time.

Why is "Delete" refused? Active users still have the role. Open "View Users", remove the role from them, and try again.

I can't find a role. Check the filters: "Show inactive" shows only inactive roles, and the dealers selected at the top bar limit the list.