



Advanced Risk Reward

NinjaTrader 8 · Complete User Manual

From drawing your setup to executing with precision — one toolkit.

VISUAL

Multi-level SL/TP ruler

SIZING

Auto contract calculator

EXECUTION

One-click order entry

CREATED BY

Luis Fernando Garrido Miranda

X: @iluisgm · PayPal: lfgm00 · USDT ERC-20: 0xEF0E0eFe33bE9487ca1D017Ceb5b1C70a3bf36BC

Version 2026



Advanced Risk Reward

NinjaTrader 8 · Complete User Manual

From drawing your setup to executing with precision — one toolkit.

VISUAL

Multi-level SL/TP ruler

SIZING

Auto contract calculator

EXECUTION

One-click order entry

CREATED BY

Luis Fernando Garrido Miranda

X: @iluisgm · PayPal: lfgm00 · USDT ERC-20: 0xEF0E0eFe33bE9487ca1D017Ceb5b1C70a3bf36BC

Version 2026

SECTION 01

Welcome

What is Advanced Risk Reward?

Advanced Risk Reward is a **two-part professional toolkit** for NinjaTrader 8 that takes you from drawing your trade setup on the chart all the way to placing and managing live orders — all in one seamless workflow.

It was built for traders who want to see exactly how much they are risking, how many contracts to trade, and where to place their stops and targets — and then execute that plan with a single button press.

The Two Components

Drawing Tool — `AdvancedRiskReward_LuisGarrido`



A custom chart drawing tool. Draw your Entry, Stop Loss, and Take Profit directly on the chart by clicking and dragging. The tool automatically calculates your risk, how many contracts to trade, and shows all the key levels visually.

Strategy — `DrawingToolSyncStrategy_BETA`



A NinjaTrader strategy that watches your drawing tool in real time. When you press the entry button, it reads the exact prices from your drawing and submits the entry order plus a Stop Loss and Take Profit bracket automatically.

HOW IT WORKS

You do NOT need to type in any prices. Draw your setup on the chart, check the numbers, and press LONG or SHORT. The strategy handles everything else.

Who Is This For?

- **Beginners:** Easy visual setup — no need to calculate risk or contract size manually.
- **Day traders:** Fast entry with pre-calculated sizing and instant bracket placement.
- **Swing traders:** Draw your levels in advance; the tool waits and executes when you click.
- **Risk-focused:** Never enter a trade without knowing exactly how much you can lose.

SECTION 02

Installation

Get set up in under 5 minutes

What You Need

- NinjaTrader 8 installed and connected to a data feed
- The two files provided: Drawing Tool (.cs) and Strategy (.cs)

Step-by-Step Installation

1

Copy the Drawing Tool file

Go to: Documents > NinjaTrader 8 > bin > Custom > DrawingTools

Copy AdvancedRiskReward_LuisGarrido.cs into that folder.

2

Copy the Strategy file

Go to: Documents > NinjaTrader 8 > bin > Custom > Strategies

Copy DrawingToolSyncStrategy_BETA.cs into that folder.

3

Compile in NinjaTrader

Open NinjaTrader. Go to: Tools > Edit NinjaScript > Compile

Both files will compile automatically. You should see no errors.

4

Add the Strategy to your chart

On your chart, right-click > Strategies > Add Strategy.

Select DrawingToolSyncStrategy_BETA and click OK.

The custom button panel will appear in your Chart Trader.

5

You are ready!

The drawing tool appears in your drawing toolbar. The strategy is running.

Open a chart, draw your setup, and press LONG or SHORT to trade.

IMPORTANT

IMPORTANT: The Strategy must be added BEFORE you draw the tool on the chart, or added while the chart is open. Both must be on the same chart panel. The strategy automatically finds the drawing tool — no configuration needed.

SECTION 03

The Drawing Tool

Your visual risk/reward ruler

The drawing tool is the heart of the system. It replaces NinjaTrader's standard risk/reward ruler with a much more powerful version. You place three points on the chart — Entry, Stop Loss, and Take Profit — and the tool does all the math for you.

How to Draw Your Setup

1

Select the tool

Find 'Advanced Risk Reward V1 By Luis Garrido' in the drawing toolbar and click it.

2

Click your Entry price

Click on the chart at the price where you plan to enter the trade.

3

Drag to your Stop Loss

Drag down (for a long trade) or up (for a short trade) to your stop loss level. Release the mouse.

4

Done!

The tool automatically calculates and draws your Take Profit target based on the Profit Ratio setting. All labels appear instantly.

What You See on the Chart

ENTRY LINE — Horizontal line at your entry price. The anchor point.

FSL LINE — Final Stop Loss — your main stop. Shows: contracts, dollar risk, and optional Ticks/Points/Currency.

TP LINE — Final Take Profit — your target. Labeled with the RR ratio (e.g. 3.0R).

PARTIAL SL LINES — Intermediate stop levels between entry and FSL (e.g. SL1, SL2). Driven by the Stop Ratio setting.

PARTIAL TP LINES — Intermediate TP levels (TP1, TP2...). Each shows its own RR ratio and optional stats.

SHADED ZONES — Red zone = your risk area (entry to stop). Green zone = your profit area (entry to target).

ANCHOR CIRCLES — Prominent dots on the Entry, FSL, and Final TP lines — easy to grab and drag.

SECTION 04

Drawing Tool Settings

All options explained

Opening the Settings

Double-click the drawing tool on the chart (or right-click > Properties) to open the settings panel.

Risk Reward Settings

SETTING	DEFAULT	WHAT IT DOES
Profit Ratio	3.0	How many TP levels to create. '3' = TP1 (1R), TP2 (2R), TP3 (3R=Final).
Stop Ratio	2.0	How many partial SL levels to show between entry and your stop.
Stop Loss Budget	\$200	Your maximum dollar risk per trade. Used to calculate contract size.
Show Partial TPs	ON	Toggle the intermediate TP lines on/off. Final TP always visible.
Font Size	11	Size of all text labels on the chart. Range: 6 to 32.
Text Alignment	InsideLeft	Where labels appear: InsideLeft, InsideRight, ExtremeLeft, ExtremeRight, or Off.

PLUS Settings — Auto Contract Sizing

This is one of the most powerful features. Instead of manually calculating how many contracts to trade, the tool does it for you based on your dollar risk budget.

SETTING	DEFAULT	WHAT IT DOES
Auto Order Qty	OFF	When ON: automatically calculates and sets the contract count in Chart Trader.
Max Contracts	10	The maximum number of contracts the auto-sizer will ever use. Prevents oversizing.

EXAMPLE

Example: Stop Loss Budget = \$200. Your stop is 10 ticks away. Each tick = \$12.50. Risk per contract = \$125.
Contracts = $200 / 125 = 1.6 \rightarrow$ rounds to 2 contracts. The FSL label will show '2 contracts, \$200 risk' and Chart Trader is automatically set to 2.

PRO Settings — Live Price Tracking

PRO settings let your entry line follow the market price in real time, so you are always analyzing your risk at the current price without dragging anything manually.

SETTING	DEFAULT	WHAT IT DOES
Track Last Price	OFF	Makes the entry line follow the selected price source in real time.
Price Source	LastPrice	Which price to track: LastPrice, Close, High, Low, or Open.
Stop Mode	FLEX	FLEX = stop stays fixed, contracts recalculate. HARD = stop moves with entry.
Stop Track On Fill	OFF	Auto-disables tracking when a position opens. Re-arms when flat.
Button Position	NearEntry	Where the on-chart button panel appears: NearEntry, NearTP, NearFSL, CenterTop, CenterBottom.
Button Opacity	80%	How transparent the on-chart buttons are (0=invisible, 100=solid).
Show Buttons On Hover	OFF	When ON: buttons auto-appear when mouse is over the tool, auto-hide when mouse leaves.

SECTION 05

On-Chart Buttons

Interactive controls on the drawing tool

The drawing tool has an interactive button panel that floats next to the drawing. By default it is hidden — press the  arrow to expand it, or enable **Show Buttons On Hover** for it to auto-appear when your mouse is over the tool.

[ / ] Collapse or expand the button panel.

[**FLIP**] Instantly mirror the setup. Long becomes Short (and vice versa), same risk distance.

[**AUTO CALC**] Toggle automatic contract sizing on/off without opening the settings panel.

[**AUTO TRACK**] Toggle live price tracking on/off. Entry line starts/stops following the market.

[**SOURCE**] Cycle through price sources: LastPrice → Close → High → Low → Open → LastPrice. Only active when AUTO TRACK is ON.

[**STOP MODE**] Toggle between FLEX stop (stop stays fixed) and HARD stop (stop moves with entry). Only active when AUTO TRACK is ON.

PRO TIP

FLIP is extremely useful when you are unsure of direction. Draw a long setup, evaluate the risk/reward, then press FLIP to instantly see the short setup — same levels, mirrored.

FLEX vs HARD Stop Mode — Explained

FLEX Mode (default): Your stop price stays exactly where you placed it. As the last price moves (when AUTO TRACK is on), the entry line follows but the stop stays put. The distance between entry and stop changes, so the number of contracts is recalculated on every tick to always risk exactly your budget.

HARD Mode: Your stop moves with the entry. If the entry moves up 4 ticks, the stop also moves up 4 ticks. The distance stays constant, so your contract count stays constant. Use this when you want a fixed-distance stop that travels with the current price.

The Strategy & Chart Trader Panel

Your execution control center

The strategy injects a custom panel into NinjaTrader's Chart Trader. Every button in this panel is connected to your drawing tool. Here is a complete breakdown of every control.

LONG / SHORT Button

This is your entry button. It automatically detects which direction your drawing tool is set to (long if entry is above stop, short if entry is below stop) and labels itself accordingly.

- **LONG (green):** Flat + long drawing tool detected. Click to enter long.
- **SHORT (red):** Flat + short drawing tool detected. Click to enter short.
- **LONG ACTIVE (dark):** You are in a long position. Button is disabled.
- **SHORT ACTIVE (dark):** You are in a short position. Button is disabled.
- **NO TOOL (gray):** No drawing tool found on the chart. Add the drawing tool first.

Entry Order Type (Strategy Setting)

Market: Fills immediately at current price. **LimitAtEntry:** Places a limit order at the drawing tool entry line price. Order is automatically cancelled if you remove the drawing tool or flip its direction.

MAGNET ON / MAGNET OFF

When MAGNET is ON (default), dragging your Stop Loss or Take Profit lines on the drawing tool while in a position will **automatically update your live orders** to match. Move the stop line → stop order moves. Move the TP line → TP order moves. When MAGNET is OFF, dragging the drawing tool does not affect live orders.

TP TARGET Selector

Choose which TP level is used for the bracket order:

- 1RR:** Uses the nearest TP line (TP1 = 1:1 risk/reward). Conservative target.
- Last RR:** Uses the final TP line (full profit ratio). E.g. TP3 at 3R. Default.
- NoTP:** No profit target is placed. Only a stop loss bracket. You exit manually.

NOTE

TP selector is locked while you are in a position. Select your TP level BEFORE pressing LONG/SHORT.

SECTION 07

Quick Buttons

Trade management while in a position

All buttons in the QUICK BUTTONS section are disabled when you are flat and enabled only while you have an open position. They let you manage the trade without touching the keyboard or order management windows.

BR

BREAKEVEN

Moves your Stop Loss to your exact entry fill price. Zero-risk trade. Also disables MAGNET so the drawing tool can't overwrite it.

CL

CLOSE POS

Closes your entire position at market immediately.

ST

STOP +N

Moves your Stop Loss N ticks further from entry (more room). N = SL Adjust Ticks setting (default: 4 ticks).

ST

STOP -N

Moves your Stop Loss N ticks closer to entry (tighter stop). Also disables MAGNET.

TP

TP +N

Moves your Take Profit N ticks further away (bigger target). N = TP Adjust Ticks setting (default: 4 ticks).

TP

TP -N

Moves your Take Profit N ticks closer to entry (lock in gains sooner). Also disables MAGNET.

CO

COVER X

Exits X contracts at market price (partial exit). X = Partial Exit Qty setting (default: 1). Bracket orders instantly update to the new position size.

IMPORTANT

STOP +N, STOP -N, TP +N, TP -N all automatically turn MAGNET OFF when pressed. This prevents the drawing tool from immediately overwriting your manual adjustment on the next tick.

Trade Timer (Stopwatch)

The STOPWATCH section shows how long your current trade has been open. It starts counting the moment your entry order fills. When you close the position, it stops and displays 'Last: HH:MM:SS' in gray so you can see your previous

trade's duration at a glance. Useful for tracking time-based trade management.

SECTION 08

Autopilot

Level-based automated trailing stop

Autopilot is the most advanced feature in the toolkit. It automatically moves your Stop Loss as price passes through the levels defined by your drawing tool — locking in profits progressively without any manual intervention.

How Autopilot Works

When Autopilot is active, the strategy builds a price ladder from your drawing tool:

SL → Entry → TP1 → TP2 → TP3 → Final TP

As price advances and touches each level (even just a wick), Autopilot moves the stop to a level behind the touched level. The stop can only move forward — never backward.

AGGRESSIVE Mode

Moves the stop to **1 level behind** the highest level price has touched:

IF PRICE TOUCHES...	STOP MOVES TO...
TP1 (1R)	Entry — breakeven
TP2 (2R)	TP1 — 1R locked in
TP3 (3R)	TP2 — 2R locked in

RUNNER Mode

Moves the stop to **2 levels behind** the highest touched level. Gives the trade more room to breathe and run further:

IF PRICE TOUCHES...	STOP MOVES TO...
TP1 (1R)	Still at original SL
TP2 (2R)	Entry — breakeven
TP3 (3R)	TP1 — 1R locked in

PRO TIP

Pre-arm: You can select AGGRESSIVE or RUNNER before entering the trade. Autopilot will activate automatically the moment your entry order fills.

Autopilot Rules

- ✓ The stop only moves toward profit — never back.
- ✓ Activating Autopilot automatically turns MAGNET OFF (Autopilot owns the stop).
- ✓ Pressing BREAK EVEN, STOP+, or STOP- disables Autopilot.
- ✓ Autopilot resets to OFF when the position closes.
- ✓ AGGRESSIVE and RUNNER are mutually exclusive (selecting one disables the other).
- ✓ Autopilot and Trail modes are mutually exclusive (selecting one disables the other).

SECTION 09

Trailing Stop

Two modes of automated stop trailing

In addition to Autopilot, the strategy offers two classic trailing stop modes. These are simpler than Autopilot and do not require multiple TP levels.

TRAIL xT — Tick Trail

Tick Trail (TRAIL xT)

xT

Tracks a high-water mark (the best price reached since activation). On every tick, if price beats the high-water mark, the stop is moved to: best price minus TrailTicks (long) or best price plus TrailTicks (short). The stop only moves forward. Default TrailTicks = 8 ticks. Configurable in strategy settings.

TRAIL xB — Bar Trail

Bar Trail (TRAIL xB)

xB

Places the stop at the lowest Low (for longs) or highest High (for shorts) of the last N bars. Recalculated on every tick. As new bars form and old lows are no longer in the lookback window, the stop naturally tightens. Default TrailBars = 3 bars. Configurable in strategy settings.

Trail Mode Rules

- ✓ Both trail modes are mutually exclusive (selecting one disables the other).
- ✓ Activating Trail automatically disables MAGNET (trail owns the stop).
- ✓ Activating MAGNET automatically disables trail.
- ✓ Trail modes and Autopilot are mutually exclusive.
- ✓ Trail state resets to OFF when the position closes.
- ✓ You can pre-arm trail mode before entering — it activates on entry fill.

WHICH TO USE?

Choosing between Autopilot and Trail:

Use AUTOPILOT when your drawing tool has clear TP levels and you want the stop to move to meaningful price levels (not arbitrary tick counts).

Use TRAIL xT when you want a simple fixed-distance trailing stop.

Use TRAIL xB when you want the stop to respect recent bar structure.

SECTION 10

Full Workflow

Everything working together

Here is a complete end-to-end example of how to use the drawing tool and strategy together for a typical trade:

1

Set your risk budget

In Drawing Tool settings: set Stop Loss Budget to your max dollar risk per trade (e.g. \$200). Enable Auto Order Qty. The tool will handle sizing automatically.

2

Choose your TP target

In the Chart Trader panel: select 1RR, Last RR, or NoTP BEFORE entering. This cannot be changed once you are in a position.

3

Draw your setup

Select the drawing tool. Click at your entry price, drag to your stop loss. The TP is calculated automatically. Read the FSL label: it shows your contract count and dollar risk.

4

Evaluate the setup

Check the RR ratio shown on the TP label. Check the contracts shown on the FSL. If the setup looks good, proceed. If not, drag the anchors to adjust or press FLIP.

5

Optional: select Autopilot

If you want automated profit protection, select AGGRESSIVE or RUNNER in the Autopilot section. It will activate on fill.

6

Press LONG or SHORT

Click the entry button. The strategy reads all prices from the drawing tool, submits your entry order, and immediately places the SL and TP bracket orders. You are in the trade.

7

Monitor and manage

Watch the trade. Use STOP +/- to adjust your stop. Use COVER to take partial profits. If Autopilot is running, the stop moves automatically as price advances.

8

Trade closes

When the TP fills, the SL is automatically cancelled. Or vice versa. The Stopwatch shows your trade duration. The system resets for the next trade.

SECTION 11

Scale-In & Native Buttons

Adding to positions

Adding to an Existing Position (Scale-In)

While in a position, you can add to it using NinjaTrader's native Chart Trader buy/sell buttons (Buy Mkt, Sell Mkt, Buy Ask, Buy Bid, Sell Ask, Sell Bid). The strategy intercepts these clicks and handles the additional entry intelligently.

SITUATION	WHAT HAPPENS
Flat, drawing tool present	Native button click → strategy entry at that price type.
Flat, no drawing tool	Native button click → passes through to NT8 normally.
In position, SAME direction	Native button click → adds contracts to the position. Bracket qty updates instantly.
In position, OPPOSITE dir	BLOCKED. Prevents accidental position reversal.

SCALE-IN

Scale-in is fully supported. Add 1 contract, then 2 more, then 3 more. The bracket orders (Stop Loss and Take Profit) are updated to cover the total position size instantly after every add-on fill — no manual adjustment needed.

Strategy Settings Reference

SETTING	DEFAULT	DESCRIPTION
Entry Order Type	Market	Market fill or Limit at drawing tool entry price.
TP Line Selection	LastTP	Which TP level the bracket uses: FirstTP (1R), LastTP (Final), NoTP.
Enable Live Sync	ON	Magnet sync: dragging the drawing tool updates live orders.
SL Adjust Ticks	4	How many ticks the STOP +/- buttons move the stop per click.
TP Adjust Ticks	4	How many ticks the TP +/- buttons move the target per click.
Partial Exit Qty	1	How many contracts the COVER button exits per press.
Trail Ticks	8	Tick distance for TRAIL xT (Tick Trail) mode.
Trail Bars	3	Lookback bars for TRAIL xB (Bar Trail) mode.
Print Debug	OFF	Enable detailed output to NT8 Output window for troubleshooting.

Top Tips for New Users

1. Start with Auto Order Qty OFF

Get comfortable drawing the tool and reading the labels before enabling auto-sizing. Once you understand how contract counts are shown on the FSL label, turn it on.

2. Use Show Buttons On Hover

Enabling this in PRO Settings keeps your chart clean. The button panel only appears when your mouse is over the drawing tool.

3. Pre-select your TP before entry

The TP selector is locked while in a position. Always check which target is active in the Chart Trader panel before pressing LONG or SHORT.

4. Use FLIP to quickly evaluate both sides

Draw a long setup, check the RR. Press FLIP, check the short RR. Take whichever side offers a better setup.

5. Stop Track On Fill is your friend

Enable this in PRO Settings when using AUTO TRACK. Your entry line follows the market for setup purposes, but stops tracking the moment you enter the trade.

6. COVER + Autopilot is a powerful combination

Press COVER to take partial profits at TP1, then let Autopilot trail the remaining position for the full run to Final TP.

Troubleshooting

Q: Button says "NO TOOL"

A: The strategy cannot find the drawing tool on the chart. Make sure you have drawn the Advanced Risk Reward tool (not the standard NT8 RR tool) on the same panel as the strategy.

Q: No bracket placed after entry

A: Check that both files are compiled (Tools > Edit NinjaScript > Compile). Also verify the strategy shows no errors in the NT8 Log window.

Q: Contract count seems wrong

A: Verify your Stop Loss Budget is set in the drawing tool settings, and Auto Order Qty is enabled. Check the FSL label — it shows exactly how many contracts and dollars.

Q: MAGNET is not syncing

A: Magnet only syncs while in a position. Also check that MAGNET shows ON in the panel and that Enable Live Sync is ON in strategy settings.

Q: Stop did not move with Autopilot

A: Autopilot moves the stop when price TOUCHES a level (high/low wick). If price only approached but did not touch, the stop will not move. Also verify Autopilot is ON (green indicator).

Thank you for using Advanced Risk Reward. This toolkit was built with care to give traders a professional-grade risk management and execution system.

CREATED BY

Luis Fernando Garrido Miranda

X (Twitter): @iluisgm

Built with Claude Sonnet by Anthropic

DONATE — if this tool saves you time or money

PayPal: lfgm00

USDT ERC-20: 0xEF0E0eFe33bE9487ca1D017Ceb5b1C70a3bf36BC

Inspired by the Risk Reward tool of YosewCapital and the Advanced Risk Reward tool by Bruno Meza.

DISCLAIMER: Any investments, trades and/or speculations made using this tool are done solely at your own risk. Past results do not guarantee future performance. This tool is for informational and educational purposes only. Always trade responsibly.