FULL GUIDE

Sports Routing on the iPad

Hold the iPad sideways. This is the screen staff use during a game.

Live commit stays off until a manager turns it on. It cannot be turned on yet.


Program names in the pictures are from one evening. They change. The buttons do not.

1. How to open it

1 Home Assistant Companion, or Safari, signed in to the bar's Home Assistant.
2 Sidebar: **Sports Routing**.
3 Turn the iPad sideways. Landscape is the layout in these pictures.

AVAccess Matrix (favorites such as FOX Local) is a separate sidebar item and is not covered here.

2. How the screen is laid out



Football. Games in the middle. Displays on the right. Take is gray until a plan is ready.

What each part does

- **Bar** is the room name. The top right is **No route** until a plan is ready.
- **Live commit** would send the plan to the DirecTV boxes and the TVs. Leave it off. The yellow line says why.
- **Left rail.** DirecTV's sports, then **Guide**, **Now**, and **Sets**. Swipe. There is no permanent scrollbar.
- **Sources** (middle). League chips, then the games. On Guide, the channel list and search. On Now, every TV.
- **Displays** (right). **All 35 TVs**, **4 Programs**, **9 Programs**, **Pick TVs**, then any sets you saved. Only one is active.
- **Take** (bottom). Gray until a program and a destination are both chosen. The sentence above the button is the plan.

3. Sports

The game list comes from DirecTV for this bar (Greensboro, ZIP 27403, Bars and Restaurants). It is not filled from the TV guide.

- College football, NFL (Sunday Ticket numbers are high, such as **9558**), and college basketball (Duke on **612** in the pictures).
- NBA, including out-of-market games on NBA League Pass (a number such as **1204**).
- The other sports on the left rail, when DirecTV has games that day.
- Locals that can carry a game: **2** CBS, **8** FOX, **12** NBC, **45** ABC.


Under Sources, **All** shows every game in that sport. The other chips are the leagues. A card with no channel number is listed, but Take will not tune it. The list refreshes when the iPad opens the page, and about every 15 minutes.

4. Guide


Guide is the DirecTV Greensboro lineup staff can put on a TV. These are left out:

- Music-only channels (Music Choice, Sirius). Music video networks such as MTV stay.
- Pay-per-view and Hot Choice.
- Promo barkers (Audience Network).
- On-demand menus.
- A second copy of a station that already has its real channel number.


News, HBO, shopping, and the sports channels stay. **Now** and **Next** show on the main locals and sports channels (2, 8, 12, 45, 206, 209, 219, 245, 9554). If listings are more than six hours old, a banner says the channel list is all you have. Search by number or name still works.



Guide. CBS 2 is showing NCIS. Titles change through the day.



Search by name. HGTV is channel 229.



Search by the program on now. NCIS is on CBS 2.


5. Where the picture goes

All 35 TVs puts one game or channel on every TV. The summary names **ENC-01**, the first DirecTV box.

4 Programs. Tap this first, then up to four games or channels. First pick is ENC-01, second is ENC-02, and so on. The room is striped.

Pick	DirecTV box	TVs
1st	ENC-01	1, 5, 9, 13, 17, 21, 25, 29, 33
2nd	ENC-02	2, 6, 10, 14, 18, 22, 26, 30, 34
3rd	ENC-03	3, 7, 11, 15, 19, 23, 27, 31, 35
4th	ENC-04	4, 8, 12, 16, 20, 24, 28, 32


If you only pick two games, the other two boxes are left alone, and those TVs stay as they were. **9 Programs** is the same rule for nine boxes. TV 1 gets the first game, TV 2 the second, TV 10 the first game again.



Two games ready for 4 Programs.


6. Named sets of TVs

A set is a saved Pick TVs list with a name. It is not a split. Swipe to **Sets**, type a name, tap the TVs, and tap **Save**. You can save 8 sets. A TV can be in more than one set. The later Take wins on a shared TV. Deleting a set removes the button. It does not clear TVs that were already routed.



Editing Patio. TVs 8, 9, and 10 are in the set.


On Sports or Guide, tap one program, tap the set, tap **Take**. The summary names one DirecTV box, the program, the TVs in the set, and the channel. Other TVs stay as they were.



Duke selected, Patio selected, Take blue.

7. Take, and replacing a program


Take shows **DRY-RUN SUMMARY** and updates the on-screen status. With Live commit off, no box changes channel and no TV switches input. Read the summary, then tap **Dismiss**.




Dry-run summary for Duke on four TVs.

All 35, 4 Programs, and 9 Programs already know which box to use. A set or Pick TVs needs a free box, ENC-01 through ENC-10. If every TV you picked is already on the same box, Take reuses that box. Any TV that was on it but is not in your set turns off, because one box can only show one channel.

If the TVs are not already on one box, and every box is busy, Take stays gray. The line above it says **All DirecTV boxes are in use. Choose one to replace.** The middle column lists the programs that are on. Tap one. Take becomes **Replace**. Dismiss closes the list and leaves your game and set selected.



Replace sheet. Patio stays selected on the right. The 49ers are one of the programs you can replace.




After Replace: ENC-03 is Duke on Patio. The 49ers go off, including TVs that were on that game and are not in Patio.

Only the box you picked changes channel. The other programs stay. Until the yellow line is gone, treat every Take and Replace as a practice press.

8. Now, and what to leave alone

Now lists TVs 1 through 35. A TV with a plan shows the program and the channel. A TV with nothing planned says **Off**.



After a Take, the TVs you chose show the game. The others say Off.

Leave these alone

- Do not turn on **Live commit**.
- Do not expect the wall to change while the yellow line is showing.
- Do not hunt the guide for music-radio channels, pay-per-view, or on-demand menus.
- Do not Take a game card that has no channel number.

If the screen looks wrong

What you see	What it means
No games in this slate	Nothing in that sport for the loaded days. Try another sport, or Guide.
Guide listings unavailable	Channels are still there. Program titles are stale. Search by name or number.
Search returns nothing	Try the channel number, or clear the box. Titles change through the day.
Take stays gray	You still need a program and a destination. A set or Pick TVs also needs at least one TV.
Choose one to replace	All ten DirecTV boxes are in use. Tap the program that should go off, then Replace.
8 sets is the limit	Delete a set you do not use. Deleting the button does not change what the TVs are showing.