

Introduction:

Do you wish to link your application, with a SMS service?

doo.ae, offers you a SMS gateway service, **SMS API**, that lets you easily connect your applications, websites, or any programs that you have, regardless the programming language that have been used to developed it, with our SMS service, with our SMS service, that is distinctive, secure and high reliability, and you can customize it according to your data and your specifications, by your programming team, all this through a HTTP protocol.

Before you start!

- 1. It's important that you have few programming skills, before you start using the API.
- **2.** The testing cost is 0, because we offer a free trial messages when you open a new account.
 - If you want to try the API, we advise you to send scheduled messages, so you can check it through a Scheduled Messages page in your account at doo.ae website, then you can delete it and send a message, this will prevent you from losing messages from your account.
- **3.** When you send SMS Through API, you should write the reception mobile numbers in international format without leading 00 or +
- **4.** When you send SMS Through API, you should write mobiles numbers, that will receive the message, in international format without 00 or +
- **5.** You can specify the message sender "Sender Name", but it's **must be** first defined by us, and it's **must be** consists of letters and numbers, and finally the length of the send name **must be** 11 character or less.

Features doo.ae API:

Connecting to doo.ae API is very easy, you can do it using your own forms, which send data as POST, or send data through the URL as GET, note that if you want to send a large amounts of data, we recommend that you use the first method POST, cause the second method GET supports a certain small amount of data.

When you connect to doo.ae API, through HTTP protocol, the data of the message must be in the right format, for example, the Sender Name **must be** encoded with URL-Encoding, the message **must be** in Windows-1256 encoding before encrypted with required Unicode.

Important Note: Sender Name must be used in same format that been defined in doo.ae, so don't change the uppercase letters or lowercase letters in the of the Sender name, when you use it to send the message.

Let's start:

In order to use doo.ae API, you should have your own account in doo.ae website, and here is an explanation of the registration process, checking your balance, and how to request a recharging for your balance through a recharge form in the website.

1. Registration process:

You can register on doo.ae website through the following link: http://doo.ae/sms/registration.php, you'll get a free balance immediately, and then you can use your username & password to send SMS massages through our API.

2. Check your balance:

You can check your balance through doo.ae API balance, and it will be explained below, also you can check your balance from the website, after you logged in to your account, your balance is shown in the Send Form, in this format i.e. 70/100, which means you current balance is 70 points out of 100 points, which is your total balance.

Note: Points are deducted based on the length of sent messages, each point represents a message, and message length is calculated as follows:

- 1. Messages in English: if the length of message is 160 characters or less, only one point will be deducted, if the length is more than 160 characters, then one point will be deducted for every 158 characters of the message.
- 2. Messages in Arabic (or English & Arabic): if the length of message is 70 characters or less, only one point will be deducted, if the length is more than 160 characters, then one point will be deducted for every 67 characters of the message.

3. Balance Recharge:

After you login to your account in doo.ae, you can recharge your balance, through request recharge form, you can access it through balance recharge tab located in the left side menu.

Fill all the required data in the form, and we will recharge your account within two hours at most, after we verification the deposit of the request recharge.

Main Services in doo.ae API:

Doo.ae SMS API provides you with a group of URL's that's serve the sending SMS service, such as check send status, activate sender name, and send SMS of course. All those URL's consist of three main parts as follows:

- 1. The link of the process that you want to do.
- 2. Your mobile number and password.
- 3. The required parameters of the process.

Examples:

- 1 http://doo.ae/api/balance.php?mobile=97155555558password=123456
- 2. http://doo.ae/api/msgSend.php?mobile=97155555555558password=123456&numbers=97155555 5555&sender=sms%20Msg&msg=062706470644062700200648063306470644062700200628064 300200645063900200064006F006F002E00610065&timeSend=0&dateSend=0&applicationType=3

Important Note: after preparing URL for the required process, use it in the address bar of you internet browser, a number will be shown, indicates the result of the process.

1. Check Send Status:

http://doo.ae/api/sendStatus.php

This URL provides you with the possibility to check the sending process status in Doo.ae, so you know if you can send your SMS now or later.

1. Request (Parameters)

None.

2. Response (Results)

1: You can send the message now.

If the URL returns otherwise or nothing, this means you can't send now.

2. Forget Password

http://doo.ae/api/forgetPassword.php

This URL provides you with the possibility to retrieve your password back, in case you forget it.

1. Request (Parameters)

- mobile: your mobile number, as registered in Doo.ae.
- type: 1 or 2, 1 the password will be sent to your mobile number, while 2 means that
 the password will be sent to your email "in this case you should have been specified it
 in your Personal Info page at you account".

2. Response (Results)

- 1: Your mobile number is incorrect.
- 2: Your email is incorrect.
- 3: Password sent to mobile number successfully.
- 4: your account is not enough to send the new password as SMS.
- 5: Password sent to email successfully.

Examples:

- 1. http://doo.ae/api/forgetPassword.php?mobile=9715555555558type=1
- 2. http://doo.ae/api/forgetPassword.php?mobile=9715555555558type=2

3. Check your Balance

http://doo.ae/api/balance.php

This URL provides you with the possibility to check your balance, in any time.

1. Request (Parameters)

- mobile: your mobile number, as registered in Doo.ae.
- password: your password, as registered in Doo.ae.

2. Response (Results)

- 1: Your mobile number is incorrect.
- 2: Your Password is incorrect.
- 3: Your Account Key is incorrect.

Otherwise: your balance, for example: 70/100.

70 means that your current (available) balance is: 70 points.

100 means that your total (charged) balance is: 100 points.

Example:

http://doo.ae/api/balance.php?mobile=971555555558password=123456

4. Send SMS

http://doo.ae/api/msqSend.php

This URL provides you with the possibility to send SMS Messages.

1. Request (Parameters)

- mobile: vour mobile number, as registered in Doo.ae.
- password: your password, as registered in Doo.ae.
- numbers: the mobile number or set of mobiles numbers that the SMS message will be sent to them, each number must be in international format, without zeros or symbol (+), and separated from others by the symbol (,). If you send SMS through the URL as GET, in this case the maximum amount of numbers you can send to them is 120 numbers each time.
- sender: message sender.

Note: If Sent to Saudi or UAE mobiles, the sender must be defined from us.

• msg: message text, and must be in Unicode format.

Note: you can encode the message to Unicode, using convertToUnicode function, located in functionUnicode file, but if you use sendSMS function, the message will be encoded automatically.

- msgId: (optional) this parameter offers you the possibility to repeat sending the same SMS that have been sent before less than one hour; because doo.ae don't allow repeat sending the same SMS (same sender name, message text and numbers) until one hour from sending the first SMS, so if you want to repeat the same SMS in less than one hour you have to specify for msgId with the repeated SMS; and of course if you need to repeat the same SMS more than one time "in the same hour", specify a different value for msgId for each repeated SMS.
- dateSend: (optional) this parameter offers you the possibility to schedule the message sending in a certain date, it must be in the following format mm/dd/yyyy.

Note: in case you don't provide this parameter or set the value to 0, the message will be sent immediately, also if you set the value in past date or with a wrong format, the message will be sent immediately.

• timeSend: (optional) this parameter offers you the possibility to schedule the message sending in a certain time, it must be in the following format hh:mm:ss.

Note: in case you don't provide this parameter or set the value to 0, the message will be sent immediately, also if you set the value in past time or with a wrong format, the message will be sent immediately.

Finally, if you use the two parameters together, and one of them was wrong, the value will become 0, as in this example:

dateSend: 30/04/2013 timeSend: 13:52:00

dateSend is wrong, so the message will be sent at: 01:52 PM today.

2. Response (Results)

- -2: connection failed to Doo.ae server.
- -1: connection failed to Doo.ae Database.
- 1: SMS message sent successfully.
- 2: Your balance is 0.
- 3: Your balance is not enough.
- 4: Your mobile number is incorrect.
- 5: Your Password is incorrect.
- 6: Problem in the Send SMS Message API, Please try again.
- 13: Sender Name not accepted, or not authorized to you.
- 15: Number(s) is empty or incorrect.
- 16: Sender Name is empty.
- 17: Message encoded incorrectly.
- 18: Your Account Key is incorrect.

Examples:

Send SMS API, default parameters:

http://doo.ae/api/msgSend.php?mobile=97155555555558 password=123456 & numbers=9715555555558 sender=sms%20Msg&msg=062706470644062700200648063306470644062700200628064300200645063900200064006F006F002E00610065& applicationType=3

2. Send SMS API, all parameters:

http://doo.ae/api/msgSend.php?mobile=97155555558.password=123456&numbers=9715555555558.sender=sms%20Msg&msg=062706470644062700200648063306470644062700200628064300200645063900200064006F0006F002E00610065&timeSend=0&dateSend=0&applicationType=3&msgId=15174

3. Send Scheduled SMS, with Time & Date:

http://doo.ae/api/msgSend.php?mobile=971555555555558 password=123456 & numbers=97155555555558 sender=sms%20Msg&msg=062706470644062700200648063306470644062700200628064300200645063900200064006F006F002E00610065 & timeSend=17:30:00 & dateSend=12/03/2051 & applicationType=3

5. Send Formatted SMS

http://doo.ae/api/msgSendWK.php

This URL provides you with the possibility to send SMS Message Template, with variables & mobile numbers, and then the API will generate one SMS message to each number according to its variable(s).

Parameters Definitions:

SMS Template: Hi (1), your subscription will ends on (2).

Now, when you want to send a Formatted SMS to a group of numbers, each number's variables must be defined, those variables will replacing (1) & (2), in the SMS that will be sent to the number, and you can include those variables, in the parameter: **msgKey**, like this:

msgKey = "(1),*, name,@,(2),*, name2***" // encoded it with Unicode Function.

- (1), (2)...: the symbols where the values will be replaced with it.
- *: separate between the symbol and the value that will replace it.
- @: separate between each definition of the symbol and its value.
- ***: separate between each SMS definitions.

Eaxmple:

SMS Template: Hi (1), your subscription will ends on (2).

msgKey: (1) ,*, Ahmad ,@, (2) ,*, 31/12/2013 *** (1) ,*, Mohamed, @, (2) ,*, 01/11/2013

Numbers: the count of numbers must equal the count of messages in the msgKey, so we will use

two numbers in this example, they are: 55599999999 & 5559444444444.

The SMSs that will be sent, according to our example are:

SMS to 55599999999 will be: Hi Ahmad, your subscription will ends on 31/12/2013.

SMS to 555944444444 will be: Hi Mohamed, your subscription will ends on 01/11/2013.

1. Request (Parameters)

- mobile: your mobile number, as registered in Doo.ae.
- password: your password, as registered in Doo.ae.
- numbers: the mobile number or set of mobiles numbers that the SMS message will be sent to them, each number must be in international format, without zeros or symbol (+), and separated from others by the symbol (,). If you send SMS through the URL as GET, in this case the maximum amount of numbers you can send to them is 120 numbers each time.
- sender: message sender.

Note: If Sent to Saudi or UAE mobiles, the sender must be defined from us.

• msg: template message text, and must be in Unicode format.

Note: you can encode the message to Unicode, using convertToUnicode function, located in functionUnicode file, but if you use sendSMS function, the message will be encoded automatically.

- msgId: (optional) this parameter offers you the possibility to repeat sending the same SMS that have been sent before less than one hour; because doo.ae don't allow repeat sending the same SMS (same sender name, message text and numbers) until one hour from sending the first SMS, so if you want to repeat the same SMS in less than one hour you have to specify for msgId with the repeated SMS; and of course if you need to repeat the same SMS more than one time "in the same hour", specify a different value for msgId for each repeated SMS.
- msgKey: set of values that will replace the symbols in the template message text, pay attention
 that the symbols used here must match the symbols used in the template message text as well
 as the values count for a single message must be equal to the symbols count in the message
 text, as well as the values sets count should equal the numbers count, finally it must be in
 Unicode format.
- dateSend: (optional) this parameter offers you the possibility to schedule the message sending in a certain date, it must be in the following format mm/dd/vvvv.

Note: in case you don't provide this parameter or set the value to 0, the message will be sent immediately, also if you set the value in past date or with a wrong format, the message will be sent immediately.

• timeSend: (optional) this parameter offers you the possibility to schedule the message sending in a certain time, it must be in the following format hh:mm:ss.

Note: in case you don't provide this parameter or set the value to 0, the message will be sent immediately, also if you set the value in past time or with a wrong format, the message will be sent immediately.

Finally, if you use the two parameters together, and one of them was wrong, the value will become 0, as in this example:

dateSend: 30/04/2013 timeSend: 13:52:00

dateSend is wrong, so the message will be sent at: 01:52 PM today.

2. Response (Results)

- -2: connection failed to Doo.ae server.
- -1: connection failed to Doo.ae Database.
- 1: SMS message sent successfully.
- 2: Your balance is 0.
- 3: Your balance is not enough.
- 4: Your mobile number is incorrect.
- 5: Your Password is incorrect.
- 10: Values sets count does not equal numbers count.

- 15: Number(s) is empty or incorrect.
- 16: Sender Name is empty.
- 17: Message encoded incorrectly.
- 18: Your Account Key is incorrect.

Example:

 $\label{lem:http://doo.ae/api/msgSendWK.php?mobile=971555555558password=123456&numbers=971544498480,\\ 971535168327&sender=sms\%20Msg\&msg=06480644064A002006270645063100200627064406370627064062800200020002800310029000D0641064A002006270644063506410020002000280033002900D006480627064406340639062806290020002800340029\&msgKey=002800300029002C0023002C002800300029002C0040002C002800310029002C0023002C0645062D0645062F00200627062D0645062F00200627064002C00280030029002C0023002C00627064406230648062F00200627064406250628062F06270646002C0040002C002800330029002C0023002C0627064406230648064400200627064406250628062A062F06270626064A002C0040002C002800340029002C0023002C0038002A002A002A002800300029002C0023002C002800300029002C0023002C0023002C00627064406250628062A062F06270626064A002C0040002C002800310029002C0023002C002800330029002C0023002C00$

6. License Sender's Name in doo.ae

http://doo.ae/api/addSender.php

This URL provides you with the possibility to license your own sender name.

1. Request (Parameters)

- mobile: your mobile number, as registered in Doo.ae.
- password: your password, as registered in Doo.ae.
- sender: the sender name that you want to license.
- Type: 1 or 2, 1 means you want to license the sender's name to be used for sending SMS to UAEs mobile numbers, while 2 means the you want to license the sender's name to be used for sending SMS to KSAs mobile numbers, you should notice that the sender name must be a component of characters only (English letters and numbers), and the length of sender's name must not be more than 11 characters.

2. Response (Results)

- 1: Your mobile number is incorrect.
- 2: Your Password is incorrect.
- 3: Sender name is incorrect.
- Sender name already exists.
- 5: Mobile number not allowed as a sender name.
- 6: Process completed successfully (in case of characters sender's name).
- 7: Process failed, (in case of characters sender's name).
- 8: Your Account Key is incorrect.

Examples:

License sender's name for UAE's mobile numbers

http://doo.ae/api/addSender.php?mobile=97155555555&password=123456&sender=doo&type=1

License sender's name for KSA's mobile numbers

http://doo.ae/api/addSender.php?mobile=97155555555&password=123456&sender=doo&type=2

7. Get vour Senders Names from doo.ae

http://doo.ae/api/senderAvailability.php

This URL provides you with the possibility to get all your active senders names.

1. Request (Parameters)

- mobile: your mobile number, as registered in Doo.ae.
- Type: 1 or 2, 1 means UAE senders names, while 2 means KSA senders names, in case you didn't pass this parameter, you will get all your active senders names.

2. Response (Results)

- 1: Your mobile number is incorrect.
- 2: Your Account Key is incorrect.

Otherwise: your active senders names separated with (,).

Examples:

Get all active senders names in your account

http://doo.ae/api/senderAvailability.php?mobile=971555555555

Get all active senders names for UAE's mobile numbers

http://doo.ae/api/senderAvailability.php?mobile=9715555555555type=1

Get all active senders names for KSA's mobile numbers

http://doo.ae/api/senderAvailability.php?mobile=97155555555555type=2